Network Working Group Request for Comments: 4444 Category: Standards Track J. Parker, Ed. Axiowave Networks April 2006

Management Information Base for Intermediate System to Intermediate System (IS-IS)

Status of This Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Copyright Notice

Copyright (C) The Internet Society (2006).

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. Specifically, this document describes a MIB for the Intermediate System to Intermediate System (IS-IS) Routing protocol when it is used to construct routing tables for IP networks.

Table of Contents

1.	The Internet-Standard Management	Framework					2
2.	Overview						2
3.	Conventions						5
4.	Definition of IS-IS MIB						6
5.	IANA Considerations						96
6.	Acknowledgements						96
7.	Security Considerations						96
8.	Normative References						101
9.	Informative References						102

Parker Standards Track [Page 1]

1. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC 3410 [RFC3410].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].

2. Overview

This document describes a management information base for the Intermediate System to Intermediate System (IS-IS) Routing protocol, as described in ISO 10589 [ISO10589], when it is used to construct routing tables for IP networks, as described in RFC 1195 [RFC1195]. The objects are mainly derived from the Guidelines for Definition of Managed Objects (GDMO) definitions in ISO 10589 and from the GDMO definitions in ISO 10733 [ISO10733]. There are also additional objects for managing the IP-specific functionality of Integrated IS-IS operation.

This MIB imports definitions from SNMPv2-TC [RFC2579], SNMPv2-SMI [RFC2578], SNMPv2-CONF [RFC2580], SNMP-FRAMEWORK-MIB [RFC3411], DIFFSERV-MIB [RFC3289], IF-MIB [RFC2863], and INET-ADDRESS-MIB [RFC4001]. See the imports section of the MIB for the specific items imported.

This MIB defines some objects to manage Mesh Groups, described in [RFC2973], and a three-way handshake for point-to-point adjacencies, described in [RFC3373].

The IS-IS MIB defines the following objects:

System-Wide Attributes

- isisSystem

This table contains information specific to a single instance of the IS-IS protocol running on a router.

- isisManAreaAddr

This table includes area addresses that are manually configured, which are used to control the associations formed between Level 1 Intermediate Systems.

- isisAreaAddr

This table includes area addresses reported in relevant L1 LSPs.

- isisSummAddr

This table holds summary addresses configured for each Level 2 instance of the IS-IS protocol running on a router.

isisRedistributeAddr

This table provides criteria to decide whether a route should be leaked from L2 to L1 when Domain Wide Prefix leaking is enabled.

- isisRouter

This table holds the hostname and router ID for Intermediate Systems in the network.

- isisSysLevel

This table contains information specific to a domain (Level 2) or an area (Level 1) of the IS-IS protocol.

isisNextCircIndex

This scalar is used to provide a unique circuit index.

Circuit-specific Attributes

- isisCirc

This table contains information specific to a point-to-point or a broadcast interface in the system.

- isisCircLevel

This table contains information specific to Level 1 or Level 2 of an interface.

Counters

- isisSystemCounter

Counters in the System table, such as number of times we have wrapped a sequence counter on one of our Link State PDUs.

- isisCircuitCounter

Counters of events particular to a circuit, such as PDUs with an illegal value of the System ID field length.

- isisPacketCounter

Counts of IS-IS Protocol PDUs broken down into packet type.

Attributes associated with an Adjacency

- isisISAdj

This table contains information about adjacencies to routers maintained by the protocol. Entries in this table cannot be created by management action: they are established through the Hello protocol.

- isisISAdjAreaAddr

This table contains the set of Area Addresses of neighboring Intermediate Systems, as reported in IIH PDUs.

- isisISAdjIPAddr

This table contains the set of IP Addresses of neighboring Intermediate Systems, as reported in received IIH PDUs.

isisISAdjProtSupp

This table contains the set of protocols supported by neighboring Intermediate Systems, as reported in received IIH PDUs.

Attributes Associated with Addresses

- isisRA

The Reachable Address Table.

This table contains information about an address prefix manually configured on the system or learned through another protocol.

- isisIPRA

The IP Reachable Address Table.

This table contains information about an IP reachable address manually configured on this system or learned from another protocol.

Attributes Associated with Link State PDU Table

- isisLSPSummaryTable

The Link State PDU Summary Table.

This table contains information contained in the headers of Link State PDUs stored by the system.

- isisLSPTLVTable

The Link State PDU TLV Table.

This table holds the sequence of TLVs that make up an LSP fragment.

Attributes Associated with a Notification

- isisNotification

This table defines attributes that will be included when reporting IS-IS notifications.

3. Conventions

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "NOT RECOMMENDED", "MAY", and "OPTIONAL", when they appear in this document, are to be interpreted as described in BCP 14, RFC 2119 [RFC2119].

4. Definition of IS-IS MIB

```
ISIS-MIB DEFINITIONS ::= BEGIN
    TMPORTS
       TEXTUAL-CONVENTION, RowStatus, TruthValue, TimeStamp
               FROM SNMPv2-TC
                                           -- RFC2579
       MODULE-IDENTITY, OBJECT-TYPE, NOTIFICATION-TYPE,
           Unsigned32, Counter32, mib-2
               FROM SNMPv2-SMI
                                            -- RFC2578
       MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP
               FROM SNMPv2-CONF
                                           -- RFC2580
       SnmpAdminString
               FROM SNMP-FRAMEWORK-MIB
                                           -- RFC2571
       IndexInteger, IndexIntegerNextFree
               FROM DIFFSERV-MIB
                                            -- RFC3289
       InterfaceIndex
               FROM IF-MIB
                                            -- RFC2863
       InetAddressType, InetAddress, InetAddressPrefixLength
               FROM INET-ADDRESS-MIB; -- RFC3291
```

isisMIB MODULE-IDENTITY

LAST-UPDATED "200604040000Z" -- April 4, 2006, midnight ORGANIZATION "IETF IS-IS for IP Internets Working Group" CONTACT-INFO

"IS-IS for IP Internets working Group http://www.ietf.org/html.charters/isis-charter.html isis-wg@ietf.org

Jeff Parker Department of Computer Science Middlebury College, Middlebury, Vermont 05753 jeffp at middlbury dot edu"

DESCRIPTION

"This document describes a management information base for the IS-IS Routing protocol, as described in ISO 10589, when it is used to construct routing tables for IP networks, as described in RFC 1195.

This document is based on a 1994 IETF document by Chris Gunner. This version has been modified to include current syntax, to exclude portions of the protocol that are not relevant to IP, and to add management support for current practice.

```
Copyright (C) The Internet Society (2006). This version
            of this MIB module is part of RFC 4444; see the RFC
            itself for full legal notices."
       REVISION "200604040000Z" -- April 4, 2006, midnight
        DESCRIPTION
            "Initial version, published as RFC 4444."
    ::= \{ mib-2 138 \}
-- Top-level structure of the MIB
isisNotifications          OBJECT IDENTIFIER ::= { isisMIB 0 }
                   OBJECT IDENTIFIER ::= { isisMIB 1 }
isisObjects
isisConformance
                      OBJECT IDENTIFIER ::= { isisMIB 2 }
-- OBJECT IDENTIFIER definitions
-- System wide attributes.
isisSystem OBJECT IDENTIFIER ::= { isisObjects 1 }
-- Attributes associated with the domain or with the area.
isisSysLevel OBJECT IDENTIFIER ::= { isisObjects 2 }
-- Attributes associated with one Circuit
isisCirc OBJECT IDENTIFIER ::= { isisObjects 3 }
-- Attributes associated with area or domain relevant within a Circuit.
isisCircLevelValues OBJECT IDENTIFIER ::= { isisObjects 4 }
-- System and circuit counters.
isisCounters OBJECT IDENTIFIER ::= { isisObjects 5 }
-- Attributes associated with an adjacent Protocol Peer.
isisISAdj OBJECT IDENTIFIER ::= { isisObjects 6 }
-- Attributes associated with a configured address.
isisReachAddr OBJECT IDENTIFIER ::= { isisObjects 7 }
-- Attributes associated with IP routes learned by
-- configuration or through another protocol.
isisIPReachAddr OBJECT IDENTIFIER ::= { isisObjects 8 }
-- The collection of Link State PDUs known to the Intermediate System
isisLSPDataBase OBJECT IDENTIFIER ::= { isisObjects 9 }
-- Objects included in Notifications.
isisNotification OBJECT IDENTIFIER ::= { isisObjects 10 }
```

Parker Standards Track [Page 7]

```
-- Type definitions
    IsisOSINSAddress ::= TEXTUAL-CONVENTION
        STATUS current
       DESCRIPTION
            "OSI Network Service Address, e.g., NSAP, SNPA, or Network
             Entity Title"
        SYNTAX OCTET STRING (SIZE(0..20))
    IsisSystemID ::= TEXTUAL-CONVENTION
       STATUS current
        DESCRIPTION
            "The ID for an Intermediate System. This should
            be unique within a network, and is included
             in all PDUs originated by an Intermediate System.
             The protocol does not place any meanings upon
             the bits, other than using ordering to break
             ties in electing a Designated IS on a LAN."
       REFERENCE "{ISIS.aoi systemId (119)}"
        SYNTAX OCTET STRING (SIZE(6))
    IsisLinkStatePDUID ::= TEXTUAL-CONVENTION
        STATUS current
       DESCRIPTION
            "The 8-byte Link State PDU (LSP) ID,
             consisting of the 6-byte SystemID of the
             originating IS; a one-byte PseudoNode ID,
             which is 0 unless the LSP represents the
             topology of a LAN; and a one-byte LSP
             fragment number that is issued in sequence,
             starting with 0. Non-zero PseudoNode IDs
             need to be unique to the IS but need not
             match the IfIndex."
        REFERENCE "{See section 9.8 of ISO 10589}"
        SYNTAX OCTET STRING (SIZE(8))
    IsisAdminState ::= TEXTUAL-CONVENTION
        STATUS current
       DESCRIPTION
            "Type used in enabling and disabling a row."
        SYNTAX INTEGER
               on(1),
               off(2)
            }
   IsisLSPBuffSize ::= TEXTUAL-CONVENTION
       DISPLAY-HINT "d"
```

```
STATUS current
   DESCRIPTION
        "Integer sub-range for maximum LSP size."
   SYNTAX Unsigned32 (512..16000)
IsisLevelState ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
        "States of the IS-IS protocol."
   SYNTAX INTEGER
       {
           off (1),
           on (2),
           waiting (3),
           overloaded(4)
        }
IsisSupportedProtocol ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
        "Types of network protocol supported by Integrated IS-IS.
        The values for ISO8473 and IP are those registered for
        these protocols in ISO TR9577."
   REFERENCE "{See section 5.3.1 of RFC 1195}"
   SYNTAX INTEGER
       {
           iso8473(129),
           ipV6(142),
           ip(204)
        }
IsisDefaultMetric ::= TEXTUAL-CONVENTION
   DISPLAY-HINT "d"
   STATUS current
   DESCRIPTION
        "Integer sub-range for default metric for single hop.
        ISO 10589 provides for 4 types of metric. Only the
         'default' metric is used in practice."
   REFERENCE "{See section 7.2.2 of ISO 10589}"
   SYNTAX Unsigned32 (0..63)
IsisWideMetric ::= TEXTUAL-CONVENTION
   DISPLAY-HINT "d"
   STATUS current
   DESCRIPTION
        "Wide metric for IS Neighbors. ISO 10589 provides a
        6-bit metric. Traffic Engineering extensions provide
        24-bit metrics."
```

```
REFERENCE "{See section 3 of RFC 3784}"
    SYNTAX Unsigned32 (0..16777215)
IsisFullMetric ::= TEXTUAL-CONVENTION
   DISPLAY-HINT "d"
   STATUS current
   DESCRIPTION
        "Full metric for IP Routes. Traffic Engineering extensions
        provide 32-bit metrics."
   REFERENCE "{See section 4 of RFC 3784}"
    SYNTAX Unsigned32
IsisMetricType ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
       "Is this an Internal or External Metric?"
   REFERENCE "{See section 7.2.2 of ISO 10589}"
   SYNTAX INTEGER
           internal(1),
           external(2)
        }
IsisMetricStyle ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
        "Do we use RFC 1195 style metrics or wide metrics?"
   REFERENCE "{See section 5 of RFC 3787}"
    SYNTAX INTEGER
        {
           narrow(1),
           wide(2),
           both(3)
IsisISLevel ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
        "Identifies a level."
   REFERENCE "{See definitions 3.6.1 and 3.6.11 of ISO 10589}"
    SYNTAX INTEGER
                          -- L1
           area(1),
           domain(2)
                           -- L2
        }
IsisLevel ::= TEXTUAL-CONVENTION
   STATUS current
```

Parker Standards Track [Page 10]

```
DESCRIPTION
       "Identifies one or more levels."
   REFERENCE "{See definitions 3.6.1 and 3.6.11 of ISO 10589}"
   SYNTAX INTEGER
       {
           level1(1),
           level2(2),
           levelland2(3)
        }
IsisPDUHeader ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
        "A block to contain the header from a PDU."
   SYNTAX OCTET STRING (SIZE(0..64))
IsisCircuitID ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
       "ID for a circuit."
   REFERENCE "{See section 7.2.7 of ISO 10589}"
   SYNTAX OCTET STRING (SIZE(0 | 7))
IsisISPriority ::= TEXTUAL-CONVENTION
   DISPLAY-HINT "d"
   STATUS current
   DESCRIPTION
        "Integer sub-range for IS-IS priority."
   REFERENCE "{See section 9.5 of ISO 10589}"
   SYNTAX Unsigned32 (0..127)
IsisUnsigned16TC ::= TEXTUAL-CONVENTION
   DISPLAY-HINT "d"
   STATUS current
   DESCRIPTION
        "An Unsigned32 further restricted to 16 bits. Note that
        the ASN.1 BER encoding may still require 24 bits for
         some values."
   SYNTAX Unsigned32 (0..65535)
IsisUnsigned8TC ::= TEXTUAL-CONVENTION
   DISPLAY-HINT "d"
   STATUS current
   DESCRIPTION
        "An Unsigned32 further restricted to 8 bits. Note that
        the ASN.1 BER encoding may still require 16 bits for
         some values."
   SYNTAX Unsigned32 (0..255)
```

```
-- Behavior Definitions
-- ResettingTimer behavior definition
-- "This behavior applies to objects that specify the interval
-- between events in the operation of the protocol state machine.
-- If the value of such an object is set to a new value while
-- the protocol state machine is in operation, the implementation
-- shall take the necessary steps to ensure that for any time
-- interval that was in progress when the value of the
-- corresponding object was changed, the next expiration of that
-- interval takes place the specified time after the original
-- start of that interval, or immediately, whichever is later.
-- The precision with which this time shall be implemented shall
-- be the same as that associated with the basic operation of
-- the timer object."
-- ReplaceOnlyWhileDisabled behavior definition
-- "This behavior applies to objects that may not be modified
-- while the corresponding table row's variable of type
-- IsisAdminState is in state on."
-- ManualOrAutomatic behavior definition
-- "This behavior applies to objects that are read-write
-- if the object was created manually. Objects that were
-- created automatically that have this behavior are
-- read-only.
    isisSysObject OBJECT IDENTIFIER ::= { isisSystem 1 }
    isisSysVersion OBJECT-TYPE
       SYNTAX INTEGER
           {
               unknown(0),
               one(1)
            }
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The version number of the IS-IS protocol that
            is implemented."
        REFERENCE "{ISIS.aoi version (1)}"
        DEFVAL { one }
    ::= { isisSysObject 1 }
    isisSysLevelType OBJECT-TYPE
       SYNTAX IsisLevel
```

```
MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "At which levels is the Intermediate System
        running? This object may not be modified when
        the isisSysAdminState variable is in state 'on'
        for this Intermediate System.
        Configured values MUST survive an agent reboot."
   REFERENCE "{ISIS.aoi iSType (2)}"
   DEFVAL { level1and2 }
::= { isisSysObject 2 }
isisSysID OBJECT-TYPE
   SYNTAX IsisSystemID
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "The ID for this Intermediate System.
        This value is appended to each of the
        area addresses to form the Network Entity Titles.
        The derivation of a value for this object is
        implementation specific. Some implementations may
        automatically assign values and not permit an
        SNMP write, while others may require the value
        to be set manually.
        Configured values MUST survive an agent reboot."
   REFERENCE "{ISIS.aoi systemId (119)}"
::= { isisSysObject 3 }
isisSysMaxPathSplits OBJECT-TYPE
   SYNTAX Unsigned32 (1..32)
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Maximum number of paths with equal routing metric value
        which it is permitted to split between. This object
        may not be modified when the isisSysAdminState variable
        is in state 'on' for this Intermediate System.
        Configured values MUST survive an agent reboot."
   REFERENCE "{ISIS.aoi maximumPathSplits (3)}"
   DEFVAL { 2 }
::= { isisSysObject 4 }
isisSysMaxLSPGenInt OBJECT-TYPE
   SYNTAX Unsigned32 (1..65235)
```

```
UNITS "seconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Maximum interval, in seconds, between generated LSPs
         by this Intermediate System. This object follows the ResettingTimer behavior. The value must be
         greater than any value configured for
         isisSysLevelMinLSPGenInt, and should be at least 300
         seconds less than isisSysMaxAge.
         Configured values MUST survive an agent reboot."
   REFERENCE "{ISIS.aoi maximumLSPGenerationInterval (6)}"
   DEFVAL { 900 }
::= { isisSysObject 5 }
isisSysPollESHelloRate OBJECT-TYPE
   SYNTAX IsisUnsigned16TC (1..65535)
   UNITS "seconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "The value, in seconds, to be used for the suggested ES
         configuration timer in ISH PDUs when soliciting the ES
         configuration.
         Configured values MUST survive an agent reboot."
   REFERENCE "{ISIS.aoi pollESHelloRate (13)}"
   DEFVAL { 50 }
::= { isisSysObject 6 }
isisSysWaitTime OBJECT-TYPE
   SYNTAX IsisUnsigned16TC (1..65535)
   UNITS "seconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Number of seconds to delay in state 'waiting' before
         entering the state 'on'. This object follows the
         ResettingTimer behavior.
         Configured values MUST survive an agent reboot."
    REFERENCE "{ISIS.aoi waitingTime (15)}"
   DEFVAL { 60 }
::= { isisSysObject 7 }
isisSysAdminState OBJECT-TYPE
   SYNTAX IsisAdminState
```

```
MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "The administrative state of this Intermediate
         System. Setting this object to the value 'on'
         when its current value is 'off' enables
         the Intermediate System.
         Configured values MUST survive an agent reboot."
   DEFVAL { off }
::= { isisSysObject 8 }
isisSysL2toL1Leaking OBJECT-TYPE
   SYNTAX TruthValue
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "If true, allow the router to leak L2 routes into L1.
         Configured values MUST survive an agent reboot."
   DEFVAL { false }
::= { isisSysObject 9 }
isisSysMaxAge OBJECT-TYPE
   SYNTAX IsisUnsigned16TC (350..65535)
   UNITS "seconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Value to place in RemainingLifeTime field of
        the LSPs we generate.
         This should be at least 300 seconds greater than
         isisSysMaxLSPGenInt.
         Configured values MUST survive an agent reboot."
   DEFVAL { 1200 }
::= { isisSysObject 10 }
isisSysReceiveLSPBufferSize OBJECT-TYPE
   SYNTAX IsisUnsigned16TC (1492..16000)
   UNITS "bytes"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Size of the largest buffer we are designed or
         configured to store. This should be at least
         as big as the maximum isisSysLevelOrigLSPBuffSize
         supported by the system.
```

If resources allow, we will store and flood LSPs

```
larger than isisSysReceiveLSPBufferSize, as this
            can help avoid problems in networks with different
            values for isisSysLevelOriqLSPBuffSize.
            Configured values MUST survive an agent reboot."
       DEFVAL { 1492 }
    ::= { isisSysObject 11 }
   isisSysProtSupported OBJECT-TYPE
       SYNTAX BITS {
                    iso8473 (0),
                    ipv4 (1),
                    ipv6 (2)
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "This attribute contains the set of protocols
             supported by this Intermediate System."
    ::= { isisSysObject 12 }
   isisSysNotificationEnable OBJECT-TYPE
       SYNTAX TruthValue
       MAX-ACCESS read-write
       STATUS current
       DESCRIPTION
            "If this object is set to true(1), then it enables
            the emission of IS-IS Notifications. If it is
            set to false(2), these notifications are not sent.
            Configured values MUST survive an agent reboot."
       DEFVAL { true }
    ::= { isisSysObject 13 }
-- The Level 1 Manual Area Address Table
   isisManAreaAddrTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisManAreaAddrEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "The set of manual area addresses configured on this
            Intermediate System.
            At least one row in which the value of
            isisManAreaAddrExistState is active must be present.
            The maximum number of rows in this table for
```

```
which the object isisManAreaAddrExistState has the
        value active is 3.
        An attempt to create more than 3 rows of
        isisManAreaAddrEntry with state 'active' in one
        instance of the IS-IS protocol should
        return inconsistentValue."
   REFERENCE "{ISIS.aoi manualAreaAddresses (10)}"
::= { isisSystem 2 }
isisManAreaAddrEntry OBJECT-TYPE
   SYNTAX IsisManAreaAddrEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "Each entry contains one area address manually configured
        on this system.
        Dynamically created rows MUST survive an agent reboot."
    INDEX { isisManAreaAddr }
::= { isisManAreaAddrTable 1 }
IsisManAreaAddrEntry ::=
   SEQUENCE {
       isisManAreaAddr
           IsisOSINSAddress,
       isisManAreaAddrExistState
           RowStatus
        }
isisManAreaAddr OBJECT-TYPE
   SYNTAX IsisOSINSAddress
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
       "A manually configured area address for this system.
        Note: An index for the entry {1, {49.0001} active} in
        this table would be the ordered pair
        (1, (0x03 0x49 0x00 0x01)), as the length of an octet
        string is part of the OID."
::= { isisManAreaAddrEntry 1 }
isisManAreaAddrExistState OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
```

```
"The state of the isisManAreaAddrEntry. If the
            isisSysAdminState for this Intermediate System is 'on' and
            an attempt is made to set this object to the value
             'destroy' or 'notInService' when this is the only
             isisManAreaAddrEntry in state 'active' for this
             Intermediate System should return inconsistentValue.
            A row entry cannot be modified when the value of this
             object is 'active'."
    ::= { isisManAreaAddrEntry 2 }
-- The Level 1 Area Address Table
-- The Level 1 Area Address Table contains the
-- union of the sets of relevant area addresses configured
-- or learned from Level 1 LSPs received by this Intermediate System.
   isisAreaAddrTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisAreaAddrEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "The union of the sets of area addresses reported in all
            Level 1 LSPs with fragment number zero generated by this
            Intermediate System, or received from other Intermediate
            Systems that are reachable via Level 1 routing."
       REFERENCE "{ISIS.aoi areaAddresses (18)}"
    ::= { isisSystem 3 }
   isisAreaAddrEntry OBJECT-TYPE
       SYNTAX IsisAreaAddrEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Each entry contains one area address reported in a
            Level 1 LSP generated or received by this Intermediate
            System.
            Dynamically learned rows do not survive an agent reboot."
        INDEX { isisAreaAddr }
    ::= { isisAreaAddrTable 1 }
   IsisAreaAddrEntry ::=
       SEQUENCE {
           isisAreaAddr
               IsisOSINSAddress
```

```
isisAreaAddr OBJECT-TYPE
       SYNTAX IsisOSINSAddress
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "An area address reported in a Level 1 LSP."
    ::= { isisAreaAddrEntry 1 }
-- The Summary Address Table
-- The Summary Address Table contains the set of summary
-- addresses manually configured for the Intermediate System.
-- This is used to control leaking L1 routes into L2.
    isisSummAddrTable OBJECT-TYPE
        SYNTAX SEQUENCE OF IsisSummAddrEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "The set of IP summary addresses to use in forming
             summary TLVs originated by this Intermediate System.
             An administrator may use a summary address to combine
             and modify IP Reachability announcements. If the
             Intermediate system can reach any subset of the summary
             address, the summary address MUST be announced instead,
             at the configured metric."
    ::= { isisSystem 4 }
    isisSummAddrEntry OBJECT-TYPE
        SYNTAX IsisSummAddrEntry
       MAX-ACCESS not-accessible
        STATUS current
       DESCRIPTION
            "Each entry contains one IP summary address.
             Dynamically created rows MUST survive an agent reboot.
             Implementers need to be aware that if the total number
             of elements (octets or sub-identifiers) in
             isisSummAddress and isisSummAddrPrefixLen is too great,
             then OIDs of column instances in this table will have
             more than 128 subidentifiers and cannot be accessed
             using SNMPv1, SNMPv2c, or SNMPv3."
        INDEX { isisSummAddressType,
                isisSummAddress,
                isisSummAddrPrefixLen }
```

```
::= { isisSummAddrTable 1 }
IsisSummAddrEntry ::=
   SEQUENCE {
       isisSummAddressType
            InetAddressType,
        isisSummAddress
            InetAddress,
       isisSummAddrPrefixLen
           InetAddressPrefixLength,
        isisSummAddrExistState
           RowStatus,
       isisSummAddrMetric
           IsisDefaultMetric,
       isisSummAddrFullMetric
           IsisFullMetric
    }
isisSummAddressType OBJECT-TYPE
   SYNTAX InetAddressType
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The Type of IP address for this summary address."
::= { isisSummAddrEntry 1 }
isisSummAddress OBJECT-TYPE
   SYNTAX InetAddress
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The IP Address value for this summary address.
         The address must not contain any set host bits
         (bits set after the address prefix determined by
         isisSummAddrPrefixLen).
         The type of this address is determined by the value of
         the isisSummAddressType object."
::= { isisSummAddrEntry 2 }
isisSummAddrPrefixLen OBJECT-TYPE
   SYNTAX InetAddressPrefixLength
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The Length of the IP NetMask for this summary address.
         The values for the index objects isisSummAddress and
```

```
isisSummAddrPrefixLen must be consistent. When the value
             of isisSummAddress (excluding the zone index, if one
             is present) is x, then the bitwise logical-AND
             of x with the value of the mask formed from the
             corresponding index object isisSummAddrPrefixLen MUST be
             equal to x. If not, then the index pair is not
             consistent, and an inconsistentName error must be
             returned on SET or CREATE requests."
    ::= { isisSummAddrEntry 3 }
    isisSummAddrExistState OBJECT-TYPE
        SYNTAX RowStatus
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
            "The existence state of this summary address. Support
             for 'createAndWait' and 'notInService' is not required.
             A row entry cannot be modified when the value of this
             object is 'active'."
    ::= { isisSummAddrEntry 4 }
    isisSummAddrMetric OBJECT-TYPE
       SYNTAX IsisDefaultMetric
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
            "The metric value to announce this summary
            address within LSPs generated by this system."
       DEFVAL { 20 }
    ::= { isisSummAddrEntry 5 }
    isisSummAddrFullMetric OBJECT-TYPE
        SYNTAX IsisFullMetric
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
            "The wide metric value to announce this summary
             address within LSPs generated by this system."
       DEFVAL { 20 }
    ::= { isisSummAddrEntry 6 }
-- The Redistribution table defines addresses that should be
-- leaked from L2 to L1 if isisSysL2toL1Leaking is enabled.
    isisRedistributeAddrTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisRedistributeAddrEntry
       MAX-ACCESS not-accessible
```

```
STATUS current
   DESCRIPTION
        "This table provides criteria to decide if a route should
        be leaked from L2 to L1 when Domain Wide Prefix leaking is
        enabled.
        Addresses that match the summary mask in the table MUST
        be announced at L1 by routers when isisSysL2toL1Leaking
        is enabled. Routes that fall into the ranges specified
        are announced as is, without being summarized. Routes
         that do not match a summary mask are not announced."
::= { isisSystem 5 }
isisRedistributeAddrEntry OBJECT-TYPE
   SYNTAX IsisRedistributeAddrEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "Each entry contains one configured IP summary
        address to manage leaking L2 addresses into L1.
        Dynamically created rows MUST survive an agent reboot.
         Implementers need to be aware that if the total number
        of elements (octets or sub-identifiers) in
        isisRedistributeAddrAddress and
        isisRedistributeAddrPrefixLen is too great, then OIDs
        of column instances in this table will have more than
        128 subidentifiers and cannot be accessed using SNMPv1,
        SNMPv2c, or SNMPv3."
    INDEX { isisRedistributeAddrType,
            isisRedistributeAddrAddress,
            isisRedistributeAddrPrefixLen }
::= { isisRedistributeAddrTable 1 }
IsisRedistributeAddrEntry ::=
   SEQUENCE {
       isisRedistributeAddrType
           InetAddressType,
        isisRedistributeAddrAddress
            InetAddress,
        isisRedistributeAddrPrefixLen
            InetAddressPrefixLength,
       isisRedistributeAddrExistState
           RowStatus
    }
isisRedistributeAddrType OBJECT-TYPE
```

```
SYNTAX InetAddressType
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The Type of IP address for this summary address."
::= { isisRedistributeAddrEntry 1 }
isisRedistributeAddrAddress OBJECT-TYPE
   SYNTAX InetAddress
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The IP Address value for this summary address.
        The type of this address is determined by the
        value of the isisRedistributeAddrType object.
        The address must not contain any set host bits -
        bits set after the address prefix determined by
        isisRedistributeAddrPrefixLen."
::= { isisRedistributeAddrEntry 2 }
isisRedistributeAddrPrefixLen OBJECT-TYPE
   SYNTAX InetAddressPrefixLength
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The Length of the IP NetMask for this summary address.
        The values for the index objects
        isisRedistributeAddrAddress and
         isisRedistributeAddrPrefixLen must be consistent.
        When the value of isisRedistributeAddrAddress
         (excluding the zone index, if one is present) is x,
         then the bitwise logical-AND of x with the value of
        the mask formed from the corresponding index object
        isisRedistributeAddrPrefixLen MUST be equal to x.
        If not, then the index pair is not consistent, and an
        inconsistentName error must be returned on SET or
        CREATE requests."
::= { isisRedistributeAddrEntry 3 }
isisRedistributeAddrExistState OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The existence state of this summary address. Support
```

```
for createAndWait and notInService is not required.
             A row entry cannot be modified when the value of this
             object is 'active'."
    ::= { isisRedistributeAddrEntry 4 }
-- The Router Table keeps track of hostnames and router IDs
-- associated with Intermediate Systems in the area and domain.
   isisRouterTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisRouterEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
           "The set of hostnames and router ID."
    ::= { isisSystem 6 }
   isisRouterEntry OBJECT-TYPE
       SYNTAX IsisRouterEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Each entry tracks information about one Intermediate
            System at one level.
             Dynamically learned rows do not survive an agent reboot."
        INDEX { isisRouterSysID,
                isisRouterLevel }
    ::= { isisRouterTable 1 }
   IsisRouterEntry ::=
       SEQUENCE {
           isisRouterSysID
               IsisSystemID,
           isisRouterLevel
               IsisISLevel,
            isisRouterHostName
               SnmpAdminString,
           isisRouterID
               Unsigned32
        }
   isisRouterSysID OBJECT-TYPE
       SYNTAX IsisSystemID
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "The System ID of the Intermediate System."
```

```
::= { isisRouterEntry 1 }
   isisRouterLevel OBJECT-TYPE
       SYNTAX IsisISLevel
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "The level at which the information about this
             Intermediate System was received."
    ::= { isisRouterEntry 2 }
   isisRouterHostName OBJECT-TYPE
       SYNTAX SnmpAdminString
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The hostname listed in the LSP, or a zero-length
             string if none."
    ::= { isisRouterEntry 3 }
   isisRouterID OBJECT-TYPE
       SYNTAX Unsigned32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The Router ID found in the LSP, or zero if none."
    ::= { isisRouterEntry 4 }
-- The System Level Table
-- This table captures level-specific information about the system
   isisSysLevelTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisSysLevelEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
           "Level specific information about the System."
    ::= { isisSysLevel 1 }
   isisSysLevelEntry OBJECT-TYPE
       SYNTAX IsisSysLevelEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Each row describes variables configured for Area or Domain.
             Configured values MUST survive an agent reboot."
       INDEX { isisSysLevelIndex }
```

```
::= { isisSysLevelTable 1 }
IsisSysLevelEntry ::=
   SEQUENCE {
       isisSysLevelIndex
            IsisISLevel,
        isisSysLevelOrigLSPBuffSize
           IsisLSPBuffSize,
       isisSysLevelMinLSPGenInt
           IsisUnsigned16TC,
        isisSysLevelState
           IsisLevelState,
        isisSysLevelSetOverload
           TruthValue,
        isisSysLevelSetOverloadUntil
           Unsigned32,
       isisSysLevelMetricStyle
           IsisMetricStyle,
        isisSysLevelSPFConsiders
           IsisMetricStyle,
       isisSysLevelTEEnabled
           TruthValue
    }
isisSysLevelIndex OBJECT-TYPE
   SYNTAX IsisISLevel
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The level that this entry describes."
::= { isisSysLevelEntry 1 }
isisSysLevelOrigLSPBuffSize OBJECT-TYPE
   SYNTAX IsisLSPBuffSize
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "The maximum size of LSPs and SNPs originated by
        this Intermediate System at this level. This
        object may not be modified when the isisSysAdminState
         variable is in state 'on' for this Intermediate System."
   REFERENCE "{ISIS.aoi originatingL1LSPBufferSize (9)}"
   DEFVAL { 1492 }
::= { isisSysLevelEntry 2 }
isisSysLevelMinLSPGenInt OBJECT-TYPE
   SYNTAX IsisUnsigned16TC (1..65535)
   UNITS "seconds"
```

```
MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Minimum interval, in seconds, between successive
        generation of LSPs with the same LSPID at this level
        by this Intermediate System."
   REFERENCE "{ISIS.aoi minimumLSPGenerationInterval (11)}"
   DEFVAL { 30 }
::= { isisSysLevelEntry 3 }
isisSysLevelState OBJECT-TYPE
   SYNTAX IsisLevelState
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The state of the database at this level.
        The value 'off' indicates that IS-IS is not active at
         this level.
        The value 'on' indicates that IS-IS is active at this
        level and is not overloaded.
        The value 'waiting' indicates a database that is low on
        an essential resource, such as memory.
        The administrator may force the state to 'overloaded'
        by setting the object isisSysLevelSetOverload.
        If the state is 'waiting' or 'overloaded', we
         originate LSPs with the overload bit set."
   REFERENCE "{ISIS.aoi l1State (17)}"
::= { isisSysLevelEntry 4 }
isisSysLevelSetOverload OBJECT-TYPE
   SYNTAX TruthValue
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Administratively set the overload bit for the level.
        The overload bit MUST continue to be set if the
        implementation runs out of memory, independent of
        this variable. It may also be set manually independent
        of this variable, using the isisSysLevelSetOverloadUntil
        object."
   DEFVAL { false }
::= { isisSysLevelEntry 5 }
isisSysLevelSetOverloadUntil OBJECT-TYPE
   SYNTAX Unsigned32
   UNITS "Seconds until clearing manually set Overload Bit"
   MAX-ACCESS read-write
   STATUS current
```

DESCRIPTION

"If this object is non-zero, the overload bit is set at this level when the isisSysAdminState variable goes to state 'on' for this Intermediate System. The overload bit remains set for isisSysLevelSetOverloadUntil seconds. When isisSysLevelSetOverloadUntil seconds have elapsed, the overload flag remains set if the implementation has run out of memory, or if it is set manually using the isisSysLevelSetOverload object.

If isisSysLevelSetOverload is false, the system clears the overload bit when isisSysLevelSetOverloadUntil seconds have elapsed, if the system has not run out of memory." ::= { isisSysLevelEntry 6 } isisSysLevelMetricStyle OBJECT-TYPE SYNTAX IsisMetricStvle MAX-ACCESS read-write STATUS current DESCRIPTION "Which style of metric do we generate in our LSPs at this level?" DEFVAL { narrow } ::= { isisSysLevelEntry 7 } isisSysLevelSPFConsiders OBJECT-TYPE SYNTAX IsisMetricStyle MAX-ACCESS read-write STATUS current DESCRIPTION "Which style of metric do we consider in our SPF computation at this level?" DEFVAL { narrow } ::= { isisSysLevelEntry 8 } isisSysLevelTEEnabled OBJECT-TYPE SYNTAX TruthValue MAX-ACCESS read-write STATUS current DESCRIPTION "Do we do Traffic Engineering at this level?" DEFVAL { false } ::= { isisSysLevelEntry 9 } -- Static to provide next CircIndex

isisNextCircIndex OBJECT-TYPE

SYNTAX IndexIntegerNextFree

```
MAX-ACCESS read-only
        STATUS current
       DESCRIPTION
            "This object is used to assist a management
             application in creating new rows in the
             isisCircTable. If it is possible to create
             a new instance of isisCircEntry, then this
             object will contain a non-zero value that
             is not in use as the index of any row in the
             isisCircTable. The network manager reads the
             value of this object and then (if the
             value read is non-zero) attempts to create
             the corresponding instance of isisCircEntry.
             If the set request fails with the code
             'inconsistentValue', then the process must be
             repeated; if the set request succeeds, then
             the agent will change the value of this object
             according to an implementation-specific
             algorithm."
    ::= { isisCirc 1 }
-- The Circuit Table
-- Each broadcast or point-to-point interface on the system
-- corresponds to one entry in the Circuit table. However, there
-- may be multiple X.25 DA circuit entries in the Circuit table
-- for a given X.25 interface.
    isisCircTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisCircEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "The table of circuits used by this
             Intermediate System."
    ::= { isisCirc 2 }
    isisCircEntry OBJECT-TYPE
        SYNTAX IsisCircEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "An isisCircEntry exists for each circuit configured
            for Integrated IS-IS on this system.
             Dynamically created rows MUST survive an agent reboot."
        INDEX { isisCircIndex }
    ::= { isisCircTable 1 }
```

```
IsisCircEntry ::=
   SEQUENCE {
        isisCircIndex
           IndexInteger,
        isisCircIfIndex
           InterfaceIndex,
        isisCircAdminState
            IsisAdminState,
        isisCircExistState
           RowStatus,
        isisCircType
           INTEGER,
        isisCircExtDomain
           TruthValue,
        isisCircLevelType
           IsisLevel,
        isisCircPassiveCircuit
           TruthValue,
        isisCircMeshGroupEnabled
           INTEGER,
        isisCircMeshGroup
           Unsigned32,
        isisCircSmallHellos
           TruthValue,
        isisCircLastUpTime
            TimeStamp,
        isisCirc3WayEnabled
           TruthValue,
        isisCircExtendedCircID
           Unsigned32
    }
isisCircIndex OBJECT-TYPE
    SYNTAX IndexInteger
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "An index used to uniquely identify this circuit.
        When creating a row in this table, the
         isisNextCircIndex object should be retrieved,
         and its value should be specified as the value
         of this index using a SET operation. A retrieved
         value of zero(0) indicates that no rows can be
         created at this time."
::= { isisCircEntry 1 }
isisCircIfIndex OBJECT-TYPE
   SYNTAX InterfaceIndex
```

```
MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The value of ifIndex for the interface to which this
        circuit corresponds. This object cannot be modified
        after creation."
::= { isisCircEntry 2 }
isisCircAdminState OBJECT-TYPE
   SYNTAX IsisAdminState
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The administrative state of the circuit."
   DEFVAL { off }
::= { isisCircEntry 3 }
isisCircExistState OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The existence state of this circuit. Setting the state
        to 'notInService' halts the generation and processing of
        IS-IS protocol PDUs on this circuit. Setting the state
        to destroy will also erase any configuration associated
        with the circuit. Support for 'createAndWait' and
        'notInService' is not required.
        A row entry cannot be modified when the value of this
        object is 'active'."
::= { isisCircEntry 4 }
isisCircType OBJECT-TYPE
   SYNTAX INTEGER
           broadcast(1),
           ptToPt(2),
           staticIn(3),
           staticOut(4),
           dA(5)
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The type of the circuit. This object follows the
        ReplaceOnlyWhileDisabled behavior. The type specified
        must be compatible with the type of the interface defined
```

```
by the value of isisCircIfIndex."
   REFERENCE "{ISIS.aoi type (33)}"
::= { isisCircEntry 5 }
isisCircExtDomain OBJECT-TYPE
   SYNTAX TruthValue
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "If true, suppress normal transmission of and
        interpretation of Intra-domain IS-IS PDUs on this
        circuit."
   REFERENCE "{ISIS.aoi externalDomain (46)}"
   DEFVAL { false }
::= { isisCircEntry 6 }
isisCircLevelType OBJECT-TYPE
   SYNTAX IsisLevel
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "Indicates which type of packets will be sent and
        accepted on this circuit. The values set will be
        saved, but the values used will be modified by
        the settings of isisSysLevelType. Thus, if the
        isisSysTpe is level2 and the isisCircLevelType
        for a circuit is level1, the circuit will not send
        or receive IS-IS packets. This object follows the
        ReplaceOnlyWhileDisabled behavior."
   DEFVAL { level1and2 }
::= { isisCircEntry 7 }
isisCircPassiveCircuit OBJECT-TYPE
   SYNTAX TruthValue
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "Should we include this interface in LSPs, even if
        it is not running the IS-IS Protocol?"
   DEFVAL { false }
::= { isisCircEntry 8 }
isisCircMeshGroupEnabled OBJECT-TYPE
   SYNTAX INTEGER
       {
           inactive(1),
           blocked(2),
            set(3)
```

```
MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "Is this port a member of a mesh group, or is it
        blocked? Circuits in the same mesh group act as a
        virtual multiaccess network. LSPs seen on one circuit
        in a mesh group will not be flooded to another circuit
        in the same mesh group."
   REFERENCE "{ RFC 2973 }"
   DEFVAL { inactive }
::= { isisCircEntry 9 }
isisCircMeshGroup OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "Circuits in the same mesh group act as a virtual
        multiaccess network. LSPs seen on one circuit in
        a mesh group will not be flooded to another circuit
        in the same mesh group. If isisCircMeshGroupEnabled
        is inactive or blocked, this value is ignored."
   REFERENCE "{ RFC 2973 }"
::= { isisCircEntry 10 }
isisCircSmallHellos OBJECT-TYPE
   SYNTAX TruthValue
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "Can we send unpadded hellos on LAN circuits? False
        means the LAN Hellos must be padded.
        Implementations should allow the administrator to read
        this value. An implementation need not be able to
        support unpadded hellos to be conformant."
    DEFVAL { false }
::= { isisCircEntry 11 }
isisCircLastUpTime OBJECT-TYPE
   SYNTAX TimeStamp
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "How long the circuit has been enabled, measured in
        hundredths of seconds since the last re-initialization
        of the network management subsystem; 0 if the
        circuit has never been 'on'."
```

```
::= { isisCircEntry 12 }
   isisCirc3WayEnabled OBJECT-TYPE
       SYNTAX TruthValue
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
            "Is this circuit enabled to run 3Way handshake?"
       DEFVAL { true }
    ::= { isisCircEntry 13 }
   isisCircExtendedCircID OBJECT-TYPE
       SYNTAX Unsigned32
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
            "The value to be used as the extended circuit ID in
            3Way handshake. This value is only used if
            isisCirc3WayEnabled is true, and it must be unique
            across all circuits on this IS."
    ::= { isisCircEntry 14 }
-- The Circuit Level Table
-- This table captures level-specific information about a circuit
   isisCircLevelTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisCircLevelEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Level specific information about circuits used by IS-IS."
    ::= { isisCircLevelValues 1 }
   isisCircLevelEntry OBJECT-TYPE
       SYNTAX IsisCircLevelEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "An isisCircLevelEntry exists for each level on
            each circuit configured for Integrated IS-IS on
            this system.
            Configured values MUST survive an agent reboot."
        INDEX { isisCircIndex,
                isisCircLevelIndex }
    ::= { isisCircLevelTable 1 }
   IsisCircLevelEntry ::=
```

```
SEQUENCE {
       isisCircLevelIndex
           IsisISLevel,
       isisCircLevelMetric
           IsisDefaultMetric,
        isisCircLevelWideMetric
           IsisWideMetric,
        isisCircLevelISPriority
           IsisISPriority,
        isisCircLevelIDOctet
           Unsigned32,
        isisCircLevelID
           IsisCircuitID,
       isisCircLevelDesIS
           IsisCircuitID,
        isisCircLevelHelloMultiplier
           Unsigned32,
       isisCircLevelHelloTimer
           Unsigned32,
        isisCircLevelDRHelloTimer
           Unsigned32,
       isisCircLevelLSPThrottle
           IsisUnsigned16TC,
        isisCircLevelMinLSPRetransInt
           Unsigned32,
       isisCircLevelCSNPInterval
           Unsigned32,
       isisCircLevelPartSNPInterval
           Unsigned32
    }
isisCircLevelIndex OBJECT-TYPE
   SYNTAX IsisISLevel
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
       "The level that this entry describes."
::= { isisCircLevelEntry 1 }
isisCircLevelMetric OBJECT-TYPE
   SYNTAX IsisDefaultMetric
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
       "The metric value of this circuit for this level."
   REFERENCE "{ISIS.aoi l1DefaultMetric (35)}"
   DEFVAL { 10 }
::= { isisCircLevelEntry 2 }
```

```
isisCircLevelWideMetric OBJECT-TYPE
   SYNTAX IsisWideMetric
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "The wide metric value of this circuit for this level."
   DEFVAL { 10 }
::= { isisCircLevelEntry 3 }
isisCircLevelISPriority OBJECT-TYPE
   SYNTAX IsisISPriority
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "The priority for becoming the LAN-Designated
        Intermediate System at this level."
   REFERENCE "{ISIS.aoi l2IntermediateSystemPriority (73)}"
   DEFVAL { 64 }
::= { isisCircLevelEntry 4 }
isisCircLevelIDOctet OBJECT-TYPE
   SYNTAX Unsigned32(0..255)
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "A one-byte identifier for the circuit selected by the
        Intermediate System.
        On point-to-point circuits, the value is used as the Local
        Circuit ID in point-to-point IIH PDUs transmitted on this
        circuit. In this case, values of isisCircLevelIDOctet do
        not need to be unique.
        For broadcast circuits, the value is used to generate the
        LAN ID that will be used if this Intermediate System is
        elected as the Designated IS on this circuit. The value
        is required to differ on LANs where the Intermediate System
         is the Designated Intermediate System."
::= { isisCircLevelEntry 5 }
isisCircLevelID OBJECT-TYPE
   SYNTAX IsisCircuitID
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "On a point-to-point circuit with a fully initialized
        adjacency to a peer IS, the value of this object is
        the circuit ID negotiated during adjacency initialization.
```

```
On a point to point circuit without such an adjacency,
        the value is the concatenation of the local system ID
        and the one-byte isisCircLevelIDOctet for this circuit,
        i.e., the value that would be proposed for the circuit ID.
        On other circuit types, the value returned is the zero-
         length OCTET STRING."
   REFERENCE "{ISIS.aoi ptPtCircuitID (51)}"
::= { isisCircLevelEntry 6 }
isisCircLevelDesIS OBJECT-TYPE
   SYNTAX IsisCircuitID
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The ID of the LAN-Designated Intermediate System
        on this circuit at this level. If, for any reason,
         this system is not partaking in the relevant
        Designated Intermediate System election process,
         then the value returned is the zero-length OCTET STRING."
   REFERENCE "{ISIS.aoi l2DesignatedIntermediateSystem (75)}"
::= { isisCircLevelEntry 7 }
isisCircLevelHelloMultiplier OBJECT-TYPE
   SYNTAX Unsigned32 (2..100)
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "This value is multiplied by the corresponding HelloTimer,
        and the result in seconds (rounded up) is used as the
        holding time in transmitted hellos, to be used by
        receivers of hello packets from this IS."
   REFERENCE "{ISIS.aoi iSISHelloTimer (45)}"
   DEFVAL { 10 }
::= { isisCircLevelEntry 8 }
isisCircLevelHelloTimer OBJECT-TYPE
   SYNTAX Unsigned32 (10..600000)
   UNITS "milliseconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Maximum period, in milliseconds, between IIH PDUs
        on multiaccess networks at this level for LANs.
        The value at L1 is used as the period between
        Hellos on L1L2 point-to-point circuits. Setting
        this value at level 2 on an L1L2 point-to-point
        circuit will result in an error of InconsistentValue.
```

```
This object follows the ResettingTimer behavior."
   REFERENCE "{ISIS.aoi iSISHelloTimer (45)}"
   DEFVAL { 3000 }
::= { isisCircLevelEntry 9 }
isisCircLevelDRHelloTimer OBJECT-TYPE
   SYNTAX Unsigned32 (10..120000)
   UNITS "milliseconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Period, in milliseconds, between Hello PDUs on
        multiaccess networks when this IS is the Designated
        Intermediate System. This object follows the
        ResettingTimer behavior."
   REFERENCE "{ISIS.aoi iSISHelloTimer (45)}"
   DEFVAL { 1000 }
::= { isisCircLevelEntry 10 }
isisCircLevelLSPThrottle OBJECT-TYPE
   SYNTAX IsisUnsigned16TC (1..65535)
   UNITS "milliseconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Minimal interval of time, in milliseconds, between
        transmissions of LSPs on an interface at this level."
   REFERENCE
        "{ISIS.aoi minimumBroadcastLSPTransmissionInterval (5)}"
   DEFVAL { 30 }
::= { isisCircLevelEntry 11 }
isisCircLevelMinLSPRetransInt OBJECT-TYPE
   SYNTAX Unsigned32 (1..300)
   UNITS "seconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
        "Minimum interval, in seconds, between re-transmission of
        an LSP at this level. This object follows the
        ResettingTimer behavior.
        Note that isisCircLevelLSPThrottle controls
        how fast we send back-to-back LSPs. This variable
        controls how fast we re-send the same LSP."
   REFERENCE "{ISIS.aoi minimumLSPTransmissionInterval (5)}"
   DEFVAL { 5 }
::= { isisCircLevelEntry 12 }
```

```
isisCircLevelCSNPInterval OBJECT-TYPE
       SYNTAX Unsigned32 (1..600)
       UNITS "seconds"
       MAX-ACCESS read-write
       STATUS current
       DESCRIPTION
            "Interval of time, in seconds, between periodic
            transmission of a complete set of CSNPs on
            multiaccess networks if this router is the
            designated router at this level.
            This object follows the ResettingTimer behavior."
       REFERENCE "{ISIS.aoi completeSNPInterval (8)}"
       DEFVAL { 10 }
    ::= { isisCircLevelEntry 13 }
   isisCircLevelPartSNPInterval OBJECT-TYPE
       SYNTAX Unsigned32 (1..120)
       UNITS "seconds"
       MAX-ACCESS read-write
       STATUS current
       DESCRIPTION
            "Minimum interval, in seconds, between sending Partial
            Sequence Number PDUs at this level. This object
            follows the ResettingTimer behavior."
       REFERENCE "{ISIS.aoi partialSNPInterval (14)}"
       DEFVAL { 2 }
    ::= { isisCircLevelEntry 14 }
-- isisSystemCounterTable keeps track of system-wide events.
   isisSystemCounterTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisSystemCounterEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
           "System-wide counters for this Intermediate System."
    ::= { isisCounters 1 }
   isisSystemCounterEntry OBJECT-TYPE
       SYNTAX IsisSystemCounterEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "System-wide IS-IS counters."
       INDEX { isisSysStatLevel }
    ::= { isisSystemCounterTable 1 }
   IsisSystemCounterEntry ::=
```

```
SEQUENCE {
       isisSysStatLevel
           IsisISLevel,
        isisSysStatCorrLSPs
            Counter32,
        isisSysStatAuthTypeFails
            Counter32,
        isisSysStatAuthFails
            Counter32,
        isisSysStatLSPDbaseOloads
            Counter32,
        isisSysStatManAddrDropFromAreas
            Counter32,
        \verb"isisSysStatAttmptToExMaxSeqNums"
            Counter32,
        isisSysStatSeqNumSkips
            Counter32,
        isisSysStatOwnLSPPurges
            Counter32,
        isisSysStatIDFieldLenMismatches
            Counter32,
        isisSysStatPartChanges
            Counter32,
        isisSysStatSPFRuns
            Counter32,
        isisSysStatLSPErrors
           Counter32
    }
isisSysStatLevel OBJECT-TYPE
   SYNTAX IsisISLevel
   MAX-ACCESS not-accessible
    STATUS current
   DESCRIPTION
        "The level that this entry describes."
::= { isisSystemCounterEntry 1 }
isisSysStatCorrLSPs OBJECT-TYPE
   SYNTAX Counter32
   UNITS "Number of corrupted in-memory frames"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "Number of corrupted in-memory LSPs detected.
         LSPs received from the wire with a bad checksum
         are silently dropped and are not counted.
```

```
LSPs received from the wire with parse errors
        are counted by isisSysStatLSPErrors."
   REFERENCE "{ISIS.aoi corruptedLSPsDetected (19)}"
::= { isisSystemCounterEntry 2 }
isisSysStatAuthTypeFails OBJECT-TYPE
   SYNTAX Counter32
   UNITS "Number of frames with authentication type mismatches"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of authentication type mismatches recognized
        by this Intermediate System."
::= { isisSystemCounterEntry 3 }
isisSysStatAuthFails OBJECT-TYPE
   SYNTAX Counter32
   UNITS "Number of frames with authentication key failures"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of authentication key failures recognized
        by this Intermediate System."
::= { isisSystemCounterEntry 4 }
isisSysStatLSPDbaseOloads OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "Number of times the LSP database has become
        overloaded."
   REFERENCE "{ISIS.aoi lSPL1DatabaseOverloads (20)}"
::= { isisSystemCounterEntry 5 }
isisSysStatManAddrDropFromAreas OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "Number of times a manual address has been dropped from
   REFERENCE "{ISIS.aoi manualAddressesDroppedFromArea (21)}"
::= { isisSystemCounterEntry 6 }
isisSysStatAttmptToExMaxSeqNums OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
```

```
STATUS current
   DESCRIPTION
        "Number of times the IS has attempted to exceed the
        maximum sequence number."
   REFERENCE
        "{ISIS.aoi attemptsToExceedmaximumSequenceNumber (22)}"
::= { isisSystemCounterEntry 7 }
isisSysStatSeqNumSkips OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "Number of times a sequence number skip has occurred."
   REFERENCE "{ISIS.aoi sequenceNumberSkips (23)}"
::= { isisSystemCounterEntry 8 }
isisSysStatOwnLSPPurges OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "Number of times a zero-aged copy of the system's own LSP
        is received from some other node."
   REFERENCE "{ISIS.aoi ownLSPPurges (24)}"
::= { isisSystemCounterEntry 9 }
isisSysStatIDFieldLenMismatches OBJECT-TYPE
   SYNTAX Counter32
   UNITS "Number of frames with ID length mismatches"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "Number of times a PDU is received with a different value
        for ID field length from that of the receiving system."
   REFERENCE "{ISIS.aoi iDFieldLengthMismatches (25)}"
::= { isisSystemCounterEntry 10 }
isisSysStatPartChanges OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "Partition changes."
::= { isisSystemCounterEntry 11 }
isisSysStatSPFRuns OBJECT-TYPE
   SYNTAX Counter32
```

```
MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Number of times we ran SPF at this level."
    ::= { isisSystemCounterEntry 12 }
   isisSysStatLSPErrors OBJECT-TYPE
       SYNTAX Counter32
       UNITS "Number of frames with errors that we have received"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Number of LSPs with errors we have received."
    ::= { isisSystemCounterEntry 13 }
-- isisCircuitCounterTable keeps track of events
-- specific to a circuit and a level
   isisCircuitCounterTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisCircuitCounterEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Circuit specific counters for this
             Intermediate System."
    ::= { isisCounters 2 }
   isisCircuitCounterEntry OBJECT-TYPE
       SYNTAX IsisCircuitCounterEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "An isisCircuitCounterEntry exists for each circuit
            used by Integrated IS-IS on this system."
       INDEX { isisCircIndex,
               isisCircuitType }
    ::= { isisCircuitCounterTable 1 }
   IsisCircuitCounterEntry ::= SEQUENCE {
          isisCircuitType
              INTEGER,
          isisCircAdjChanges
              Counter32,
          isisCircNumAdj
             Unsigned32,
          isisCircInitFails
             Counter32,
         isisCircRejAdjs
```

```
Counter32,
     isisCircIDFieldLenMismatches
         Counter32,
      isisCircMaxAreaAddrMismatches
          Counter32,
      isisCircAuthTypeFails
          Counter32,
      isisCircAuthFails
          Counter32,
      isisCircLANDesISChanges
         Counter32
   }
isisCircuitType OBJECT-TYPE
    SYNTAX INTEGER
       {
            lanlevel1(1),
           lanlevel2(2),
           p2pcircuit(3)
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "What type of circuit saw these counts?
         The point-to-point Hello PDU includes
         both L1 and L2, and ISs form a single
         adjacency on point-to-point links.
         Thus, we combine counts on
        point-to-point links into one group."
::= { isisCircuitCounterEntry 1 }
isisCircAdjChanges OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of times an adjacency state change has
         occurred on this circuit."
   REFERENCE "{ISIS.aoi changesInAdjacencyState (40)}"
::= { isisCircuitCounterEntry 2 }
isisCircNumAdj OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of adjacencies on this circuit."
```

```
REFERENCE "{ISIS.aoi changesInAdjacencyState (40)}"
::= { isisCircuitCounterEntry 3 }
isisCircInitFails OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of times initialization of this circuit has
        failed. This counts events such as PPP NCP failures.
        Failures to form an adjacency are counted by
        isisCircRejAdjs."
::= { isisCircuitCounterEntry 4 }
isisCircRejAdjs OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of times an adjacency has been rejected on
        this circuit."
   REFERENCE "{ISIS.aoi rejectedAdjacencies (42)}"
::= { isisCircuitCounterEntry 5 }
isisCircIDFieldLenMismatches OBJECT-TYPE
   SYNTAX Counter32
   UNITS "Number of frames with ID field length mismatch"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of times an IS-IS control PDU with an ID
        field length different from that for this system has been
        received."
   REFERENCE "{ISIS.aoi iDFieldLengthMismatches (25)}"
::= { isisCircuitCounterEntry 6 }
isisCircMaxAreaAddrMismatches OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of times an IS-IS control PDU with a
        max area address field different from that for this
        system has been received."
   REFERENCE "{ISIS.aoi iDFieldLengthMismatches (25)}"
::= { isisCircuitCounterEntry 7 }
isisCircAuthTypeFails OBJECT-TYPE
```

```
SYNTAX Counter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The number of times an IS-IS control PDU with
            an auth type field different from that for this
             system has been received."
    ::= { isisCircuitCounterEntry 8 }
    isisCircAuthFails OBJECT-TYPE
       SYNTAX Counter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The number of times an IS-IS control PDU with
             the correct auth type has failed to pass authentication
             validation."
    ::= { isisCircuitCounterEntry 9 }
    isisCircLANDesISChanges OBJECT-TYPE
        SYNTAX Counter32
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The number of times the Designated IS has changed
             on this circuit at this level. If the circuit is
             point to point, this count is zero."
    ::= { isisCircuitCounterEntry 10 }
-- isisPacketCounterTable keeps track of the number of IS-IS
-- control packets sent and received at each level
    isisPacketCounterTable OBJECT-TYPE
        SYNTAX SEQUENCE OF IsisPacketCounterEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Information about IS-IS protocol traffic at one level,
            on one circuit, in one direction."
    ::= { isisCounters 3 }
    isisPacketCounterEntry OBJECT-TYPE
        SYNTAX IsisPacketCounterEntry
       MAX-ACCESS not-accessible
       STATUS current
        DESCRIPTION
            "Information about IS-IS protocol traffic at one level,
            on one circuit, in one direction."
```

```
INDEX { isisCircIndex,
           isisPacketCountLevel,
            isisPacketCountDirection }
::= { isisPacketCounterTable 1 }
IsisPacketCounterEntry ::=
   SEQUENCE {
        isisPacketCountLevel
           IsisISLevel,
        isisPacketCountDirection
           INTEGER,
        isisPacketCountIIHello
           Counter32,
        isisPacketCountISHello
           Counter32,
        isisPacketCountESHello
           Counter32,
        isisPacketCountLSP
           Counter32,
        isisPacketCountCSNP
           Counter32,
        isisPacketCountPSNP
           Counter32,
        isisPacketCountUnknown
           Counter32
}
isisPacketCountLevel OBJECT-TYPE
   SYNTAX IsisISLevel
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
       "The level at which these PDU counts have been collected."
::= { isisPacketCounterEntry 1 }
isisPacketCountDirection OBJECT-TYPE
   SYNTAX INTEGER
           sending(1),
           receiving(2)
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "Were we sending or receiving these PDUs?"
::= { isisPacketCounterEntry 2 }
isisPacketCountIIHello OBJECT-TYPE
```

```
SYNTAX Counter32
   UNITS "Number of IS-IS Hellos frames seen in this direction
         at this level"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of IS-IS Hello PDUs seen in this
        direction at this level.
        Point-to-Point IIH PDUs are counted at
        the lowest enabled level: at L1 on L1 or L1L2 circuits,
        and at L2 otherwise."
   REFERENCE "{ISIS.aoi iSISControlPDUsSent (43)}"
::= { isisPacketCounterEntry 3 }
isisPacketCountISHello OBJECT-TYPE
   SYNTAX Counter32
   UNITS "Number of ES-IS frames seen in this direction at
        this level."
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of ES-IS Hello PDUs seen in this
        direction. ISH PDUs are counted at the
        lowest enabled level: at L1 on L1 or L1L2
        circuits, and at L2 otherwise."
::= { isisPacketCounterEntry 4 }
isisPacketCountESHello OBJECT-TYPE
   SYNTAX Counter32
   UNITS "Number of ES Hello frames seen in this direction at
        this level"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The number of ES Hello PDUs seen in this
        direction. ESH PDUs are counted at the
        lowest enabled level: at L1 on L1 or L1L2
        circuits, and at L2 otherwise."
::= { isisPacketCounterEntry 5 }
isisPacketCountLSP OBJECT-TYPE
   SYNTAX Counter32
   UNITS "Number of IS-IS LSP frames seen in this direction at
        this level"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
```

```
"The number of IS-IS LSPs seen in this
             direction at this level."
       REFERENCE "{ISIS.aoi iSISControlPDUsSent (43)}"
    ::= { isisPacketCounterEntry 6 }
    isisPacketCountCSNP OBJECT-TYPE
       SYNTAX Counter32
        UNITS "Number of IS-IS CSNP frames seen in this direction at
             this level"
       MAX-ACCESS read-only
       STATUS current
        DESCRIPTION
            "The number of IS-IS CSNPs seen in this
            direction at this level."
       REFERENCE "{ISIS.aoi iSISControlPDUsSent (43)}"
    ::= { isisPacketCounterEntry 7 }
    isisPacketCountPSNP OBJECT-TYPE
       SYNTAX Counter32
       UNITS "Number of IS-IS PSNP frames seen in this direction at
            this level"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The number of IS-IS PSNPs seen in this
             direction at this level."
        REFERENCE "{ISIS.aoi iSISControlPDUsSent (43)}"
    ::= { isisPacketCounterEntry 8 }
    isisPacketCountUnknown OBJECT-TYPE
       SYNTAX Counter32
       UNITS "Number of unknown IS-IS frames seen at this level"
       MAX-ACCESS read-only
        STATUS current
       DESCRIPTION
            "The number of unknown IS-IS PDUs seen
            at this level."
        REFERENCE "{ISIS.aoi iSISControlPDUsSent (43)}"
    ::= { isisPacketCounterEntry 9 }
-- The IS Adjacency Table
-- Each adjacency to an IS corresponds to one entry in this
-- table.
    isisISAdjTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisISAdjEntry
       MAX-ACCESS not-accessible
```

```
STATUS current
   DESCRIPTION
        "The table of adjacencies to Intermediate Systems."
::= { isisISAdj 1 }
isisISAdjEntry OBJECT-TYPE
    SYNTAX IsisISAdjEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "Each entry corresponds to one adjacency to an
         Intermediate System on this system.
        Dynamically learned rows do not survive an agent reboot."
    INDEX { isisCircIndex,
            isisISAdjIndex }
::= { isisISAdjTable 1 }
IsisISAdjEntry ::=
    SEQUENCE {
        isisISAdjIndex
           Unsigned32,
        isisISAdjState
            INTEGER,
        isisISAdj3WayState
            INTEGER,
        isisISAdjNeighSNPAAddress
           IsisOSINSAddress,
        isisISAdjNeighSysType
           INTEGER,
        isisISAdjNeighSysID
            IsisSystemID,
        isisISAdjNbrExtendedCircID
           Unsigned32,
        isisISAdjUsage
           IsisLevel,
        isisISAdjHoldTimer
            IsisUnsigned16TC,
        isisISAdjNeighPriority
            IsisISPriority,
        isisISAdjLastUpTime
            TimeStamp
  }
isisISAdjIndex OBJECT-TYPE
   SYNTAX Unsigned32(1..4294967295)
   MAX-ACCESS not-accessible
   STATUS current
```

```
DESCRIPTION
       "A unique value identifying the IS adjacency from all
        other such adjacencies on this circuit. This value is
         automatically assigned by the system when the adjacency
        is created."
::= { isisISAdjEntry 1 }
isisISAdjState OBJECT-TYPE
   SYNTAX INTEGER
        {
             down (1),
             initializing (2),
             up (3),
             failed(4)
        }
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
       "The state of the adjacency."
   REFERENCE "{ISIS.aoi adjacencyState (78)}"
::= { isisISAdjEntry 2 }
isisISAdj3WayState OBJECT-TYPE
   SYNTAX INTEGER
             up (0),
             initializing (1),
             down (2),
             failed (3)
        }
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The 3Way state of the adjacency. These are picked
         to match the historical on-the-wire representation
        of the 3Way state and are not intended to match
         isisISAdjState."
   REFERENCE "{ RFC 3373 }"
::= { isisISAdjEntry 3 }
isisISAdjNeighSNPAAddress OBJECT-TYPE
   SYNTAX IsisOSINSAddress
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The SNPA address of the neighboring system."
   REFERENCE "{ISIS.aoi neighbourSNPAAddress (79)}"
::= { isisISAdjEntry 4 }
```

```
isisISAdjNeighSysType OBJECT-TYPE
   SYNTAX INTEGER
       {
           11IntermediateSystem(1),
           12IntermediateSystem(2),
           11L2IntermediateSystem(3),
           unknown(4)
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The type of the neighboring system."
   REFERENCE "{ISIS.aoi neighbourSystemType (80)}"
::= { isisISAdjEntry 5 }
isisISAdjNeighSysID OBJECT-TYPE
   SYNTAX IsisSystemID
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The system ID of the neighboring Intermediate
         System."
   REFERENCE "{ISIS.aoi neighbourSystemIds (83)}"
::= { isisISAdjEntry 6 }
isisISAdjNbrExtendedCircID OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The 4-byte Extended Circuit ID learned from the
        Neighbor during 3-way handshake, or 0."
::= { isisISAdjEntry 7 }
isisISAdjUsage OBJECT-TYPE
   SYNTAX IsisLevel
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "How is the adjacency used? On a point-to-point link,
         this might be levelland2, but on a LAN, the usage will
         be level1 on the adjacency between peers at L1,
         and level2 for the adjacency between peers at L2."
   REFERENCE "{ISIS.aoi adjacencyUsage (82)}"
::= { isisISAdjEntry 8 }
isisISAdjHoldTimer OBJECT-TYPE
   SYNTAX IsisUnsigned16TC (1..65535)
```

UNITS "seconds"

```
MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The holding time, in seconds, for this adjacency.
            This value is based on received IIH PDUs and
             the elapsed time since receipt."
        REFERENCE "{ISIS.aoi holdingTimer (85)}"
    ::= { isisISAdjEntry 9 }
    isisISAdjNeighPriority OBJECT-TYPE
       SYNTAX IsisISPriority
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Priority of the neighboring Intermediate System for
            becoming the Designated Intermediate System."
       REFERENCE "{ISIS.aoi lANPriority (86)}"
    ::= { isisISAdjEntry 10 }
    isisISAdjLastUpTime OBJECT-TYPE
       SYNTAX TimeStamp
       MAX-ACCESS read-only
       STATUS current
        DESCRIPTION
            "When the adjacency most recently entered the state 'up',
            measured in hundredths of a second since the last
            re-initialization of the network management subsystem.
            Holds 0 if the adjacency has never been in state 'up'."
    ::= { isisISAdjEntry 11 }
-- The IS Adjacency Area Address Table
-- The IS Adjacency Area Address Table contains the set of
-- Area Addresses of neighboring
-- Intermediate Systems as reported in IIH PDUs.
    isisISAdjAreaAddrTable OBJECT-TYPE
        SYNTAX SEQUENCE OF IsisISAdjAreaAddrEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "This table contains the set of Area Addresses of
            neighboring Intermediate Systems as reported in received
             IIH PDUs."
        REFERENCE "{ISIS.aoi areaAddressesOfNeighbour (84)}"
    ::= { isisISAdj 2 }
```

```
isisISAdjAreaAddrEntry OBJECT-TYPE
        SYNTAX IsisISAdjAreaAddrEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Each entry contains one Area Address reported by a
             neighboring Intermediate System in its IIH PDUs.
             Dynamically learned rows do not survive an agent reboot."
        INDEX { isisCircIndex,
                isisISAdjIndex,
                isisISAdjAreaAddrIndex }
    ::= { isisISAdjAreaAddrTable 1 }
    IsisISAdjAreaAddrEntry ::=
        SEQUENCE {
           isisISAdjAreaAddrIndex
               Unsigned32,
            isisISAdjAreaAddress
               IsisOSINSAddress
            }
    isisISAdjAreaAddrIndex OBJECT-TYPE
       SYNTAX Unsigned32(1..4294967295)
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "An index for the areas associated with one neighbor.
            This provides a simple way to walk the table."
    ::= { isisISAdjAreaAddrEntry 1 }
    isisISAdjAreaAddress OBJECT-TYPE
       SYNTAX IsisOSINSAddress
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "One Area Address as reported in IIH PDUs received from
             the neighbor."
    ::= { isisISAdjAreaAddrEntry 2 }
-- The IS Adjacency IP Address Table
-- The IS Adjacency IP Address Table contains the
-- set of IP Addresses of neighboring Intermediate Systems
-- as reported in received IIH PDUs.
   isisISAdjIPAddrTable OBJECT-TYPE
        SYNTAX SEQUENCE OF IsisISAdjIPAddrEntry
```

```
MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "This table contains the set of IP Addresses of
        neighboring Intermediate Systems as reported in received
::= { isisISAdj 3 }
isisISAdjIPAddrEntry OBJECT-TYPE
   SYNTAX IsisISAdjIPAddrEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "Each entry contains one IP Address reported by a
        neighboring Intermediate System in its IIH PDUs.
        Dynamically learned rows do not survive an agent reboot."
   INDEX { isisCircIndex,
           isisISAdjIndex,
            isisISAdjIPAddrIndex
::= { isisISAdjIPAddrTable 1 }
IsisISAdjIPAddrEntry ::=
   SEQUENCE {
       isisISAdjIPAddrIndex
           Unsigned32,
       isisISAdjIPAddrType
            InetAddressType,
       isisISAdjIPAddrAddress
           InetAddress
    }
isisISAdjIPAddrIndex OBJECT-TYPE
   SYNTAX Unsigned32(1..4294967295)
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "An index to this table that identifies the IP addresses
        to which this entry belongs."
::= { isisISAdjIPAddrEntry 1 }
isisISAdjIPAddrType OBJECT-TYPE
   SYNTAX InetAddressType
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The type of one IP Address as reported in IIH PDUs
```

```
received from the neighbor."
    ::= { isisISAdjIPAddrEntry 2 }
    isisISAdjIPAddrAddress OBJECT-TYPE
        SYNTAX InetAddress
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "One IP Address as reported in IIH PDUs received from the
            neighbor.
             The type of this address is determined by the value of
             the isisISAdjIPAddrType object."
    ::= { isisISAdjIPAddrEntry 3 }
-- The IS Adjacency Protocol Supported Table
-- The IS Adjacency Protocol Supported Table contains the set of
-- protocols supported by neighboring
-- Intermediate Systems as reported in received IIH PDUs.
    isisISAdjProtSuppTable OBJECT-TYPE
        SYNTAX SEQUENCE OF IsisISAdjProtSuppEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "This table contains the set of protocols supported by
            neighboring Intermediate Systems as reported in received
            IIH PDUs."
    ::= { isisISAdj 4 }
    isisISAdjProtSuppEntry OBJECT-TYPE
        SYNTAX IsisISAdjProtSuppEntry
       MAX-ACCESS not-accessible
        STATUS current
       DESCRIPTION
            "Each entry contains one protocol supported by a
            neighboring Intermediate System as reported in its IIH
             PDUs.
             Dynamically learned rows do not survive an agent reboot."
        INDEX { isisCircIndex,
                 isisISAdjIndex,
                 isisISAdjProtSuppProtocol }
    ::= { isisISAdjProtSuppTable 1 }
   IsisISAdjProtSuppEntry ::=
       SEQUENCE {
```

```
isisISAdjProtSuppProtocol
               IsisSupportedProtocol
        }
    isisISAdjProtSuppProtocol OBJECT-TYPE
        SYNTAX IsisSupportedProtocol
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "One supported protocol as reported in IIH PDUs received
            from the neighbor."
    ::= { isisISAdjProtSuppEntry 1 }
-- The Reachable Address Group
-- The Reachable Address Table
-- Each entry records information about a reachable address
-- (NSAP or address prefix) manually configured on the system
-- or learned through another protocol.
    isisRATable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisRAEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "The table of Reachable Addresses to NSAPs or Address
             Prefixes."
    ::= { isisReachAddr 1 }
    isisRAEntry OBJECT-TYPE
       SYNTAX IsisRAEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Each entry defines a configured Reachable Address
             to an NSAP or Address Prefix.
            Dynamically created rows MUST survive an agent reboot."
        INDEX { isisCircIndex,
                isisRAIndex }
    ::= { isisRATable 1 }
    IsisRAEntry ::=
        SEQUENCE {
           isisRAIndex
               Unsigned32,
            isisRAExistState
               RowStatus,
```

```
isisRAAdminState
           IsisAdminState,
        isisRAAddrPrefix
           IsisOSINSAddress,
       isisRAMapType
           INTEGER,
        isisRAMetric
           IsisDefaultMetric,
       isisRAMetricType
           IsisMetricType,
        isisRASNPAAddress
           IsisOSINSAddress,
       isisRASNPAMask
           IsisOSINSAddress,
       isisRASNPAPrefix
           IsisOSINSAddress,
       isisRAType
           INTEGER
    }
isisRAIndex OBJECT-TYPE
   SYNTAX Unsigned32(1..4294967295)
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The identifier for this isisRAEntry. This value must be
        unique amongst all Reachable Addresses on the same parent
        Circuit."
::= { isisRAEntry 1 }
isisRAExistState OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The existence state of this Reachable Address. This
        object follows the ManualOrAutomatic behaviors. Support
        for 'createAndWait' and 'notInService' is not required.
        A row entry cannot be modified when the value of this
        object is 'active'."
::= { isisRAEntry 2 }
isisRAAdminState OBJECT-TYPE
   SYNTAX IsisAdminState
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
```

```
"The administrative state of the Reachable Address.
        object follows the ManualOrAutomatic behaviors."
   DEFVAL { off }
::= { isisRAEntry 3 }
isisRAAddrPrefix OBJECT-TYPE
   SYNTAX IsisOSINSAddress
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The destination of this Reachable Address. This is an
        Address Prefix. This object follows the
        ReplaceOnlyWhileDisabled and ManualOrAutomatic
        behaviors."
   REFERENCE "{ISIS.aoi addressPrefix (98)}"
::= { isisRAEntry 4 }
isisRAMapType OBJECT-TYPE
   SYNTAX INTEGER
       {
           none (1),
           explicit (2),
           extractIDI (3),
           extractDSP (4)
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The type of mapping to be employed to ascertain the SNPA
        Address that should be used in forwarding PDUs for this
        Reachable Address prefix. This object follows the
        ManualOrAutomatic behavior. The following values of
        mapping type are defined:
            none: The mapping is null because the neighbor SNPA is
                   implicit by nature of the subnetwork (e.g., a
                  point-to-point linkage).
             explicit: The subnetwork addresses in the object
                   isisRASNPAAddress are to be used.
             extractIDI: The SNPA is embedded in the IDI of
                   the destination NSAP Address. The mapping
                   algorithm extracts the SNPA to be used
                  according to the format and encoding rules of
                  ISO8473/Add2. This SNPA extraction algorithm can
                  be used in conjunction with Reachable Address
                  prefixes from the X.121, F.69, E.163, and E.164
```

addressing subdomains.

extractDSP: All, or a suffix, of the SNPA is embedded in the DSP of the destination address. This SNPA extraction algorithm extracts the embedded subnetwork addressing information by performing a logical AND of the isisRASNPAMask object value with the destination address. The part of the SNPA extracted from the destination NSAP is appended to the isisRASNPAPrefix object value to form the next hop subnetwork addressing information."

```
REFERENCE "{ISO10589-ISIS.aoi mappingType (107)}"
::= { isisRAEntry 5 }
isisRAMetric OBJECT-TYPE
   SYNTAX IsisDefaultMetric
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The metric value for reaching the specified
        prefix over this circuit. This object follows the
        ManualOrAutomatic behavior."
   REFERENCE "{ISIS.aoi DefaultMetric (99)}"
   DEFVAL { 20 }
::= { isisRAEntry 6 }
isisRAMetricType OBJECT-TYPE
   SYNTAX IsisMetricType
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "Indicates whether the metric is internal or
        external. This object follows the ManualOrAutomatic
        behavior."
   REFERENCE "{ISIS.aoi DefaultMetricType (103)}"
   DEFVAL { internal }
::= { isisRAEntry 7 }
isisRASNPAAddress OBJECT-TYPE
   SYNTAX IsisOSINSAddress
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The SNPA Address to which a PDU may be forwarded in
        order to reach a destination that matches the address
        prefix of the Reachable Address. This object follows the
```

```
ManualOrAutomatic behavior."
       REFERENCE "{ISIS.aoi sNPAAddresses (109)}"
-- Note only one address may be specified per Reachable Address
-- in the MIB
       DEFVAL { ''H }
    ::= { isisRAEntry 8 }
    isisRASNPAMask OBJECT-TYPE
        SYNTAX IsisOSINSAddress
       MAX-ACCESS read-create
       STATUS current
        DESCRIPTION
            "A bit mask with 1 bit indicating the positions in the
            effective destination address from which embedded SNPA
             information is to be extracted. For the extraction, the
             first octet of the isisRASNPAMask object value is aligned
             with the first octet (AFI) of the NSAP Address. If the
             isisRASNPAMask object value and NSAP Address are of
             different lengths, the shorter of the two is logically
             padded with zeros before performing the extraction. This
             object follows the ManualOrAutomatic behavior."
       REFERENCE "{ISIS.aoi sNPAMask (122)}"
       DEFVAL { '00'H }
    ::= { isisRAEntry 9 }
    isisRASNPAPrefix OBJECT-TYPE
        SYNTAX IsisOSINSAddress
       MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
            "A fixed SNPA prefix for use when the isisRAMapType is
             extractDSP. The SNPA Address to use is formed by
             concatenating the fixed SNPA prefix with a variable SNPA
             part that is extracted from the effective destination
             address. For Reachable Address prefixes in which the
             entire SNPA is embedded in the DSP, the SNPA Prefix shall
            be null. This object follows the ManualOrAutomatic
             behavior."
       REFERENCE "{ISIS.aoi sNPAPrefix (123)}"
       DEFVAL { '00'H }
    ::= { isisRAEntry 10 }
    isisRAType OBJECT-TYPE
        SYNTAX INTEGER
           {
               manual (1),
               automatic (2)
            }
```

```
MAX-ACCESS read-create
       STATUS current
       DESCRIPTION
            "The type of Reachable address. Those of type
            manual are created by the network manager. Those
             of type automatic are created through propagation
             of routing information from another routing
             protocol (e.g., IDRP). "
       DEFVAL {manual}
    ::= {isisRAEntry 11 }
-- The IP Reachable Address Table
-- Each entry records information about one IP reachable
-- address manually configured on this system or learned from
-- another protocol.
    isisIPRATable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisIPRAEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "The table of IP Reachable Addresses to networks,
             subnetworks, or hosts either manually configured or
             learned from another protocol."
    ::= { isisIPReachAddr 1 }
    isisIPRAEntry OBJECT-TYPE
       SYNTAX IsisIPRAEntry
       MAX-ACCESS not-accessible
        STATUS current
        DESCRIPTION
            "Each entry defines an IP Reachable Address to a network,
             subnetwork, or host.
             Each IP Reachable Address may have multiple entries in the
             table, one for each equal cost path to the reachable
             address.
             Dynamically created rows MUST survive an agent reboot.
             Implementers need to be aware that if the total number
             of elements (octets or sub-identifiers) in
             isisIPRADestr, isisIPRADestPrefixLen, and
             isisIPRANextHopIndex is too great, then OIDs of column
             instances in this table will have more than 128
             subidentifiers and cannot be accessed using SNMPv1,
```

```
SNMPv2c, or SNMPv3."
    INDEX { isisSysLevelIndex,
             isisIPRADestType,
             isisIPRADest,
             isisIPRADestPrefixLen,
             isisIPRANextHopIndex }
::= { isisIPRATable 1 }
IsisIPRAEntry ::=
    SEQUENCE {
        isisIPRADestType
            InetAddressType,
        isisIPRADest
           InetAddress,
        isisIPRADestPrefixLen
           InetAddressPrefixLength,
        isisIPRANextHopIndex
           Unsigned32,
        isisIPRANextHopType
           InetAddressType,
        isisIPRANextHop
           InetAddress,
        isisIPRAType
            INTEGER,
        isisIPRAExistState
            RowStatus,
        isisIPRAAdminState
           IsisAdminState,
        isisIPRAMetric
           IsisDefaultMetric,
        isisIPRAMetricType
            IsisMetricType,
        isisIPRAFullMetric
            IsisFullMetric,
        isisIPRASNPAAddress
           IsisOSINSAddress,
        isisIPRASourceType
           INTEGER
    }
isisIPRADestType OBJECT-TYPE
    SYNTAX InetAddressType
    MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
        "The type of this IP Reachable Address."
::= { isisIPRAEntry 1 }
```

```
isisIPRADest OBJECT-TYPE
   SYNTAX InetAddress
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The destination of this IP Reachable Address. This is
        a network address, subnetwork address, or host
        The type of this address is determined by the value of
         the isisIPRADestType object."
::= { isisIPRAEntry 2 }
isisIPRADestPrefixLen OBJECT-TYPE
   SYNTAX InetAddressPrefixLength
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The length of the IP Netmask for Reachability Address.
        The values for the index objects isisIPRADest and
        isisIPRADestPrefixLen must be consistent. When the value
        of isisIPRADest (excluding the zone index, if one
        is present) is x, then the bitwise logical-AND
        of x with the value of the mask formed from the
        corresponding index object isisIPRADestPrefixLen MUST be
        equal to x. If not, then the index pair is not
        consistent, and an inconsistentName error must be
        returned on SET or CREATE requests."
::= { isisIPRAEntry 3 }
isisIPRANextHopIndex OBJECT-TYPE
   SYNTAX Unsigned32(1..4294967295)
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "Index of next hop. Used when there are multiple Equal
        Cost Multipath alternatives for the same destination."
::= { isisIPRAEntry 4 }
isisIPRANextHopType OBJECT-TYPE
   SYNTAX InetAddressType
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The type of the IP next hop address."
::= { isisIPRAEntry 5 }
```

```
isisIPRANextHop OBJECT-TYPE
   SYNTAX InetAddress
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The IP next hop to this destination.
        The type of this address is determined by the value of
         the isisIPRANextHopType object."
::= { isisIPRAEntry 6 }
isisIPRAType OBJECT-TYPE
   SYNTAX INTEGER
       {
           manual (1),
           automatic (2)
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The type of this IP Reachable Address. Those of type
        manual are created by the network manager. Those of type
        automatic are created through propagation of routing
        information from another routing protocol. This object
         follows the ManualOrAutomatic behavior."
::= { isisIPRAEntry 7 }
isisIPRAExistState OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The state of this IP Reachable Address. This object
        follows the ExistenceState and ManualOrAutomatic
        behaviors. Support for 'createAndWait' and
        'notInService' is not required.
        A row entry cannot be modified when the value of this
        object is 'active'."
::= { isisIPRAEntry 8 }
isisIPRAAdminState OBJECT-TYPE
   SYNTAX IsisAdminState
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The administrative state of the IP Reachable Address. This
        object follows the IsisAdminState and ManualOrAutomatic
```

```
behaviors."
   DEFVAL { off }
::= { isisIPRAEntry 9 }
isisIPRAMetric OBJECT-TYPE
   SYNTAX IsisDefaultMetric
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The metric value for reaching the specified
        destination over this circuit. This object follows the
        ManualOrAutomatic behavior."
   DEFVAL { 10 }
::= { isisIPRAEntry 10 }
isisIPRAMetricType OBJECT-TYPE
   SYNTAX IsisMetricType
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "Indicates whether the metric is internal or
        external. This object follows the ManualOrAutomatic
        behavior."
   DEFVAL { internal }
::= { isisIPRAEntry 11 }
isisIPRAFullMetric OBJECT-TYPE
   SYNTAX IsisFullMetric
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The wide metric value for reaching the specified
        destination over this circuit. This object follows the
        ManualOrAutomatic behavior."
   DEFVAL { 10 }
::= { isisIPRAEntry 12 }
isisIPRASNPAAddress OBJECT-TYPE
   SYNTAX IsisOSINSAddress
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
        "The SNPA Address to which a PDU may be forwarded in
        order to reach a destination that matches this IP
        Reachable Address. This object follows the
        ManualOrAutomatic behavior."
   DEFVAL { ''H }
::= { isisIPRAEntry 13 }
```

```
isisIPRASourceType OBJECT-TYPE
       SYNTAX INTEGER
           {
               static (1),
               direct (2),
               ospfv2 (3),
               ospfv3 (4),
               isis (5),
               rip (6),
               igrp (7),
               eigrp (8),
               bgp (9),
               other (10)
       MAX-ACCESS read-only
        STATUS current
       DESCRIPTION
           "The origin of this route."
    ::= { isisIPRAEntry 14 }
-- The LSP Database Table
-- The first table provides Summary Information about LSPs
-- The next table provides a complete record
    isisLSPSummaryTable OBJECT-TYPE
        SYNTAX SEQUENCE OF IsisLSPSummaryEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "The table of LSP Headers."
    ::= { isisLSPDataBase 1 }
    isisLSPSummaryEntry OBJECT-TYPE
       SYNTAX IsisLSPSummaryEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Each entry provides a summary describing an
            LSP currently stored in the system.
            Dynamically learned rows will not survive an
            agent reboot."
        INDEX { isisLSPLevel,
                isisLSPID }
    ::= { isisLSPSummaryTable 1 }
   IsisLSPSummaryEntry ::=
```

```
SEQUENCE {
       isisLSPLevel
           IsisISLevel,
        isisLSPID
           IsisLinkStatePDUID,
        isisLSPSeq
           Unsigned32,
        isisLSPZeroLife
            TruthValue,
        isisLSPChecksum
           IsisUnsigned16TC,
        isisLSPLifetimeRemain
           IsisUnsigned16TC,
        \verb"isisLSPPDULength"
           IsisUnsigned16TC,
       isisLSPAttributes
           IsisUnsigned8TC
    }
isisLSPLevel OBJECT-TYPE
    SYNTAX IsisISLevel
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "At which level does this LSP appear?"
::= { isisLSPSummaryEntry 1 }
isisLSPID OBJECT-TYPE
   SYNTAX IsisLinkStatePDUID
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The 8-byte LSP ID for this Link State PDU."
::= { isisLSPSummaryEntry 2 }
isisLSPSeq OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The sequence number for this LSP."
::= { isisLSPSummaryEntry 3 }
isisLSPZeroLife OBJECT-TYPE
   SYNTAX TruthValue
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
```

```
"Is this LSP being purged by this system?"
    ::= { isisLSPSummaryEntry 4 }
    isisLSPChecksum OBJECT-TYPE
       SYNTAX IsisUnsigned16TC
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The 16-bit Fletcher Checksum for this LSP."
    ::= { isisLSPSummaryEntry 5 }
    isisLSPLifetimeRemain OBJECT-TYPE
       SYNTAX IsisUnsigned16TC
       UNITS "seconds"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The remaining lifetime, in seconds, for this LSP."
    ::= { isisLSPSummaryEntry 6 }
    isisLSPPDULength OBJECT-TYPE
       SYNTAX IsisUnsigned16TC
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The length of this LSP."
    ::= { isisLSPSummaryEntry 7 }
    isisLSPAttributes OBJECT-TYPE
       SYNTAX IsisUnsigned8TC
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "Flags carried by the LSP."
    ::= { isisLSPSummaryEntry 8 }
-- LSP Table
-- The full LSP as a sequence of {Type, Len, Value} tuples
-- Since the underlying LSP may have changed while downloading
-- TLVs, we provide the Sequence number and Checksum for each
-- LSP TLV, so the network manager may verify that they are
-- still working on the same version of the LSP.
    isisLSPTLVTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IsisLSPTLVEntry
       MAX-ACCESS not-accessible
       STATUS current
```

```
DESCRIPTION
       "The table of LSPs in the database."
::= { isisLSPDataBase 2 }
isisLSPTLVEntry OBJECT-TYPE
   SYNTAX IsisLSPTLVEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "Each entry describes a TLV within
        an LSP currently stored in the system.
         Dynamically learned rows will not survive an
        agent reboot."
   INDEX { isisLSPLevel,
            isisLSPID,
            isisLSPTLVIndex }
::= { isisLSPTLVTable 1 }
IsisLSPTLVEntry ::=
   SEQUENCE {
       isisLSPTLVIndex
           Unsigned32,
       isisLSPTLVSeq
           Unsigned32,
       isisLSPTLVChecksum
           IsisUnsigned16TC,
       isisLSPTLVType
           IsisUnsigned8TC,
       isisLSPTLVLen
           IsisUnsigned8TC,
       isisLSPTLVValue
           OCTET STRING
    }
isisLSPTLVIndex OBJECT-TYPE
   SYNTAX Unsigned32(1..4294967295)
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "The index of this TLV in the LSP. The first TLV has
         index 1, and the Nth TLV has an index of N."
::= { isisLSPTLVEntry 1 }
isisLSPTLVSeq OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-only
   STATUS current
```

```
DESCRIPTION
           "The sequence number for this LSP."
    ::= { isisLSPTLVEntry 2 }
    isisLSPTLVChecksum OBJECT-TYPE
        SYNTAX IsisUnsigned16TC
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The 16-bit Fletcher Checksum for this LSP."
    ::= { isisLSPTLVEntry 3 }
    isisLSPTLVType OBJECT-TYPE
       SYNTAX IsisUnsigned8TC
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The type of this TLV."
    ::= { isisLSPTLVEntry 4 }
    isisLSPTLVLen OBJECT-TYPE
       SYNTAX IsisUnsigned8TC
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The length of this TLV."
    ::= { isisLSPTLVEntry 5 }
    isisLSPTLVValue OBJECT-TYPE
       SYNTAX OCTET STRING (SIZE(0..255))
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The value of this TLV."
    ::= { isisLSPTLVEntry 6 }
-- The IS-IS Notification Table
-- The IS-IS Notification Table records fields that are
-- required for notifications
    isisNotificationEntry OBJECT IDENTIFIER
        ::= { isisNotification 1 }
    isisNotificationSysLevelIndex OBJECT-TYPE
       SYNTAX IsisLevel
       MAX-ACCESS accessible-for-notify
```

```
STATUS current
   DESCRIPTION
        "The system level for this notification."
::= { isisNotificationEntry 1 }
isisNotificationCircIfIndex OBJECT-TYPE
   SYNTAX Unsigned32 (1..2147483647)
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "The identifier of this circuit relevant to
        this notification."
::= { isisNotificationEntry 2 }
isisPduLspId OBJECT-TYPE
   SYNTAX IsisLinkStatePDUID
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "An Octet String that uniquely identifies
        a Link State PDU."
::= { isisNotificationEntry 3 }
isisPduFragment OBJECT-TYPE
   SYNTAX IsisPDUHeader
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "Holds up to 64 initial bytes of a PDU that
        triggered the notification."
::= { isisNotificationEntry 4 }
isisPduFieldLen OBJECT-TYPE
   SYNTAX IsisUnsigned8TC
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "Holds the System ID length reported in PDU we received."
::= { isisNotificationEntry 5 }
isisPduMaxAreaAddress OBJECT-TYPE
   SYNTAX IsisUnsigned8TC
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "Holds the Max Area Addresses reported in a PDU
        we received."
::= { isisNotificationEntry 6 }
```

```
isisPduProtocolVersion OBJECT-TYPE
   SYNTAX IsisUnsigned8TC
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "Holds the Protocol version reported in PDU we received."
::= { isisNotificationEntry 7 }
isisPduLspSize OBJECT-TYPE
    SYNTAX Unsigned32 (0..2147483647)
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "Holds the size of LSP we received that is too
        big to forward."
::= { isisNotificationEntry 8 }
\verb|isisPduOriginatingBufferSize| OBJECT-TYPE|
    SYNTAX IsisUnsigned16TC (0..16000)
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "Holds the size of isisSysLevelOrigLSPBuffSize advertised
        by the peer in the originatingLSPBufferSize TLV.
         If the peer does not advertise this TLV, this
         value is set to 0."
::= { isisNotificationEntry 9 }
isisPduBufferSize OBJECT-TYPE
   SYNTAX IsisUnsigned16TC (0..16000)
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "Holds the size of LSP received from peer."
::= { isisNotificationEntry 10 }
isisPduProtocolsSupported OBJECT-TYPE
    SYNTAX OCTET STRING (SIZE(0..255))
   MAX-ACCESS accessible-for-notify
   STATUS current
   DESCRIPTION
        "The list of protocols supported by an
         adjacent system. This may be empty."
::= { isisNotificationEntry 11 }
isisAdjState OBJECT-TYPE
    SYNTAX INTEGER
        {
```

```
down (1),
                 initializing (2),
                up (3),
                failed(4)
       MAX-ACCESS accessible-for-notify
       STATUS current
       DESCRIPTION
            "The current state of an adjacency."
    ::= { isisNotificationEntry 12 }
   isisErrorOffset OBJECT-TYPE
       SYNTAX Unsigned32
       MAX-ACCESS accessible-for-notify
       STATUS current
       DESCRIPTION
            "An offset to a problem in a PDU. If the problem
            is a malformed TLV, this points to the beginning
            of the TLV. If the problem is in the header, this
            points to the byte that is suspicious."
    ::= { isisNotificationEntry 13 }
   isisErrorTLVType OBJECT-TYPE
       SYNTAX Unsigned32 (0..255)
       MAX-ACCESS accessible-for-notify
       STATUS current
       DESCRIPTION
             "The type for a malformed TLV."
    ::= { isisNotificationEntry 14 }
   isisNotificationAreaAddress OBJECT-TYPE
       SYNTAX IsisOSINSAddress
       MAX-ACCESS accessible-for-notify
       STATUS current
       DESCRIPTION
           "An Area Address."
    ::= { isisNotificationEntry 15 }
-- Notification definitions
-- Note that notifications can be disabled by setting
      isisSysNotificationEnable false
   isisDatabaseOverload NOTIFICATION-TYPE
       OBJECTS {
           isisNotificationSysLevelIndex,
           isisSysLevelState
        }
```

```
STATUS current
   DESCRIPTION
       "This notification is generated when the system
        enters or leaves the Overload state. The number
        of times this has been generated and cleared is kept
         track of by isisSysStatLSPDbaseOloads."
::= { isisNotifications 1 }
isisManualAddressDrops NOTIFICATION-TYPE
   OBJECTS {
       isisNotificationAreaAddress
    }
   STATUS current
   DESCRIPTION
        "This notification is generated when one of the
        manual areaAddresses assigned to this system is
        ignored when computing routes. The object
        isisNotificationAreaAddress describes the area that
        has been dropped.
        The number of times this event has been generated
        is counted by isisSysStatManAddrDropFromAreas.
        The agent must throttle the generation of
        consecutive isisManualAddressDrops notifications
        so that there is at least a 5-second gap between
        notifications of this type. When notifications
        are throttled, they are dropped, not queued for
        sending at a future time."
::= { isisNotifications 2 }
isisCorruptedLSPDetected NOTIFICATION-TYPE
   OBJECTS {
       isisNotificationSysLevelIndex,
       isisPduLspId
   STATUS current
   DESCRIPTION
        "This notification is generated when we find that
        an LSP that was stored in memory has become
        corrupted. The number of times this has been
        generated is counted by isisSysCorrLSPs.
        We forward an LSP ID. We may have independent
        knowledge of the ID, but in some implementations
        there is a chance that the ID itself will be
        corrupted."
```

```
::= { isisNotifications 3 }
isisAttemptToExceedMaxSequence NOTIFICATION-TYPE
    OBJECTS {
        isisNotificationSysLevelIndex,
        isisPduLspId
    STATUS current
    DESCRIPTION
        "When the sequence number on an LSP we generate
        wraps the 32-bit sequence counter, we purge and
         wait to re-announce this information. This
        notification describes that event. Since these
         should not be generated rapidly, we generate
         an event each time this happens.
         While the first 6 bytes of the LSPID are ours,
         the other two contain useful information."
::= { isisNotifications 4 }
isisIDLenMismatch NOTIFICATION-TYPE
    OBJECTS {
        isisNotificationSysLevelIndex,
        isisPduFieldLen,
        isisNotificationCircIfIndex,
        isisPduFragment
    }
    STATUS current
    DESCRIPTION
        "A notification sent when we receive a PDU
         with a different value for the System ID Length.
         This notification includes an index to identify
         the circuit where we saw the PDU and the header of
         the PDU, which may help a network manager identify
         the source of the confusion.
         The agent must throttle the generation of
         consecutive isisIDLenMismatch notifications
         so that there is at least a 5-second gap between
         notifications of this type. When notifications
         are throttled, they are dropped, not queued for
         sending at a future time."
::= { isisNotifications 5 }
isisMaxAreaAddressesMismatch NOTIFICATION-TYPE
   OBJECTS {
```

isisNotificationSysLevelIndex,

```
isisPduMaxAreaAddress,
       isisNotificationCircIfIndex,
       isisPduFragment
    }
   STATUS current
   DESCRIPTION
        "A notification sent when we receive a PDU
        with a different value for the Maximum Area
        Addresses. This notification includes the
        header of the packet, which may help a
        network manager identify the source of the
        confusion.
        The agent must throttle the generation of
        consecutive isisMaxAreaAddressesMismatch
        notifications so that there is at least a 5-second
        gap between notifications of this type. When
        notifications are throttled, they are dropped, not
        queued for sending at a future time."
::= { isisNotifications 6 }
isisOwnLSPPurge NOTIFICATION-TYPE
   OBJECTS {
       isisNotificationSysLevelIndex,
       isisNotificationCircIfIndex,
       isisPduLspId
    }
   STATUS current
   DESCRIPTION
        "A notification sent when we receive a PDU
        with our systemID and zero age. This
        notification includes the circuit Index
        and router ID from the LSP, if available,
        which may help a network manager
        identify the source of the confusion."
::= { isisNotifications 7 }
isisSequenceNumberSkip NOTIFICATION-TYPE
   OBJECTS {
       isisNotificationSysLevelIndex,
        isisNotificationCircIfIndex,
       isisPduLspId
    }
   STATUS current
```

```
DESCRIPTION
        "When we receive an LSP with our System ID
        and different contents, we may need to reissue
         the LSP with a higher sequence number.
         We send this notification if we need to increase
         the sequence number by more than one. If two
         Intermediate Systems are configured with the same
         System ID, this notification will fire."
::= { isisNotifications 8 }
{\tt isis} {\tt AuthenticationTypeFailure\ NOTIFICATION-TYPE}
    OBJECTS {
       isisNotificationSysLevelIndex,
        isisNotificationCircIfIndex,
        isisPduFragment
    STATUS current
    DESCRIPTION
        "A notification sent when we receive a PDU
        with the wrong authentication type field.
         This notification includes the header of the
         packet, which may help a network manager
         identify the source of the confusion.
         The agent must throttle the generation of
         consecutive isisAuthenticationTypeFailure
         notifications so that there is at least a 5-second
         gap between notifications of this type. When
         notifications are throttled, they are dropped, not
         queued for sending at a future time."
::= { isisNotifications 9 }
isisAuthenticationFailure NOTIFICATION-TYPE
   OBJECTS {
        isisNotificationSysLevelIndex,
        isisNotificationCircIfIndex,
        isisPduFragment
    STATUS current
    DESCRIPTION
        "A notification sent when we receive a PDU
        with an incorrect authentication information
         field. This notification includes the header
```

of the packet, which may help a network manager

identify the source of the confusion.

notifications so that there is at least a 5-second

The agent must throttle the generation of consecutive isisAuthenticationFailure

gap between notifications of this type. When notifications are throttled, they are dropped, not queued for sending at a future time." ::= { isisNotifications 10 } isisVersionSkew NOTIFICATION-TYPE OBJECTS { isisNotificationSysLevelIndex, isisNotificationCircIfIndex, isisPduProtocolVersion, isisPduFragment STATUS current DESCRIPTION "A notification sent when we receive a Hello PDU from an IS running a different version of the protocol. This notification includes the header of the packet, which may help a network manager identify the source of the confusion. The agent must throttle the generation of consecutive isisVersionSkew notifications so that there is at least a 5-second gap between notifications of this type. When notifications are throttled, they are dropped, not queued for sending at a future time." ::= { isisNotifications 11 } isisAreaMismatch NOTIFICATION-TYPE OBJECTS { isisNotificationCircIfIndex, isisPduFragment

Parker Standards Track [Page 79]

"A notification sent when we receive a Hello PDU from an IS that does not share any area address. This notification includes the header of the packet, which may help a network manager identify the source of the

STATUS current DESCRIPTION

confusion.

The agent must throttle the generation of

```
consecutive isisAreaMismatch notifications
        so that there is at least a 5-second gap
        between notifications of this type. When
        notifications are throttled, they are dropped, not
        queued for sending at a future time."
::= { isisNotifications 12 }
isisRejectedAdjacency NOTIFICATION-TYPE
   OBJECTS {
       isisNotificationSysLevelIndex,
       isisNotificationCircIfIndex,
       isisPduFragment
   STATUS current
   DESCRIPTION
        "A notification sent when we receive a Hello
        PDU from an IS but do not establish an
        adjacency for some reason.
        The agent must throttle the generation of
        consecutive isisRejectedAdjacency notifications
        so that there is at least a 5-second gap
        between notifications of this type. When
        notifications are throttled, they are dropped, not
        queued for sending at a future time."
::= { isisNotifications 13 }
isisLSPTooLargeToPropagate NOTIFICATION-TYPE
   OBJECTS {
        isisNotificationSysLevelIndex,
       isisNotificationCircIfIndex,
       isisPduLspSize,
       isisPduLspId
   STATUS current
   DESCRIPTION
        "A notification sent when we attempt to propagate
        an LSP that is larger than the dataLinkBlockSize
        for the circuit.
        The agent must throttle the generation of
        consecutive isisLSPTooLargeToPropagate notifications
        so that there is at least a 5-second gap
        between notifications of this type. When
        notifications are throttled, they are dropped, not
```

```
queued for sending at a future time."
::= { isisNotifications 14 }
isisOrigLSPBuffSizeMismatch NOTIFICATION-TYPE
   OBJECTS {
        isisNotificationSysLevelIndex,
       isisNotificationCircIfIndex,
       isisPduLspId,
       isisPduOriginatingBufferSize,
       isisPduBufferSize
    }
   STATUS current
   DESCRIPTION
        "A notification sent when a Level 1 LSP or Level
        2 LSP is received that is larger than the local
        value for isisSysLevelOrigLSPBuffSize, or when an
        LSP is received that contains the supported Buffer Size
        option and the value in the PDU option field does
        not match the local value for isisSysLevelOrigLSPBuffSize.
        We pass up the size from the option field and the
        size of the LSP when one of them exceeds our configuration.
        The agent must throttle the generation of
        consecutive isisOrigLSPBuffSizeMismatch notifications
        so that there is at least a 5-second gap
        between notifications of this type. When
        notifications are throttled, they are dropped, not
        queued for sending at a future time."
::= { isisNotifications 15 }
isisProtocolsSupportedMismatch NOTIFICATION-TYPE
   OBJECTS {
       isisNotificationSysLevelIndex,
       isisNotificationCircIfIndex,
       isisPduProtocolsSupported,
       isisPduLspId,
       isisPduFragment
   STATUS current
   DESCRIPTION
        "A notification sent when a non-pseudonode
        segment 0 LSP is received that has no matching
        protocols supported. This may be because the system
        does not generate the field, or because there are no
        common elements. The list of protocols supported
        should be included in the notification: it may be
```

```
empty if the TLV is not supported, or if the
        TLV is empty.
        The agent must throttle the generation of
        consecutive isisProtocolsSupportedMismatch
        notifications so that there is at least a 5-second
        gap between notifications of this type. When
        notifications are throttled, they are dropped, not
        queued for sending at a future time."
::= { isisNotifications 16 }
isisAdjacencyChange NOTIFICATION-TYPE
   OBJECTS {
       isisNotificationSysLevelIndex,
       isisNotificationCircIfIndex,
       isisPduLspId,
       isisAdjState
   STATUS current
   DESCRIPTION
        "A notification sent when an adjacency changes
        state, entering or leaving state up.
        The first 6 bytes of the isisPduLspId are the
        SystemID of the adjacent IS.
        The isisAdjState is the new state of the adjacency."
::= { isisNotifications 17 }
isisLSPErrorDetected NOTIFICATION-TYPE
   OBJECTS {
       isisNotificationSysLevelIndex,
       isisPduLspId,
       isisNotificationCircIfIndex,
       isisPduFragment,
       isisErrorOffset,
       isisErrorTLVType
   STATUS current
   DESCRIPTION
        "This notification is generated when we receive
        an LSP with a parse error. The isisCircIfIndex
        holds an index of the circuit on which the PDU
        arrived. The isisPduFragment holds the start of the
        LSP, and the isisErrorOffset points to the problem.
        If the problem is a malformed TLV, isisErrorOffset
        points to the start of the TLV, and isisErrorTLVType
```

```
holds the value of the type.
             If the problem is with the LSP header, isisErrorOffset
             points to the suspicious byte.
             The number of such LSPs is accumulated in
             isisSysStatLSPErrors."
    ::= { isisNotifications 18 }
-- Agent Conformance Definitions
-- We define the objects a conformant agent must define
isisCompliances OBJECT IDENTIFIER ::= { isisConformance 1 }
isisGroups     OBJECT IDENTIFIER ::= { isisConformance 2 }
-- compliance statements
    isisCompliance MODULE-COMPLIANCE
       STATUS current
       DESCRIPTION
            "The compliance statement for agents that support
             the IS-IS MIB.
             There are a number of INDEX objects that cannot be
             represented in the form of OBJECT clauses in SMIv2,
             but for which there are compliance requirements.
             Those requirements and similar requirements for
             related objects are expressed below, in
             pseudo-OBJECT clause form, in this description:
             -- OBJECT isisSummAddressType
             -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
             -- DESCRIPTION
                 The MIB requires support for IPv4 Summary
                 Addresses and anticipates the support of
                  IPv6 addresses.
             __
             -- OBJECT isisRedistributeAddrType
             -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
             -- DESCRIPTION
             -- The MIB requires support for IPv4
                 Redistribution Addresses and anticipates
                 the support of IPv6 addresses."
             ___
```

```
-- OBJECT isisISAdjIPAddrType
        -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
         -- DESCRIPTION
             The MIB requires support for IPv4
              Adjacency Addresses and anticipates the
             support of IPv6 addresses.
   MODULE -- this module
       MANDATORY-GROUPS {
               isisSystemGroup,
               isisCircuitGroup,
               isisISAdjGroup,
               isisNotificationObjectGroup,
                isisNotificationGroup
::= { isisCompliances 1 }
-- List of all groups, mandatory and optional
isisAdvancedCompliance MODULE-COMPLIANCE
   STATUS current
   DESCRIPTION
        "The compliance statement for agents that fully
         support the IS-IS MIB.
        There are a number of INDEX objects that cannot be
        represented in the form of OBJECT clauses in SMIv2,
        but for which there are compliance requirements.
        Those requirements and similar requirements for
        related objects are expressed below, in
        pseudo-OBJECT clause form, in this description:
         -- OBJECT isisSummAddressType
         -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
         -- DESCRIPTION
         -- The MIB requires support for IPv4 Summary
         -- Addresses and anticipates the support of
             IPv6 addresses.
         ___
         -- OBJECT isisRedistributeAddrType
         -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
         -- DESCRIPTION
         -- The MIB requires support for IPv4
             Redistribution Addresses and anticipates
             the support of IPv6 addresses."
```

```
-- OBJECT isisISAdjIPAddrType
        -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
        --
         -- DESCRIPTION
         -- The MIB requires support for IPv4
             Adjacency Addresses and anticipates the
             support of IPv6 addresses.
         -- OBJECT isisIPRADestType
        -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
         -- DESCRIPTION
         -- The MIB requires support for IPv4 RA
             Addresses and anticipates the support of
             IPv6 addresses.
         ___
         -- OBJECT isisIPRANextHopType
        -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
         -- DESCRIPTION
             The MIB requires support for IPv4 NextHop
              Addresses and anticipates the support of
              IPv6 addresses.
   MODULE -- this module
       MANDATORY-GROUPS {
               isisSystemGroup,
               isisCircuitGroup,
               isisISAdjGroup,
               isisNotificationObjectGroup,
               isisNotificationGroup,
               isisISPDUCounterGroup,
               isisRATableGroup,
               isisISIPRADestGroup,
               isisLSPGroup
::= { isisCompliances 2 }
isisReadOnlyCompliance MODULE-COMPLIANCE
  STATUS
             current
  DESCRIPTION
           "When this MIB is implemented without support for
           read-create (i.e., in read-only mode), the
           implementation can claim read-only compliance. Such
           a device can then be monitored but cannot be
```

```
configured with this MIB."
MODULE -- this module
     MANDATORY-GROUPS {
            isisSystemGroup,
             isisCircuitGroup,
             isisISAdjGroup
     }
OBJECT isisSysLevelType
MIN-ACCESS read-only
DESCRIPTION
     "Write access is not required."
OBJECT isisSysID
MIN-ACCESS read-only
DESCRIPTION
     "Write access is not required."
OBJECT isisSysMaxPathSplits
MIN-ACCESS read-only
DESCRIPTION
     "Write access is not required."
OBJECT isisSysMaxLSPGenInt
MIN-ACCESS read-only
DESCRIPTION
     "Write access is not required."
OBJECT isisSysPollESHelloRate
MIN-ACCESS read-only
DESCRIPTION
     "Write access is not required."
OBJECT isisSysWaitTime
MIN-ACCESS read-only
DESCRIPTION
     "Write access is not required."
OBJECT isisSysAdminState
MIN-ACCESS read-only
DESCRIPTION
     "Write access is not required."
OBJECT isisSysL2toL1Leaking
MIN-ACCESS read-only
DESCRIPTION
     "Write access is not required."
```

OBJECT isisSysMaxAge MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisManAreaAddrExistState MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSysLevelOrigLSPBuffSize MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSysLevelMinLSPGenInt MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSysLevelSetOverload MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSysLevelSetOverloadUntil MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSysLevelMetricStyle MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSysLevelSPFConsiders MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSysLevelTEEnabled MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSysReceiveLSPBufferSize MIN-ACCESS read-only DESCRIPTION "Write access is not required."

OBJECT isisSummAddrExistState MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSummAddrMetric MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisSummAddrFullMetric MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisRedistributeAddrExistState MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircAdminState MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircExistState MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircType MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircExtDomain MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircLevelType MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircPassiveCircuit

MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircMeshGroupEnabled MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircMeshGroup MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircSmallHellos MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircExtendedCircID MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircIfIndex MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCirc3WayEnabled MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircLevelMetric MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircLevelWideMetric MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

OBJECT isisCircLevelISPriority MIN-ACCESS read-only DESCRIPTION

"Write access is not required."

```
OBJECT isisCircLevelHelloMultiplier
      MIN-ACCESS read-only
      DESCRIPTION
            "Write access is not required."
      OBJECT isisCircLevelHelloTimer
      MIN-ACCESS read-only
      DESCRIPTION
            "Write access is not required."
      OBJECT isisCircLevelDRHelloTimer
      MIN-ACCESS read-only
      DESCRIPTION
            "Write access is not required."
      OBJECT isisCircLevelLSPThrottle
      MIN-ACCESS read-only
      DESCRIPTION
           "Write access is not required."
      OBJECT isisCircLevelMinLSPRetransInt
      MIN-ACCESS read-only
      DESCRIPTION
            "Write access is not required."
      OBJECT isisCircLevelCSNPInterval
      MIN-ACCESS read-only
      DESCRIPTION
            "Write access is not required."
      OBJECT isisCircLevelPartSNPInterval
      MIN-ACCESS read-only
      DESCRIPTION
            "Write access is not required."
    ::= { isisCompliances 3 }
-- MIB Grouping
    isisSystemGroup OBJECT-GROUP
        OBJECTS {
            isisSysVersion,
            isisSysLevelType,
            isisSysID,
            isisSysMaxPathSplits,
            isisSysMaxLSPGenInt,
            isisSysPollESHelloRate,
            isisSysWaitTime,
```

```
isisSysAdminState,
        isisSysL2toL1Leaking,
        isisSysMaxAge,
        isisSysProtSupported,
        isisSysNotificationEnable,
        isisManAreaAddrExistState,
        isisSysLevelOrigLSPBuffSize,
        isisSysLevelMinLSPGenInt,
        isisSysLevelState,
        isisSysLevelSetOverload,
        isisSysLevelSetOverloadUntil,
        isisSysLevelMetricStyle,
        isisSysLevelSPFConsiders,
        isisSysLevelTEEnabled,
        isisSysReceiveLSPBufferSize,
        isisSummAddrExistState,
        isisSummAddrMetric,
        isisAreaAddr,
        isisSummAddrFullMetric,
        isisRedistributeAddrExistState,
        isisRouterHostName,
        isisRouterID,
        isisSysStatCorrLSPs,
        isisSysStatLSPDbaseOloads,
        isisSysStatManAddrDropFromAreas,
        isisSysStatAttmptToExMaxSeqNums,
        isisSysStatSeqNumSkips,
        isisSysStatOwnLSPPurges,
        isisSysStatIDFieldLenMismatches,
        isisSysStatPartChanges,
        isisSysStatSPFRuns,
        isisSysStatAuthTypeFails,
        isisSysStatAuthFails,
        isisSysStatLSPErrors
    STATUS current
    DESCRIPTION
        "The collections of objects used to manage an
         IS-IS router."
::= { isisGroups 1 }
isisCircuitGroup OBJECT-GROUP
    OBJECTS {
        isisNextCircIndex,
        isisCircAdminState,
        isisCircExistState,
        isisCircType,
        isisCircExtDomain,
```

```
isisCircLevelType,
        isisCircAdjChanges,
        isisCircNumAdj,
        isisCircInitFails,
        isisCircRejAdjs,
        isisCircIDFieldLenMismatches,
        isisCircMaxAreaAddrMismatches,
        isisCircAuthTypeFails,
        isisCircAuthFails,
        isisCircLANDesISChanges,
        isisCircPassiveCircuit,
        isisCircMeshGroupEnabled,
        isisCircMeshGroup,
        isisCircSmallHellos,
        isisCircLastUpTime,
        isisCirc3WayEnabled,
        isisCircExtendedCircID,
        isisCircIfIndex,
        isisCircLevelMetric,
        isisCircLevelWideMetric,
        isisCircLevelISPriority,
        isisCircLevelIDOctet,
        isisCircLevelID,
        isisCircLevelDesIS,
        isisCircLevelHelloMultiplier,
        isisCircLevelHelloTimer,
        isisCircLevelDRHelloTimer,
       isisCircLevelLSPThrottle,
        isisCircLevelMinLSPRetransInt,
        isisCircLevelCSNPInterval,
        isisCircLevelPartSNPInterval
    STATUS current
    DESCRIPTION
        "The collections of objects used to describe an
        IS-IS Circuit."
::= { isisGroups 2 }
isisISAdjGroup OBJECT-GROUP
    OBJECTS {
        isisISAdjState,
        isisISAdj3WayState,
        isisISAdjNeighSNPAAddress,
        isisISAdjNeighSysType,
        isisISAdjNeighSysID,
        isisISAdjNbrExtendedCircID,
        isisISAdjUsage,
        isisISAdjHoldTimer,
```

```
isisISAdjNeighPriority,
        isisISAdjLastUpTime,
        isisISAdjAreaAddress,
        isisISAdjIPAddrType,
        isisISAdjIPAddrAddress,
        isisISAdjProtSuppProtocol
    STATUS current
   DESCRIPTION
        "The collections of objects used to manage an
        IS-IS Adjacency."
::= { isisGroups 3 }
isisNotificationObjectGroup OBJECT-GROUP
   OBJECTS {
        isisNotificationSysLevelIndex,
        isisNotificationCircIfIndex,
        isisPduLspId,
        isisPduFragment,
        isisPduFieldLen,
        isisPduMaxAreaAddress,
        isisPduProtocolVersion,
        isisPduLspSize,
        isisPduOriginatingBufferSize,
        isisPduBufferSize,
        isisPduProtocolsSupported,
        isisAdjState,
       isisErrorOffset,
        isisErrorTLVType,
       isisNotificationAreaAddress
    }
    STATUS current
    DESCRIPTION
        "The objects used to record notification parameters."
::= { isisGroups 4 }
isisNotificationGroup
                            NOTIFICATION-GROUP
   NOTIFICATIONS {
        isisDatabaseOverload,
        isisManualAddressDrops,
        isisCorruptedLSPDetected,
        isisAttemptToExceedMaxSequence,
        isisIDLenMismatch,
        isisMaxAreaAddressesMismatch,
        isisOwnLSPPurge,
        isisSequenceNumberSkip,
        isisAuthenticationTypeFailure,
```

```
isisAuthenticationFailure,
       isisVersionSkew,
        isisAreaMismatch,
       isisRejectedAdjacency,
        isisLSPTooLargeToPropagate,
        isisOrigLSPBuffSizeMismatch,
        isisProtocolsSupportedMismatch,
        isisAdjacencyChange,
        isisLSPErrorDetected
    }
    STATUS current
   DESCRIPTION
        "The collections of notifications sent by an IS."
::= { isisGroups 5 }
isisISPDUCounterGroup OBJECT-GROUP
   OBJECTS {
       isisPacketCountIIHello,
        isisPacketCountISHello,
       isisPacketCountESHello,
       isisPacketCountLSP,
       isisPacketCountCSNP,
        isisPacketCountPSNP,
        isisPacketCountUnknown
    STATUS current
   DESCRIPTION
        "The collections of objects used to count protocol PDUs."
::= { isisGroups 6 }
isisRATableGroup OBJECT-GROUP
   OBJECTS {
       isisRAExistState,
       isisRAAdminState,
       isisRAAddrPrefix,
        isisRAMapType,
        isisRAMetric,
       isisRAMetricType,
       isisRASNPAAddress,
        isisRASNPAMask,
       isisRASNPAPrefix,
       isisRAType
    }
    STATUS current
    DESCRIPTION
        "The collections of objects used to manage the
```

```
reachable NSAP prefixes."
::= { isisGroups 7 }
isisISIPRADestGroup OBJECT-GROUP
    OBJECTS {
        isisIPRANextHopType,
        isisIPRANextHop,
       isisIPRAType,
        isisIPRAExistState,
        isisIPRAAdminState,
        isisIPRAMetric,
       isisIPRAFullMetric,
       isisIPRAMetricType,
       isisIPRASNPAAddress,
       isisIPRASourceType
    STATUS current
   DESCRIPTION
        "The collections of objects used to manage configured
        IP addresses."
::= { isisGroups 8 }
isisLSPGroup OBJECT-GROUP
   OBJECTS {
       isisLSPSeq,
       isisLSPZeroLife,
       isisLSPChecksum,
       isisLSPLifetimeRemain,
       isisLSPPDULength,
       isisLSPAttributes,
        isisLSPTLVSeq,
        isisLSPTLVChecksum,
        isisLSPTLVType,
       isisLSPTLVLen,
       isisLSPTLVValue
    STATUS current
   DESCRIPTION
        "The collections of objects used to observe the LSP
        Database."
::= { isisGroups 9 }
```

Parker Standards Track [Page 95]

END

5. IANA Considerations

The MIB module in this document uses the following IANA-assigned OBJECT IDENTIFIER values recorded in the SMI Numbers registry:

Descriptor	OBJECT	IDENTIFIER	value
isisMIB	{ mib-2	2 138 }	

6. Acknowledgements

This MIB is based on a March 1994 document by Chris Gunner, who should be held blameless for the errors introduced since then. This version has been modified to include MIB-II syntax, to exclude portions of the protocol that are not relevant to IP, such as the ES-IS protocol, and to add management support for current practice.

We would like to thank the following individuals for constructive and valuable comments: Mike Bartlett, Neal Castagnoli, Ken Chapman, Joan Cucchiara, Satish Dattatri, Nagi Jonnala, Adrian Farrel, Shamik Ganguly, Les Ginsberg, Don Goodspeed, Jeff Gross, Jim Halpin, Jon Harrison, Dimitri Haskin, C. M. Heard, Peter Higginson, Christian Hopps, Laura Liu, Gavin McPherson, Kay Noguchi, Serge Maskalik, Z. Opalka, Jeff Pickering, Sundar Ramachandran, Swaminatha Ramalingam, Aravind Ravikumar, Juergen Schoenwaelder, Koen Vermeulen, Hans De Vleeschouwer, Bert Wijnen, and Bingzhang Zhao.

7. Security Considerations

Management information defined in this MIB may be considered sensitive in some network environments.

7.1. Discussion

This MIB may be used to manage an IP router, which is used to direct network traffic. The control of network traffic allows an attacker to deny service to a region of the network or to forward traffic to adversaries. By raising or lowering metrics, traffic may be directed to insecure portions of the network. By disabling the protocol on an interface, the network may be partitioned. Changes to the network topology will force all routers to recompute their routes. Periodic route changes have brought down networks in the past by subjecting routers to stressful recomputations.

There are a number of management objects defined in this MIB that have a MAX-ACCESS clause of read-write and/or read-create. Such objects may be considered sensitive or vulnerable in some network

Parker Standards Track [Page 96]

environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations. Authentication of received SNMP requests and controlled access to management information should be employed in such environments.

We identify a set of threats and then list attributes that can be used in each form of attack. We discuss the effects that can be obtained by a single change to the variable in each class.

7.2. Threats

- Drop an Adjacency
- Drop all Peers
- Drop Subnetwork
- Split the Network
- Intermittent Outages
- Redirect Traffic
- Delay Convergence
- Avoid Detection
- Prevent Updates
- Hijack LAN
- Create Problems for CLNS Networks

7.2.1. Drop an Adjacency

By changing attributes that are used to peer, we can disrupt an adjacency and bring a link down.

isisCirc3WayEnabled isisCircAdminState isisCircExistState isisCircLevelDRHelloTimer isisCircLevelHelloTimer isisCircLevelType isisCircSmallHellos

7.2.2. Drop All Adjacencies

These attributes can be used to break some or all of a router's adjacencies. In the case of System ID, the adjacency may be restored. However, it will subject the network to additional stress.

isisSysLevelType
isisManAreaAddrExistState
isisSysAdminState
isisSysID

7.2.3. Drop Subnetwork

This attribute can be used to stop advertisement of a subnetwork reachable through a single interface.

isisCircPassiveCircuit

7.2.4. Split the Network

If the network design depends upon Wide Metrics or TE, we can use these attributes to prevent traffic from passing through a router.

isisSysLevelMetricStyle isisSysLevelOrigLSPBuffSize isisSysLevelSPFConsiders isisSysLevelTEEnabled isisSysReceiveLSPBufferSize

7.2.5. Intermittent Outages

We can use these attributes to subject the network to a series of topology changes, or otherwise force extensive recomputations of routes.

isisSysLevelMinLSPGenInt isisSysLevelSetOverload isisSysLevelSetOverloadUntil isisSysMaxAge isisSysMaxLSPGenInt isisSysL2toL1Leaking isisSysID

7.2.6. Redirect Traffic

By changing attributes such as metrics, we can push traffic to different parts of the network. This may allow an intruder to observe data traffic from otherwise remote parts of the network.

We may also use these attributes to deny service to parts of the network.

isisSysMaxPathSplits isisCircLevelMetric isisCircLevelWideMetric isisIPRAAdminState isisIPRAExistState isisIPRAFullMetric isisIPRAMetric isisIPRAMetricType
isisIPRANextHop
isisIPRANextHopType
isisIPRASNPAAddress
isisIPRAType
isisRedistributeAddrExistState
isisSummAddrExistState
isisSummAddrFullMetric
isisSummAddrMetric
isisSysL2toL1Leaking

7.2.7. Delay Convergence

These attributes can be used to slow convergence by increasing the minimal interval required to update a packet.

isisCircLevelCSNPInterval
isisCircLevelLSPThrottle
isisCircLevelMinLSPRetransInt
isisCircLevelPartSNPInterval
isisSysWaitTime
isisCircPassiveCircuit

7.2.8. Avoid Detection

By turning off traps, we can prevent a Network Management station from observing problems in the network caused by other aspects of an attack.

isisSysNotificationEnable

7.2.9. Prevent Updates

Mesh Groups can be used to prevent the transmission of Link State PDUs on certain interfaces, delaying or preventing the propagation of updates.

isisCircMeshGroup
isisCircMeshGroupEnabled

7.2.10. Hijack LAN

If we have compromised a router, we can use this attribute to become the designated router and lie about the topology of a LAN.

isisCircLevelISPriority

7.2.11. Create Problems for CLNS Networks

This attribute can be used to modify the handling of CLNS traffic.

isisRAAddrPrefix
isisRAAdminState
isisRAExistState
isisRAMapType
isisRAMetric
isisRAMetricType
isisRASNPAAddress
isisRASNPAMask
isisRASNPAPrefix
isisRAType
isisSysPollESHelloRate

7.2.12. Mostly Harmless

The following writable attributes do not pose a known security risk.

isisCircExtDomain
isisCircExtendedCircID
isisCircIfIndex
isisCircLevelHelloMultiplier
isisCircType

7.2.13. Recommendations

Much of the MIB is used to set or read attributes which are readily visible to any intruder who has access to traffic. None of the security attributes are setable or visible through the MIB. Read access to the MIB does not pose additional risks or vulnerabilities.

If write access is to be provided, it is RECOMMENDED that implementers consider the security features as provided by the SNMPv3 framework (see [RFC3410], section 8), including full support for the SNMPv3 cryptographic mechanisms (for authentication and privacy).

SNMP versions prior to SNMPv3 did not include adequate security. Even if the network itself is secure (for example by using IPSec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB module.

Deployment of SNMP versions prior to SNMPv3 is NOT RECOMMENDED. Instead, it is RECOMMENDED to deploy SNMPv3 and to enable cryptographic security. It is then a customer/operator responsibility to ensure that the SNMP entity giving access to an

Parker Standards Track [Page 100]

instance of this MIB module is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

8. Normative References

- [ISO10589] ISO 10589, "Intermediate system to Intermediate system routeing information exchange protocol for use in conjunction with the Protocol for providing the Connectionless-mode Network Service (ISO 8473)," ISO/IEC 10589:2002.
- [ISO10733] ISO 10733, "Information Processing Systems Open Systems Interconnection Specification of the elements of Management Information related to OSI Network layer Standards", September 1998.
- [RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [RFC1195] Callon, R., "Use of OSI IS-IS for routing in TCP/IP and dual environments", RFC 1195, December 1990.
- [RFC2863] McCloghrie, K. and F. Kastenholz, "The Interfaces Group MIB", RFC 2863, June 2000.
- [RFC3289] Baker, F., Chan, K., and A. Smith, "Management Information Base for the Differentiated Services Architecture", RFC 3289, May 2002.
- [RFC3411] Harrington, D., Presuhn, R., and B. Wijnen, "An Architecture for Describing Simple Network Management Protocol (SNMP) Management Frameworks", STD 62, RFC 3411, December 2002.

[RFC4001] Daniele, M., Haberman, B., Routhier, S., and J. Schoenwaelder, "Textual Conventions for Internet Network Addresses", RFC 4001, February 2005.

9. Informative References

- [RFC2973] Balay, R., Katz, D., and J. Parker, "IS-IS Mesh Groups", RFC 2973, October 2000.
- [RFC3410] Case, J., Mundy, R., Partain, D., and B. Stewart,
 "Introduction and Applicability Statements for InternetStandard Management Framework", RFC 3410, December 2002.

Authors' Address

Jeff Parker Department of Computer Science Middlebury College, Middlebury, Vermont 05753

EMail: jeffp@middlebury.edu

Parker Standards Track [Page 102]

Full Copyright Statement

Copyright (C) The Internet Society (2006).

This document is subject to the rights, licenses and restrictions contained in BCP 78, and except as set forth therein, the authors retain all their rights.

This document and the information contained herein are provided on an "AS IS" basis and THE CONTRIBUTOR, THE ORGANIZATION HE/SHE REPRESENTS OR IS SPONSORED BY (IF ANY), THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Intellectual Property

The IETF takes no position regarding the validity or scope of any Intellectual Property Rights or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; nor does it represent that it has made any independent effort to identify any such rights. Information on the procedures with respect to rights in RFC documents can be found in BCP 78 and BCP 79.

Copies of IPR disclosures made to the IETF Secretariat and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementers or users of this specification can be obtained from the IETF on-line IPR repository at http://www.ietf.org/ipr.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights that may cover technology that may be required to implement this standard. Please address the information to the IETF at ietf-ipr@ietf.org.

Acknowledgement

Funding for the RFC Editor function is provided by the IETF Administrative Support Activity (IASA).