

Conditioning of linear systems

Saturday, December 6, 2025 7:35 PM

Short and important!

Spectral Norm

For a vector $\vec{x} \in \mathbb{R}^n$, we'll exclusively use the Euclidean norm $\|\vec{x}\|_2$

Def Euclidean norm $\|\vec{x}\|_2 = \sqrt{\sum_{i=1}^n |x_i|^2}$

hence the notation

aka the "distance formula" as it's called in algebra and calculus classes

There are many other types of norms which hopefully you saw in your linear algebra cla

For a matrix, there are also many norms (e.g., think of an $m \times n$ matrix as a length $m \cdot n$ vector)

but we'll focus on the most important norm you never heard of ...

click-bait for mathematicians

the spectral norm.

Def The spectral norm of a matrix A is

This was covered
in APPM 3310

$$\|A\|_2 := \max_{\vec{x} \neq 0} \frac{\|A\vec{x}\|_2}{\|\vec{x}\|_2} = \max_{\|\vec{x}\|_2=1} \|A\vec{x}\|_2$$

= maximum singular value of A

= $\sqrt{\text{maximum eigenvalue of } A^T A}$

we say it's "induced" by the Euclidean norm, hence the reason for writing $\|A\|_2$

The Olver et al. APPM 3310 book uses the term "natural" instead of "induced"

Given a matrix A , $\|A\|_2 = \max_{\vec{x} \neq 0} \frac{\|A\vec{x}\|_2}{\|\vec{x}\|_2}$

so for any particular $\vec{x} \neq 0$, $\frac{\|A\vec{x}\|_2}{\|\vec{x}\|_2} \leq \max_{\vec{x}' \neq 0} \frac{\|A\vec{x}'\|_2}{\|\vec{x}'\|_2} = \|A\|_2$

i.e., $\forall \vec{x} \neq 0, \frac{\|A\vec{x}\|_2}{\|\vec{x}\|_2} \leq \|A\|_2$ i.e., $\forall \vec{x}, \boxed{\|A\vec{x}\|_2 \leq \|A\|_2 \cdot \|\vec{x}\|_2}$

↑ Euclidean ↑ Spectral ↑ Euclidean

Fact (not essential for us): Spectral norm is sub-multiplicative, $\|AB\|_2 \leq \|A\|_2 \cdot \|B\|_2$

Frobenius norm, $\|A\|_F = \sqrt{\sum_{i,j} |A_{ij}|^2} = \sqrt{\text{tr}(A^T A)}$, $\|AB\|_F \leq \|A\|_2 \cdot \|B\|_F$

$\|A\|_F = \sqrt{\sum_{i,j} |A_{ij}|^2} \leq \sqrt{n} = \|A\|_2$, $\|AB\|_F \leq \|A\|_F \cdot \|B\|_2$

Frobenius norm
is also
submultiplicative

Condition number (i.e. relative condition number)

Recall if we're trying to compute $f(x)$, we perturb $\tilde{x} = x + \Delta x$

and the

relative condition number is $K_f(x) = \lim_{\Delta x \rightarrow 0}$

input output is $f(x)$

$$\frac{|f(x) - f(\tilde{x})|}{|f(x)|} \cdot \frac{1}{|\tilde{x} - x|} = \frac{1}{|x|} \Delta x$$

For solving linear equations $A\tilde{x} = \tilde{b}$, our input is \tilde{b} (or, \tilde{A} and \tilde{b} , but we'll focus on \tilde{b})

and our output is \tilde{x} , so " x " is now the output not the input!

(we had a similar issue in the root-finding case... this is just a multi-dimensional extension)

So, perturb $\tilde{b} = b + \Delta b$, and " $f(\tilde{b})$ " is \tilde{x} , i.e.,

$A\tilde{x} = \tilde{b}$. If we write $\tilde{x} = x + \Delta x$, then

$$A \cdot (x + \Delta x) = b + \Delta b$$

I'm going to stop writing \tilde{x} . Just remember it's a vector

$$\text{So } K_2(b) = \lim_{\|\Delta b\|_2 \rightarrow 0} \frac{\frac{\|x - \tilde{x}\|_2}{\|x\|_2}}{\frac{\|b - \tilde{b}\|_2}{\|b\|_2}} = \lim_{\|\Delta b\|_2 \rightarrow 0} \frac{\frac{\|\Delta x\|_2}{\|x\|_2}}{\frac{\|\Delta b\|_2}{\|b\|_2}}$$

we call it K_2 because we use Euclidean norm.

You can use other norms but K_2 is most common.

$$\text{Now, } A(x + \Delta x) = b + \Delta b \quad \text{and } Ax = b \quad \text{so } A \cdot \Delta x = \Delta b \\ \text{so } \underline{\Delta x = A^{-1} \cdot \Delta b}$$

Think back to $\|\cdot\|_2$ for matrices (spectral norm):

$$\text{so } \|\Delta x\|_2 = \|A^{-1} \Delta b\|_2 \leq \|A^{-1}\|_2 \cdot \|\Delta b\|_2$$

$$\boxed{\|A^{-1} \Delta b\|_2 \leq \|A^{-1}\|_2 \cdot \|\Delta b\|_2}$$

↓ ↑ ↓
Euclidean Spectral Euclidean

and in fact $\exists \Delta b$ s.t. $\|A^{-1} \Delta b\|_2 = \|A^{-1}\|_2 \cdot \|\Delta b\|_2$ so it can be tight.

So...

$$K_2(b) = \lim_{\|\Delta b\|_2 \rightarrow 0} \frac{\frac{\|\Delta x\|_2}{\|x\|_2}}{\frac{\|\Delta b\|_2}{\|b\|_2}} = \lim_{\|\Delta b\|_2 \rightarrow 0} \frac{\frac{\|\Delta x\|_2}{\|x\|_2} \cdot \|\Delta b\|_2}{\|\Delta b\|_2} = \lim_{\|\Delta b\|_2 \rightarrow 0} \frac{\|\Delta x\|_2}{\|x\|_2} \cdot \frac{\|\Delta b\|_2}{\|\Delta b\|_2}$$

$$\leq \lim_{\|\Delta b\|_2 \rightarrow 0} \frac{\|A^{-1}\|_2 \cdot \|\Delta b\|_2 \cdot \|\Delta b\|_2}{\|x\|_2 \cdot \|\Delta b\|_2} = \frac{\|A^{-1}\|_2 \cdot \|\Delta b\|_2}{\|x\|_2}$$

| and since $b = Ax$

$$\|\Delta b\|_2 = \|A\Delta x\|_2 \leq \|A\|_2 \cdot \|\Delta x\|_2 \quad (\text{same trick})$$

$$\leq \frac{\|A^{-1}\|_2 \cdot \|A\|_2 \cdot \|\Delta x\|_2}{\|x\|_2} = \frac{\|A^{-1}\|_2 \cdot \|A\|_2}{\|x\|_2}$$

This was a bound on $K_2(b)$.

In general, we define the condition number, independent of b , to be

$$K_2(A) := \|A^{-1}\|_2 \cdot \|A\|_2$$

↑
spectral norms

$$\|A^{-1}\|_2 \cdot \|A\|_2 = \frac{\text{largest singular value of } A}{\text{smallest singular value of } A}$$

(slight modification of relative condition number that we use for numerical linear algebra)

$$\left(\begin{array}{l} \text{if } A = A^T \\ = \frac{\max |\lambda|}{\min |\lambda|} \end{array} \right)$$

↑ eigenvalues of A

a measure of dynamic range in a sense.

Facts: $\|A\|_2 = \|A^T\|_2$ so $K_2(A) = K_2(A^T)$

$$\|A^T A\|_2 = \|A A^T\|_2 = \|A\|_2^2 \text{ so } K_2(A^T A) = K_2(A A^T) = K_2(A)^2$$

In Matlab, use `cond(A)` to find $K_2(A)$

In Python, it's `numpy.linalg.cond(A)`

So... $K_2(A)$ measures the inherent difficulty of solving $A\vec{x} = \vec{b}$

(it's also useful for other problems too)

We can't complain if our algorithm "loses" $\log_{10}(K_2(A))$ digits

but if our algorithm does worse than this, e.g., if we ever form an intermediate quantity with $K_2(A)^2$, then the algorithm is **unstable**, i.e., it's doing worse than it needs to.

As before, we're distinguishing:

Conditioning \longleftrightarrow math problem, i.e., find x s.t. $Ax = b$
 vs.
 Stability \longleftrightarrow algorithm / implementation