



tBits Collabwrite - Engineering Document Control and Project Monitoring System

Overview of Project Configuration on tBits CollabWrite for IMP GROUP





© Copyright 2011 - TransBit Technologies

Confidential computer software. Valid license from TransBit Technologies required for possession, use or copying. The information contained herein is subject to change without notice. The only warranties for TransBit Technologies products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. TransBit Technologies shall not be liable for technical or editorial errors or omissions contained herein.





Table of Contents Including List of Diagrams

List of BA's which can be used directly after importing4
List of BA's/Modules which needs configuration after importing4
Procedure to Configure Document Control Module5
Import of all BA's related to Document Control Module5
Naming Convention for Prefix of BA6
Creation of Users6
Creation of Mailing List with respect to each BA6
Change in Display Name of Fields/Types in BA's after importing7
Replicating Previous Project Transmittal Configuration to New Project7
Changes to be done after replicating the process9
Transmittal Process Params9
Post Transmittal Field Values10
Procedure to configure MoM Module12
Entries to me made in App Properties for MoM BA12
Entires to me made in Database for MoM BA12
Changes to be done in BA Properties for MoM
Numbering System for MoM14
Procedure to configure Technical Query BA15
Changes to be done in BA Properties for TQ BA16





List of BA's which can be used directly after exporting from previous project and importing into new project.

- 1. Task Tracking
- 2. Punch List
- 3. Extension of Time Request
- 4. Non Conformance Request
- 5. Site Instruction on IMP
- 6. Inspection and Test Plan
- 7. Hazard and Accident Incident Log

The only change which needs to be done in the above BA's is change the type value of Field called "Project". Give the value suiting to the current project.

List of BA's/Modules which needs configuration after exporting from previous project and importing into new project.

- 1. Document Control Module
- 2. Correspondence Module
- 3. Minutes of Meeting Module
- 4. Variation Order Request / FCN
- 5. Technical Query
- 6. Health and Safety Environment





Procedure to Configure Document Control Module

If the work flow is same as the previously configured project "FMG 2nd Outload Circuit SPF" DCM then we can replicate the same process for the upcoming projects with minimal changes.

Before replicating the process we have to make sure that the following things are done in tBits.

- 1. Import of all BA's related to Document Control from 2nd Outload Circuit Project
- 2. Naming Convention for prefix of BA [Sys prefix]
- 3. Creation of Users [including the Doc Controller for Each BA]
- 4. Creation of Mailing Lists w.r.t to each BA [Follow Naming Convention]
- 5. Change in Display Name of fields/type in each BA after importing [If required]

Import of all the BA's related to Document Control.

1. Export all the BA's related to Doc Control from 2nd Outload Circuit SPF Project into the system.

[FMG_IMP,FMG_HERZOG,FMG_EPCM,FMG_OWNER.FMG_SITE,FMG_DTN,FMG_DTNApp]

2. Now import the BA's one by one from your system [.XML format]



Note: Sys_prefix and Name should not have any spaces or special characters except underscore(_)

Email Id of BA for IMP project should be sys_prefix followed by impgroup.com.au [fmg_imp@impgroup.com.au]





Naming Convention for prefix of BA [Sys_prefix]

1. Generally we follow a naming convention for sys_prefix of BA , it starts with project code/name followed by name of BA.

[Eg: For Project "Christmas Creek Lab Equipment" the sys_prefix of IMP BA is "CCLE_IMP"]

Creation of Users [including the Doc Controller for Each BA]

- 1. All the users related to this particular project should be created in tBits.
- 2. Mention their email id, firm code, firm address etc after creating the user in "All Users" Admin Panel.
- 3. Also a doc controller user login should be created for each of the BA. The purpose of this user is it updates the doc/dwg from one BA to other BA.
- 4. After creating add the doc controllers in all DCM BA's and give the Role of DTN System user
- 5. Usually DTN System User Role has all the permissions.

[Eg: Doc controller for IMP in DCM "Christmas Creek Lab Equipment" is "dc_ccle_imp"]

Note: No Login name should have spaces and special characters except underscore and dot.

Creation of Mailing Lists w.r.t to each BA [Follow Naming Convention]

- 1. Create a Mailing List for each BA.
- 2. Add all the users who have access to this particular BA in this Mailing List.
- 3. In "Admin Panel", select the desired BA and click on BA users tab. Now add the mailing list in BA users and give the desired roles to the mailing list.

Note: Follow a Naming Convention for Mailing List so that a new administrator can easily understand to which BA the mailing list belongs to.

[Eg: The mailing list for IMP in DCM "Christmas Creek Lab Equipment" is "aus_002_ccle_imp_dtn_users"]

Change in Display Name of BA's/ fields /type in each BA after importing [If required]

1. After importing all the BA's, change the display name of BA's, fields and field types if required.





- Currently we have 5 BA's each relating to a company and one of them is Vendor "HERZOG", Later in another project if Vendor becomes "NWSM" then first export the BA of Vendor- HERZOG and import the BA again by changing the BA name, display name, sys_prefix to "NWSM", "NWSM-VENDOR", "CCLE_NWSM" respectively.
- 3. Now go to the BA and change the name of all the fields and types to "NWSM" where there was "HERZOG". Similarly with other BA's too
- 4. Type values should be mainly changed for field "Originator" in all BA's and for Field "Recipient" in DTN and DTNApp BA.

Replicating Previous Project Transmittal Configuration to New Project.

As the Work flow is same for both the Projects "FMG 2nd Outload Circuit SPF" and "Christmas Creek Lab Equipement" im replicating the configuration of former to the latter and it includes the following steps.

a. Click on "Transmittal" button in Administration Panel




Screen Shot 1






b. Select "Replicate Process"




Screen Shot 2

 Select a Transmittal Process which needs to be replicated and also Select the Source BA for New Process



Screen Shot 3

- d. After the selection, you get three colums Parameter, Selected Process value, New process Value.
- e. By Comparing the Selected Process Values give the Corresponding New Process Values and Click Save.



Screen Shot 4

f. Replication of Process is successfully done.





g. Similarly replicate the other processes based on Work Flow.


Changes which needs to be done after replicating the process

After successful replication of process, few changes have to be done in mainly two tables

- 1. Transmittal Process Params
- 2. Post Transmittal Field Values

Transmittal Process Params

- 1. Select Transmittal in Admin Panel
- 2. Select Transmittal Process Params under Transmittal




Screen Shot 5

- 3. Now select the newly configured process [the replicated process]
- 4. After selecting it displays the values for each parameter in the table
- 5. Verify each and every parameter and its value
- 6. Change the value according to the new project.








Screen Shot 6

Post Transmittal Field Values

- 1. Select Transmittal in Admin Panel
- 2. Select Post Transmittal under Transmittal



Screen Shot 7





- 3. Now select the newly configured process [the replicated process]
- 4. After selecting it displays the values for each parameter in the table
- 5. Verify each and every parameter and its value
- 6. Change the value according to the new project.



Screen Shot 8





Procedure to Configure Minutes of Meeting Module Import the BA of MoM.

Export the BA of MoM from 2nd Outload Circuit SPF Project into the system.

[FMG MoM]]

Now import the BA from your system [.XML format]

Note: Sys_prefix and Name should not have any spaces or special characters except underscore(_)

Email Id of BA for IMP project should be sys_prefix followed by impgroup.com.au [fmg_mom@impgroup.com.au]

As sys_prefix of MoM for earlier project was "FMG_MoM", this time I name it as "CCLE_MoM"

Entries to be done in App Properties for MoM

The exact sys_prefix value of newly created MoM BA has to be given in App Properties "MOM_Prefixes". If you have multiple MoM BA's then give the values separated by comma.



Entries to be done in Database for MoM

After making the entries in App Properties, some of the entries have to be made in Database.

- Know the sys_id of the BA [select * from business_areas where sys_prefix='CCLE_MoM']
- 2. By executing the above query I found out that sys_id is 38 of CCLE_MoM BA.
- 3. Now execute the below query in database table "mom_templates"






insert into mom_templates values (38,0,0,1,'imp_mom_template.rptdesign')
insert into mom_templates values (38,0,0,0,'imp_mom_MomAgendaTemplate.rptdesign')
insert into mom_templates values (38,6,1,1,'imp_mom_template.rptdesign')
insert into mom_templates values (38,6,2,1,'imp_mom_template.rptdesign')
insert into mom_templates values (38,6,6,1,'imp_mom_template.rptdesign')
insert into mom_templates values (38,6,7,1,'imp_mom_template.rptdesign')
insert into mom_templates values (38,6,8,1,'imp_mom_template.rptdesign')
insert into mom_templates values (38,6,9,1,'imp_mom_template.rptdesign')
insert into mom_templates values (38,6,10,1,'imp_mom_template.rptdesign')

- 4. Where 38 is the sys_id in the query.[Put the sys_id of you MoM BA]
- 5. Note: The sys id may be different when you import the BA.
- 6. Rest of the values remain same.

Changes to be done in BA Properties for MoM.

 As BA has been imported, the BA Property description will be the same as previous project MoM BA. So change the description for the new MoM BA by giving the Project Name.



- 2. Generally the Agenda and Meeting Auto generated PDF files pick the Project Name from the description of BA Properties.
- 3. So template will be common for all MoM BA's

13








Permissions to MoM


- 1. They are different roles in MoM
- 2. Give the permissions as per roles to each user.
- 3. Eg: Project Director will get the role of Project Director and you can change the permissions of that particular role as suitable to you.

Numbering System for MoM

1. In Admin Panel, Click BA fields Tab, Select field "Meeting Type" and click on its Types.



- 2. Now Type Tab opens,in Type Description specify your MoM Numbering format
- 3. [Eg: for Internal Meeting Type,I want the No. to be "IM-IMP-001" so I give "IM-IMP" in type description and Save.]



14





Procedure to Configure Technical Query [TQ] Import the BA of TQ.

1. Export the BA of TQ from 2nd Outload Circuit SPF Project into the system.

[[FMG TechQuery]]

2. Now import the BA from your system [.XML format]

Note: Sys_prefix and Name should not have any spaces or special characters except underscore(_)

Email Id of BA for IMP project should be sys_prefix followed by impgroup.com.au [fmg_techquery@impgroup.com.au]

As sys_prefix of TQ for earlier project was "FMG_TechQuery", this time I name it as "CCLE_TQ"

Entries to be done in Database for MoM

- 1. Some entries have to be made in "trn_change_note_configuration" table
- 2. Select * from trn_change_note_configuration

	change_note_id	src_sys_prefix	ba_type	target_sys_prefix	caption	template_name	src_attachment_field_id	target_attachment_field_id
1	1	FMG_IMP	DCN	FMG_FCN	Create FCN	fcn_template.rptdesign	0	0
2	2	FMG_IMP	TECH_QUERY	FMG_TechQuery	Create Tech Query	technical_query.rptdesign	0	0

- 3. The above value is showed when the query is executed, by the help of the query we can know the maximum number of column "change_note_id", The max number is 2 and next entry is 3.
- 4. Now insert the following query for new Tech Query entry in DB
- 5. insert into trn change note configuration values

(3,'CCLE_IMP','TECH_QUERY','CCLE_TQ','Create TechQuery','technical_query.rptdesign',0,0)

	change_note_id	src_sys_prefix	ba_type	target_sys_prefix	caption	template_name	src_attachment_field_id	target_attachment_field_id
1	1	FMG_IMP	DCN	FMG_FCN	Create FCN	fcn_template.rptdesign	0	0
2	2	FMG IMP	TECH QUERY	FMG TechQuery	Create Tech Querv	technical auerv.rptdesian	0	0
3	3	CCLE_IMP	TECH_QUERY	CCLE_TQ	Create TechQuery	technical_query.rptdesign	0	0

- 6. In the above result first column is change_note_id which should be unique and incremented by one
- 7. Second column is sys prefix of IMP BA from DCM.
- 8. Fourth column is sys prefix of Tech Query.
- 9. Now execute [Select * from trn_change_note_field_map]





	src_sys_id	template_field_name	field_name
1	4	subject	subject
2	4	drawingNumber	VendorNo
3	4	Revision	Revision

Now Execute

insert into trn_change_note_field_map values (32,'subject','subject')

insert into trn_change_note_field_map values (32,'drawingNumber','VendorNo')

insert into trn change note field map values (32, 'Revision', 'Revision')

	src_sys_id	template_field_name	field_name
1	4	subject	subject
2	4	drawingNumber	VendorNo
3	4	Revision	Revision
4	32	subject	subject
5	32	drawingNumber	VendorNo
6	32	Revision	Revision


Here Src_sys_id 4 is the sys_id of IMP BA [DCM] in Project FMG 2nd Outload Circuit SPF and src_sys_id 32 is the sys_id of IMP BA [DCM] from Project Christmas Creek Lab Equipment.

update business_areas set type='CC-CO-OP-0010-IMP-' where sys_id=39

Here sys id 39 is that of Tech Query BA.

Changes to be done in BA Properties for TQ.

 As BA has been imported, the BA Property description will be the same as previous project TQ BA. So change the description for the new TQ BA by giving the Project Name.



- Generally the TQ PDF files pick the Project Name from the description of BA Properties.
- 6. So template will be common for all TQ BA'