

Network Configuration Compliance

Assessed 75 device(s) against 15 controls · Generated 2026-09-15T19:07:18 · Controls version 320e51b


Executive Summary

Overall Configuration Posture: HIGH RISK. 75 network device(s) were evaluated against 15 configuration controls. Strict verified compliance is 68.9% with 100.0% assessment coverage. 75 device(s) contain unresolved deviations. TACACS represents the largest systemic gap.

Key Metrics

68.9% STRICT COMPLIANCE	100.0% ASSESSMENT COVERAGE
75 DEVICES ASSESSED	0 FULLY COMPLIANT DEVICES
75 DEVICES WITH FINDINGS	0 CRITICAL FINDINGS
350 FAILED CHECKS	0 APPROVED EXCEPTIONS
0 ASSESSMENT ERRORS	

Device Posture



- Fully Compliant: 0
- Compliant With Approved Exceptions: 0
- Needs Remediation: 75
- Critical Non-Compliant: 0
- Not Fully Assessed: 0

Findings by Severity

Critical		0 finding(s)
High		259 finding(s)
Medium		82 finding(s)
Low		9 finding(s)

Compliance by Control

Sorted lowest compliance first.

control_00004 - TACACS		0.0% (0/75) · 75 affected
control_00008 - ACL for VTY		0.0% (0/75) · 75 affected
control_00014 - VTY Lines		0.0% (0/75) · 75 affected
control_00009 - NTP		1.3% (1/75) · 74 affected
control_00002 - Domain		93.3% (70/75) · 5 affected
control_00005 - Local and emergency users		93.3% (70/75) · 5 affected
control_00006 - SSH		93.3% (70/75) · 5 affected
control_00007 - Global password encryption		93.3% (70/75) · 5 affected
control_00010 - Syslog		93.3% (70/75) · 5 affected
control_00011 - SNMP		93.3% (70/75) · 5 affected
control_00013 - Passwords		93.3% (70/75) · 5 affected
control_00015 - Local user and enable secret		93.3% (70/75) · 5 affected
control_00001 - Hostname		94.7% (71/75) · 4 affected
control_00003 - AAA		94.7% (71/75) · 4 affected
control_00012 - Banners		96.0% (72/75) · 3 affected


Top Failing Controls

CONTROL	FAILURES	CUMULATIVE %	SEVERITY
control_00004 - TACACS	75	21.4%	HIGH
control_00008 - ACL for VTY	75	42.9%	HIGH
control_00014 - VTY Lines	75	64.3%	HIGH
control_00009 - NTP	74	85.4%	MEDIUM
control_00002 - Domain	5	86.9%	LOW
control_00005 - Local and emergency users	5	88.3%	HIGH
control_00006 - SSH	5	89.7%	HIGH
control_00007 - Global password encryption	5	91.1%	HIGH
control_00010 - Syslog	5	92.6%	MEDIUM
control_00011 - SNMP	5	94.0%	HIGH

Top Non-Compliant Devices

DEVICE	COMPLIANCE	FAILED CONTROLS	CRITICAL?
domain_config_01	60.0% (9/15)	6	
emergency_user_config_03	60.0% (9/15)	6	
emergency_user_config_05	60.0% (9/15)	6	
aaa_config_02	66.7% (10/15)	5	
aaa_config_03	66.7% (10/15)	5	
aaa_config_04	66.7% (10/15)	5	
aaa_config_05	66.7% (10/15)	5	
banner_config_01	66.7% (10/15)	5	
banner_config_03	66.7% (10/15)	5	
banner_config_05	66.7% (10/15)	5	

Compliance Trend



3 run(s) in history (compliance_history/).

[illegible]

DEVICE	01	02	03	04	05	06	07	08	09	10	11
NTP_CONFIG_03											
NTP_CONFIG_04											
NTP_CONFIG_05											
SSH_CONFIG_03											
TACACS_CONFIG_01											
TACACS_CONFIG_02											
TACACS_CONFIG_03											
TACACS_CONFIG_04											
TACACS_CONFIG_05											
VTY_LINES_CONFIG_01											
VTY_LINES_CONFIG_02											
VTY_LINES_CONFIG_03											
VTY_LINES_CONFIG_04											
VTY_LINES_CONFIG_05											
AAA_CONFIG_01											

Legend: PASS FAIL APPROVED_EXCEPTION N_A MANUAL_REVIEW ASSESSMENT_ERROR NOT_ASSESSED

Device Detail

domain_config_01 - 60.0% (9/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	No 'ip domain name' command found in device configuration. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	FAIL	HIGH	IP domain-name is not configured. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.

MEDIUM

CONTROL	STATUS	SEVERITY	FINDING
control_00009 - NTP	FAIL		'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

emergency_user_config_03 - 60.0% (9/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA			All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	No local emergency user with 'algorithm-type scrypt' found. Remediation: Configure a local admin user and 'enable secret' using high-security hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	FAIL	HIGH	Local administrator username 'admin_bckp' does not match the corporate standard 'admin'. Remediation: Ensure an 'enable secret' and a privilege 15 local administrator account are present and secured.

emergency_user_config_05 - 60.0% (9/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as

CONTROL	STATUS	SEVERITY	FINDING
			specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	No local emergency user with 'algorithm-type scrypt' found. Remediation: Configure a local admin user and 'enable secret' using high-security hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to

CONTROL	STATUS	SEVERITY	FINDING
			secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	FAIL	HIGH	Local administrator username 'admin_bckp' does not match the corporate standard 'admin'. Remediation: Ensure an 'enable secret' and a privilege 15 local administrator account are present and secured.

aaa_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	FAIL	HIGH	Required AAA command missing (expected to match '^aaa accounting exec default start-stop group \S+').; Required AAA command missing (expected to match '^aaa accounting commands 1 default start-stop group \S+').; Required AAA command missing (expected to match '^aaa accounting commands 15 default start-stop group \S+'). Remediation: Implement the full AAA suite (Authentication, Authorization, and Accounting) pointing to the authorized TACACS group.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as

CONTROL	STATUS	SEVERITY	FINDING
			specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a

CONTROL	STATUS	SEVERITY	FINDING
			password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

aaa_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	FAIL	HIGH	AAA commands reference inconsistent TACACS groups: ['ACME_TACACS_GROUP', 'ACME_TACACS_SERVER_GROUP']. Remediation: Implement the full AAA suite (Authentication, Authorization, and Accounting) pointing to the authorized TACACS group.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

aaa_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	FAIL	HIGH	Required AAA command missing (expected to match '^aaa authentication login default group \S+ local'). Remediation: Implement the full AAA suite (Authentication, Authorization, and Accounting) pointing to the authorized TACACS group.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
FAIL		MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00009 - NTP			'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

aaa_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
	FAIL	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA			Required AAA command missing (expected to match '^aaa authorization commands 1 default group \S+ if-authenticated'). Remediation: Implement the full AAA suite (Authentication, Authorization, and Accounting) pointing to the authorized TACACS group.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	FAIL	MEDIUM	'banner motd' is not configured. Remediation: Configure a 'banner motd' containing approved legal language regarding authorized access and monitoring.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords			'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	FAIL	MEDIUM	'banner motd' opening delimiter '\$' has no matching closing '\$' - the banner is malformed/incomplete. Remediation: Configure a 'banner motd' containing approved legal language regarding authorized access and monitoring.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication

CONTROL	STATUS	SEVERITY	FINDING
			default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found

CONTROL	STATUS	SEVERITY	FINDING
			'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	FAIL	MEDIUM	'banner motd' is not configured. Remediation: Configure a 'banner motd' containing approved legal language regarding authorized access and monitoring.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

domain_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	Domain 'name othercorp.net' does not match the corporate domain 'name acme.com'. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

CONTROL	STATUS	SEVERITY	FINDING
			Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

domain_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	Domain 'acme.com' does not match the corporate domain 'name acme.com'. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
	FAIL	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00004 - TACACS			'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
	PASS	MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00012 - Banners			'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

domain_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	Domain 'name acem.com' does not match the corporate domain 'name acme.com'. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.

CONTROL	STATUS	SEVERITY	FINDING
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication

CONTROL	STATUS	SEVERITY	FINDING
			default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

domain_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	Domain 'name acme.org' does not match the corporate domain 'name acme.com'. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.

CONTROL	STATUS	SEVERITY	FINDING
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

emergency_user_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	No local emergency user with 'algorithm-type scrypt' found. Remediation: Configure a local admin user and 'enable secret' using high-security hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two

CONTROL	STATUS	SEVERITY	FINDING
			reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

emergency_user_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02':

CONTROL	STATUS	SEVERITY	FINDING
			address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	Emergency user 'admin_bckp': privilege level is '7', expected 15. Remediation: Configure a local admin user and 'enable secret' using high-security hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords			'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

emergency_user_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	Emergency user name 'admin_bkup' does not match the corporate standard 'admin_bckp'. Remediation: Configure a local admin user and 'enable secret' using high-security

CONTROL	STATUS	SEVERITY	FINDING
			hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

hostname_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	FAIL	LOW	Hostname 'Router' is generic.; Hostname 'Router' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts). Remediation: Configure the hostname following the corporate naming convention: hostname <COMPANY>_<COUNTRY>_<TYPE>_<FUNCTION>_<SITE>_<DEVICE>
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate key specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands in the running configuration.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, in the configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference for authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference for authentication key.

CONTROL	STATUS	SEVERITY	FINDING
			reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'ntp authentication-key' command to set the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15' 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines on console and 'login authentication default' on VTY; restrict transport to secure protocols; bind VTY lines to a named ACL via 'access-class'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

hostname_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	FAIL	LOW	Hostname 'ACME_USA_RT' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts). Remediation: Configure the hostname following the corporate naming convention: <COMPANY>_<COUNTRY>_<TYPE>_<FUNCTION>_<SITE>_<DEVICE>
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate key-chains specified by the security policy, using Type 6 key encryption instead of Type 7.
	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00005 - Local and emergency users			
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, in the configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the first as the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; apply 'login authentication default' on console and 'login authentication default' on VTY; restrict transport to secure protocols; bind VTY lines to a named ACL via 'access-class'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration

hostname_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
	FAIL	LOW	

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname			Hostname 'ACME-USA-RT-INT-GOLDEN-01' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts). Remediation: Configure the hostname following the corporate naming convention: <COMPANY>_<COUNTRY>_<TYPE>_<FUNCTION>_<SITE>_<DEVICE>
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate key chain specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands in the running configuration.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, in the configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the corporate-standard NTP servers as the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output in the running configuration.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15' 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines on console and 'login authentication default' on VTY; restrict transport output to secure protocols; bind VTY lines to a named ACL via 'access-class'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

hostname_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	FAIL	LOW	Hostname 'ACME_USA_Router_INT_GOLDEN_01': Type should be a short device-class code (e.g. 'RT', 'SW', 'WL', 'FW'), not a spelled-out word. Remediation: Configure the hostname following the corporate naming convention: <COMPANY>_<COUNTRY>_<TYPE>_<FUNCTION>_<SITE>_<ID>
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate key chain specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
		HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00008 - ACL for VTY	FAIL		ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, in the configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the first as the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15 transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines on console and 'login authentication default' on VTY; restrict transport to secure protocols; bind VTY lines to a named ACL via 'access-class'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

local_admin_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02':

CONTROL	STATUS	SEVERITY	FINDING
			address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	FAIL	HIGH	Local administrator 'admin': privilege level is '1', expected 15. Remediation: Ensure an 'enable secret' and a privilege 15 local administrator account are present and secured.

local_admin_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user	FAIL	HIGH	'enable secret' uses a weak/guessable value. Remediation: Ensure an 'enable secret'

CONTROL	STATUS	SEVERITY	FINDING
and enable secret			and a privilege 15 local administrator account are present and secured.

local_admin_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the

CONTROL	STATUS	SEVERITY	FINDING
			NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	FAIL	HIGH	Local administrator username 'administrator' does not match the corporate standard 'admin'. Remediation: Ensure an 'enable secret' and a privilege 15 local administrator account are present and secured.

password_encryption_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA			All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	FAIL	HIGH	'key config-key password-encrypt <device_master_key>' is missing.; 'password encryption aes' is missing. Remediation: Apply 'key config-key password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.

CONTROL	STATUS	SEVERITY	FINDING
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_encryption_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers

CONTROL	STATUS	SEVERITY	FINDING
			with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	FAIL	HIGH	'key config-key password-encrypt <device_master_key>' is missing. Remediation: Apply 'key config-key password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15':

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines			'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_encryption_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global	FAIL	HIGH	'password encryption aes' is missing. Remediation: Apply 'key config-key

CONTROL	STATUS	SEVERITY	FINDING
password encryption			password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_encryption_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	FAIL	HIGH	'key config-key password-encrypt' uses a weak/guessable master key value. Remediation: Apply 'key config-key password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>'

CONTROL	STATUS	SEVERITY	FINDING
			reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_encryption_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	FAIL	HIGH	'key config-key password-encrypt <device_master_key>' is missing. Remediation: Apply 'key config-key password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
	PASS	MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00012 - Banners			'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
emergency users			
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	FAIL	HIGH	'security passwords min-length' is not configured.; 'service password-encryption' is missing. Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication

CONTROL	STATUS	SEVERITY	FINDING
			default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found

CONTROL	STATUS	SEVERITY	FINDING
			'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	FAIL	HIGH	'security passwords min-length' is set to 4, below the required minimum of 10. Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	FAIL	HIGH	'security passwords min-length' is set to 9, below the required minimum of 10. Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server

CONTROL	STATUS	SEVERITY	FINDING
			address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
	FAIL	HIGH	'security passwords min-length' is not configured.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords			Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	FAIL	HIGH	'security passwords min-length' is not configured. Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

snmp_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard

CONTROL	STATUS	SEVERITY	FINDING
			ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	FAIL	HIGH	SNMPv3 group with 'priv' is not configured.; SNMPv3 user is not created with SHA/AES configuration.; SNMP trap host is missing.; 'snmp-server enable traps' command is missing.; An SNMPv1/v2c community string ('snmp-server community') coexists with the SNMPv3 configuration. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES) exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

CONTROL	STATUS	SEVERITY	FINDING
and enable secret			

snmp_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the

CONTROL	STATUS	SEVERITY	FINDING
			NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	FAIL	HIGH	'snmp-server enable traps' command is missing. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES) exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

snmp_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
	FAIL	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00011 - SNMP			SNMPv3 group with 'priv' is not configured.; 'snmp-server user' references group 'acme_snmp_grp01', which has no matching 'snmp-server group acme_snmp_grp01 v3 priv' definition. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES) exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

snmp_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server

CONTROL	STATUS	SEVERITY	FINDING
			address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	FAIL	HIGH	'snmp-server user' references group 'acme_snmp_group01', which has no matching 'snmp-server group acme_snmp_group01 v3 priv' definition. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES)

CONTROL	STATUS	SEVERITY	FINDING
			exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

snmp_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.

CONTROL	STATUS	SEVERITY	FINDING
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	FAIL	HIGH	SNMPv3 user is not created with SHA/AES configuration. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES) exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to

CONTROL	STATUS	SEVERITY	FINDING
			secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ssh_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	FAIL	HIGH	'crypto key generate rsa modulus <bits>' is missing - SSH cannot function without it. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

CONTROL	STATUS	SEVERITY	FINDING
---------	--------	----------	---------

and enable secret			
-------------------	--	--	--

ssh_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
---------	--------	----------	---------

control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
-----------------------------	------	-----	---

control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
---------------------------	------	-----	--

control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
------------------------	------	------	--

control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
---------------------------	------	------	---

control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
--	------	------	--

control_00006 - SSH	FAIL	HIGH	'ip ssh version' is set to '1', expected '2' per corporate standard. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.
------------------------	------	------	---

control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
---	------	------	--

control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
--------------------------------	------	------	--

CONTROL	STATUS	SEVERITY	FINDING
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ssh_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	FAIL	HIGH	'ip ssh authentication-retries' is set to '10', expected '3' per corporate standard. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.

CONTROL	STATUS	SEVERITY	FINDING
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ssh_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers

CONTROL	STATUS	SEVERITY	FINDING
			with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	FAIL	HIGH	'ip ssh time-out' is set to '300', expected '60' per corporate standard. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	FAIL	MEDIUM	'logging on' command is missing.; Logging host IP address is missing.; Logging trap level is not set to 'informational'.; 'logging source-interface' is not configured. Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard

CONTROL	STATUS	SEVERITY	FINDING
			ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	FAIL	MEDIUM	Logging host IP address is missing. Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
FAIL		MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00010 - Syslog			Logging trap level is not set to 'informational'. Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	FAIL	MEDIUM	'logging source-interface' ('source-interface gigabitethernet0/1') does not match the corporate standard ('source-interface loopback0'). Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	FAIL	MEDIUM	Logging host '30.30.30.101' does not match the corporate syslog server '30.30.30.100'. Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and

CONTROL	STATUS	SEVERITY	FINDING
			output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	No 'ip access-list extended' block found in the running configuration. Remediation: Apply the corporate-standard

CONTROL	STATUS	SEVERITY	FINDING
			ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; ACL 'ACME_VTY_MGMT_ACL' referenced by access-class was not found in the configuration. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
	PASS	LOW	

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname			The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; 'line vty 0 15': no 'access-class' ACL is bound to this VTY line. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs

CONTROL	STATUS	SEVERITY	FINDING
			server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL name 'ACME_VTY_MGT_ACL' does not match the corporate ACL name 'ACME_VTY_MGMT_ACL'; ACL 'ACME_VTY_MGT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; ACL 'ACME_VTY_MGMT_ACL' referenced by access-class was not found in the configuration. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
emergency users			'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule 'permit ip 0.0.0.0 255.255.255.255 any' uses a wildcard mask (255.255.255.255) that is functionally equivalent to 'any', defeating the

CONTROL	STATUS	SEVERITY	FINDING
			purpose of the management ACL.; ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip 0.0.0.0 255.255.255.255 any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

hostname_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

CONTROL	STATUS	SEVERITY	FINDING
---------	--------	----------	---------

and enable secret			
-------------------	--	--	--

local_admin_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
---------	--------	----------	---------

control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
-----------------------------	------	-----	---

control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
---------------------------	------	-----	--

control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
------------------------	------	------	--

control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
---------------------------	------	------	---

control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
--	------	------	--

control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
------------------------	------	------	---

control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
---	------	------	--

control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
--------------------------------	------	------	--

control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the
------------------------	------	--------	---

CONTROL	STATUS	SEVERITY	FINDING
			NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

local_admin_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
	PASS	MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00012 - Banners			'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
emergency users			
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	NTP server configuration is missing.; NTP authentication is not configured ('ntp authenticate' / 'ntp authentication-key' / 'ntp trusted-key' missing). Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard

CONTROL	STATUS	SEVERITY	FINDING
			ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA			All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'prefer' keyword is missing on the primary NTP server.; 'ntp server 10.10.10.100': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as

CONTROL	STATUS	SEVERITY	FINDING
			specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	NTP authentication is not configured ('ntp authenticate' / 'ntp authentication-key' / 'ntp trusted-key' missing). Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication

CONTROL	STATUS	SEVERITY	FINDING
			default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found

CONTROL	STATUS	SEVERITY	FINDING
			'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp trusted-key 2' does not match 'ntp authentication-key 1'.; 'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ssh_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	Fewer than two 'tacacs server' definitions found.; 'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.

CONTROL	STATUS	SEVERITY	FINDING
			Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15':

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines			'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; No 'ip tacacs source-interface' configured under the TACACS server group. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running

CONTROL	STATUS	SEVERITY	FINDING
password encryption			configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_01': timeout '30' does not match the corporate standard '10'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>'

CONTROL	STATUS	SEVERITY	FINDING
			reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.; 'aaa group server tacacs+ ACME_TACACS_SERVER_GROUP': references server 'ACME_TACACS_2', which has no matching 'tacacs server ACME_TACACS_2' definition. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as

CONTROL	STATUS	SEVERITY	FINDING
			specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a

CONTROL	STATUS	SEVERITY	FINDING
			password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any

CONTROL	STATUS	SEVERITY	FINDING
			173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport input' is not restricted to secure protocols.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line con 0': 'exec-timeout 0 0' disables session timeout entirely (sessions never expire).; 'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'exec-timeout 0 0' disables session timeout entirely (sessions never expire).; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
	FAIL	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00004 - TACACS			'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
	PASS	MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00012 - Banners			'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
emergency users			
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line con 0': 'exec-timeout 20 0' (20 minute(s)) exceeds the corporate policy maximum of 10 minute(s).; 'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'exec-timeout 20 0' (20 minute(s)) exceeds the corporate policy maximum of 10 minute(s).; 'line vty 0 15': 'transport output' is not restricted to secure protocols.

CONTROL	STATUS	SEVERITY	FINDING
			Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.

CONTROL	STATUS	SEVERITY	FINDING
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; 'line vty 0 15': 'access-class ACME_VTY_MGMT_ACL' is missing the required 'in' direction keyword. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

aaa_config_01 - 80.0% (12/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'deny ip any 173.245.48.0 0.0.15.255'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	PASS	MEDIUM	'ntp server' lines, 'ntp authenticate'/'ntp authentication-key' lines, and 'show ntp associations' output.
PASS		MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00010 - Syslog			'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': password is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

Control Detail

control_00001 - Hostname (94.7% compliant, 4 affected)		
DEVICE	STATUS	FINDING
hostname_config_01	FAIL	Hostname 'Router' is generic.; Hostname 'Router' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts).
hostname_config_02	FAIL	Hostname 'ACME_USA_RT' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts).
hostname_config_03	FAIL	Hostname 'ACME-USA-RT-INT-GOLDEN-01' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts).
hostname_config_04	FAIL	Hostname 'ACME_USA_Router_INT_GOLDEN_01': Type field 'Router' should be a short device-class code (e.g. 'RT', 'SW', 'AP', 'PBX', 'FW'), not a spelled-out word.

control_00002 - Domain (93.3% compliant, 5 affected)		
DEVICE	STATUS	FINDING
domain_config_01	FAIL	No 'ip domain name' command found in device configuration.
domain_config_02	FAIL	Domain 'name othercorp.net' does not match the corporate domain 'name acme.com'.
domain_config_03	FAIL	Domain 'acme.com' does not match the corporate domain 'name acme.com'.
domain_config_04	FAIL	Domain 'name acem.com' does not match the corporate domain 'name acme.com'.
domain_config_05	FAIL	Domain 'name acme.org' does not match the corporate domain 'name acme.com'.

control_00003 - AAA (94.7% compliant, 4 affected)		
DEVICE	STATUS	FINDING
aaa_config_02	FAIL	Required AAA command missing (expected to match '^aaa accounting exec default start-stop group \S+'); Required AAA command missing (expected to match '^aaa accounting commands 1 default start-stop group \S+'); Required AAA command missing (expected to match '^aaa

DEVICE	STATUS	FINDING
		accounting commands 15 default start-stop group \S+').
aaa_config_03	FAIL	AAA commands reference inconsistent TACACS groups: ['ACME_TACACS_GROUP', 'ACME_TACACS_SERVER_GROUP'].
aaa_config_04	FAIL	Required AAA command missing (expected to match '^aaa authentication login default group \S+ local').
aaa_config_05	FAIL	Required AAA command missing (expected to match '^aaa authorization commands 1 default group \S+ if-authenticated').

control_00004 - TACACS (0.0% compliant, 75 affected)

DEVICE	STATUS	FINDING
aaa_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
aaa_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
aaa_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
aaa_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the

DEVICE	STATUS	FINDING
		corporate TACACS server address '192.168.100.102'.
aaa_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs

DEVICE	STATUS	FINDING
		server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

DEVICE	STATUS	FINDING
		match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
emergency_user_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.

DEVICE	STATUS	FINDING
emergency_user_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
emergency_user_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
emergency_user_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
emergency_user_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
hostname_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
hostname_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the

DEVICE	STATUS	FINDING
		corporate TACACS server address '192.168.100.102'.
hostname_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
hostname_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
hostname_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs

DEVICE	STATUS	FINDING
		server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

DEVICE	STATUS	FINDING
		match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_encryption_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_encryption_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_encryption_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_encryption_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.

DEVICE	STATUS	FINDING
password_encryption_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the

DEVICE	STATUS	FINDING
		corporate TACACS server address '192.168.100.102'.
snmp_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
snmp_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
snmp_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
snmp_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
snmp_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs

DEVICE	STATUS	FINDING
		server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

DEVICE	STATUS	FINDING
		match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
tacacs_config_01	FAIL	Fewer than two 'tacacs server' definitions found.; 'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.
tacacs_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; No 'ip tacacs source-interface' configured under the TACACS server group.

DEVICE	STATUS	FINDING
tacacs_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_01': timeout '30' does not match the corporate standard '10'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
tacacs_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
tacacs_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; 'aaa group server tacacs+ ACME_TACACS_SERVER_GROUP': references server 'ACME_TACACS_2', which has no matching 'tacacs server ACME_TACACS_2' definition.
vty_lines_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
vty_lines_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the

DEVICE	STATUS	FINDING
		corporate TACACS server address '192.168.100.102'.
vty_lines_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
vty_lines_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
vty_lines_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.

control_00005 - Local and emergency users (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
emergency_user_config_01	FAIL	No local emergency user with 'algorithm-type scrypt' found.
emergency_user_config_02	FAIL	Emergency user 'admin_bckp': privilege level is '7', expected 15.
emergency_user_config_03	FAIL	No local emergency user with 'algorithm-type scrypt' found.
emergency_user_config_04	FAIL	Emergency user name 'admin_bkup' does not match the corporate standard 'admin_bckp'.
emergency_user_config_05	FAIL	No local emergency user with 'algorithm-type scrypt' found.

control_00006 - SSH (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
domain_config_01	FAIL	IP domain-name is not configured.
ssh_config_01	FAIL	'crypto key generate rsa modulus <bits>' is missing - SSH cannot function without it.
ssh_config_02	FAIL	'ip ssh version' is set to '1', expected '2' per corporate standard.
ssh_config_04	FAIL	'ip ssh authentication-retries' is set to '10', expected '3' per corporate standard.
ssh_config_05	FAIL	'ip ssh time-out' is set to '300', expected '60' per corporate standard.

control_00007 - Global password encryption (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
password_encryption_config_01	FAIL	'key config-key password-encrypt <device_master_key>' is missing.; 'password encryption aes' is missing.
password_encryption_config_02	FAIL	'key config-key password-encrypt <device_master_key>' is missing.
password_encryption_config_03	FAIL	'password encryption aes' is missing.
password_encryption_config_04	FAIL	'key config-key password-encrypt' uses a weak/guessable master key value.
password_encryption_config_05	FAIL	'key config-key password-encrypt <device_master_key>' is missing.

control_00008 - ACL for VTY (0.0% compliant, 75 affected)

DEVICE	STATUS	FINDING
aaa_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'deny ip any 173.245.48.0 0.0.15.255'.

DEVICE	STATUS	FINDING
aaa_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
aaa_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
aaa_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
aaa_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
acl_vty_config_01	FAIL	No 'ip access-list extended' block found in the running configuration.
acl_vty_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
acl_vty_config_03	FAIL	ACL name 'ACME_VTY_MGT_ACL' does not match the corporate ACL name 'ACME_VTY_MGMT_ACL'; ACL 'ACME_VTY_MGT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
acl_vty_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
acl_vty_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule 'permit ip 0.0.0.0 255.255.255.255 any' uses a wildcard mask (255.255.255.255) that is functionally equivalent to 'any', defeating the purpose of the management ACL.; ACL

DEVICE	STATUS	FINDING
		'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip 0.0.0.0 255.255.255.255 any'.
banner_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
banner_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
banner_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
banner_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
banner_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any

DEVICE	STATUS	FINDING
		173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.

DEVICE	STATUS	FINDING
local_admin_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
local_admin_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
local_admin_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
local_admin_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
local_admin_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any

DEVICE	STATUS	FINDING
		173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
snmp_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.

DEVICE	STATUS	FINDING
snmp_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
snmp_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
snmp_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
snmp_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any

DEVICE	STATUS	FINDING
		173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
vty_lines_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
vty_lines_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.

DEVICE	STATUS	FINDING
vty_lines_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
vty_lines_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
vty_lines_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.

control_00009 - NTP (1.3% compliant, 74 affected)

DEVICE	STATUS	FINDING
aaa_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
aaa_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
aaa_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
aaa_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100':

DEVICE	STATUS	FINDING
		missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
banner_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
banner_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
banner_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
banner_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
banner_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.;

DEVICE	STATUS	FINDING
		'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
hostname_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
hostname_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
hostname_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
hostname_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
hostname_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ntp_config_01	FAIL	NTP server configuration is missing.; NTP authentication is not configured ('ntp

DEVICE	STATUS	FINDING
		authenticate' / 'ntp authentication-key' / 'ntp trusted-key' missing).
ntp_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.
ntp_config_03	FAIL	'prefer' keyword is missing on the primary NTP server.; 'ntp server 10.10.10.100': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ntp_config_04	FAIL	NTP authentication is not configured ('ntp authenticate' / 'ntp authentication-key' / 'ntp trusted-key' missing).
ntp_config_05	FAIL	'ntp trusted-key 2' does not match 'ntp authentication-key 1'; 'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_encryption_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_encryption_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_encryption_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
password_encryption_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_encryption_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.;

DEVICE	STATUS	FINDING
		'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ssh_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ssh_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ssh_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
ssh_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ssh_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.;

DEVICE	STATUS	FINDING
		'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
vty_lines_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
vty_lines_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
vty_lines_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
vty_lines_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
vty_lines_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

control_00010 - Syslog (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
syslog_config_01	FAIL	'logging on' command is missing.; Logging host IP address is missing.; Logging trap level is not set to 'informational'.; 'logging source-interface' is not configured.
syslog_config_02	FAIL	Logging host IP address is missing.
syslog_config_03	FAIL	Logging trap level is not set to 'informational'.
syslog_config_04	FAIL	'logging source-interface' ('source-interface gigabitethernet0/1') does not match the corporate standard ('source-interface loopback0').
syslog_config_05	FAIL	Logging host '30.30.30.101' does not match the corporate syslog server '30.30.30.100'.

control_00011 - SNMP (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
snmp_config_01	FAIL	SNMPv3 group with 'priv' is not configured.; SNMPv3 user is not created with SHA/AES configuration.; SNMP trap host is missing.; 'snmp-server enable traps' command is missing.; An SNMPv1/v2c community string ('snmp-server community') coexists with the SNMPv3 configuration.
snmp_config_02	FAIL	'snmp-server enable traps' command is missing.
snmp_config_03	FAIL	

DEVICE	STATUS	FINDING
		SNMPv3 group with 'priv' is not configured.; 'snmp-server user' references group 'acme_snmp_grp01', which has no matching 'snmp-server group acme_snmp_grp01 v3 priv' definition.
snmp_config_04	FAIL	'snmp-server user' references group 'acme_snmp_group01', which has no matching 'snmp-server group acme_snmp_group01 v3 priv' definition.
snmp_config_05	FAIL	SNMPv3 user is not created with SHA/AES configuration.

control_00012 - Banners (96.0% compliant, 3 affected)

DEVICE	STATUS	FINDING
banner_config_01	FAIL	'banner motd' is not configured.
banner_config_03	FAIL	'banner motd' opening delimiter '\$' has no matching closing '\$' - the banner is malformed/incomplete.
banner_config_05	FAIL	'banner motd' is not configured.

control_00013 - Passwords (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
password_policy_config_01	FAIL	'security passwords min-length' is not configured.; 'service password-encryption' is missing.
password_policy_config_02	FAIL	'security passwords min-length' is set to 4, below the required minimum of 10.
password_policy_config_03	FAIL	'security passwords min-length' is set to 9, below the required minimum of 10.
password_policy_config_04	FAIL	'security passwords min-length' is not configured.
password_policy_config_05	FAIL	'security passwords min-length' is not configured.

control_00014 - VTY Lines (0.0% compliant, 75 affected)

DEVICE	STATUS	FINDING
aaa_config_01	FAIL	'line vty 0 15': password is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
aaa_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
aaa_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
aaa_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
aaa_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
acl_vty_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; ACL 'ACME_VTY_MGMT_ACL' referenced by access-class was not found in the configuration.
acl_vty_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; 'line vty 0 15': no 'access-class' ACL is bound to this VTY line.
acl_vty_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.;

DEVICE	STATUS	FINDING
		ACL 'ACME_VTY_MGMT_ACL' referenced by access-class was not found in the configuration.
acl_vty_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
acl_vty_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
domain_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.

DEVICE	STATUS	FINDING
domain_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
domain_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
domain_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
domain_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15':

DEVICE	STATUS	FINDING
		'transport output' is not restricted to secure protocols.
hostname_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
hostname_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
hostname_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
hostname_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
hostname_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_04	FAIL	'line vty 0 15': 'login authentication default' is

DEVICE	STATUS	FINDING
		missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_encryption_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_encryption_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.

DEVICE	STATUS	FINDING
password_encryption_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_encryption_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_encryption_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
snmp_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15':

DEVICE	STATUS	FINDING
		'transport output' is not restricted to secure protocols.
snmp_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
snmp_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
snmp_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
snmp_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_05	FAIL	'line vty 0 15': 'login authentication default' is

DEVICE	STATUS	FINDING
		missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
tacacs_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
tacacs_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
tacacs_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.

DEVICE	STATUS	FINDING
tacacs_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
tacacs_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport input' is not restricted to secure protocols.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_02	FAIL	'line con 0': 'exec-timeout 0 0' disables session timeout entirely (sessions never expire).; 'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'exec-timeout 0 0' disables session timeout entirely (sessions never expire).; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_04	FAIL	'line con 0': 'exec-timeout 20 0' (20 minute(s)) exceeds the corporate policy maximum of 10 minute(s).; 'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'exec-timeout 20 0' (20 minute(s)) exceeds the corporate policy maximum of 10 minute(s).; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_05		

DEVICE	STATUS	FINDING
	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; 'line vty 0 15': 'access-class ACME_VTY_MGMT_ACL' is missing the required 'in' direction keyword.

control_00015 - Local user and enable secret (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
emergency_user_config_03	FAIL	Local administrator username 'admin_bckp' does not match the corporate standard 'admin'.
emergency_user_config_05	FAIL	Local administrator username 'admin_bckp' does not match the corporate standard 'admin'.
local_admin_config_02	FAIL	Local administrator 'admin': privilege level is '1', expected 15.
local_admin_config_03	FAIL	'enable secret' uses a weak/ guessable value.
local_admin_config_05	FAIL	Local administrator username 'administrator' does not match the corporate standard 'admin'.

Findings & Remediation

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	aaa_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'd 0.0.15.255'.
HIGH	aaa_config_01	control_00014 - VTY Lines	'line vty 0 15': password is missing not restricted to secure protocols.
HIGH	aaa_config_02	control_00003 - AAA	Required AAA command missing (accounting exec default start-stop command missing (expected to match default start-stop group \S+).; Required AAA command missing (expected to match '^aaa accounting group \S+').
HIGH	aaa_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	aaa_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	aaa_config_03	control_00003 - AAA	AAA commands reference inconsistent ['ACME_TACACS_GROUP', 'ACME
HIGH	aaa_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	aaa_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	aaa_config_04	control_00003 - AAA	Required AAA command missing (authentication login default group '')

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	aaa_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	aaa_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	aaa_config_05	control_00003 - AAA	Required AAA command missing (authorization commands 1 default
HIGH	aaa_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	aaa_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	acl_vty_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_01	control_00008 - ACL for VTY	No 'ip access-list extended' block f
HIGH	acl_vty_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t 'ACME_VTY_MGMT_ACL' referen found in the configuration.
HIGH	acl_vty_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	acl_vty_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t no 'access-class' ACL is bound to
HIGH	acl_vty_config_03		'tacacs server ACME_TACACS_02' not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
		control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_03	control_00008 - ACL for VTY	ACL name 'ACME_VTY_MGT_ACL' not match the corporate ACL name 'ACME_VTY_MGMT_ACL'. ACL name 'ACME_VTY_MGMT_ACL' rule #1: 'deny ip any 0.0.15.255', found 'permit ip any any'.
HIGH	acl_vty_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration. 'transport output' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration.
HIGH	acl_vty_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule #1: 'deny ip 173.245.48.0 0.0.15.255', found 'permit ip any any'.
HIGH	acl_vty_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration. 'transport output' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration.
HIGH	acl_vty_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule #1: 'deny ip 255.255.255.255 any' uses a wildcard that is functionally equivalent to 'any', not expected in management ACL.; ACL 'ACME_VTY_MGMT_ACL' rule #2: 'deny ip 173.245.48.0 0.0.15.255', expected 'deny ip any 173.245.48.0 0.0.15.255'.
HIGH	acl_vty_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration. 'transport output' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration.
HIGH	banner_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule #1: 'deny ip 173.245.48.0 0.0.15.255', found 'permit ip any any'.
HIGH	banner_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration. 'transport output' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration.
HIGH	banner_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
			'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	banner_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	banner_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	banner_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	banner_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	banner_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	banner_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	banner_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	domain_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_01	control_00006 - SSH	IP domain-name is not configured.
HIGH	domain_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	domain_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	domain_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	domain_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	domain_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	domain_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	domain_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	domain_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	domain_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	domain_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	emergency_user_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	emergency_user_config_01	control_00005 - Local and emergency users	No local emergency user with 'algo
HIGH	emergency_user_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	emergency_user_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	emergency_user_config_02	control_00005 - Local and emergency users	Emergency user 'admin_bckp': pri
HIGH	emergency_user_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	emergency_user_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	emergency_user_config_03	control_00005 - Local and emergency users	No local emergency user with 'algo
HIGH	emergency_user_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	emergency_user_config_03	control_00015 - Local user and enable secret	Local administrator username 'adr corporate standard 'admin'.
HIGH	emergency_user_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
			'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	emergency_user_config_04	control_00005 - Local and emergency users	Emergency user name 'admin_bkp' not match standard 'admin_bckp'.
HIGH	emergency_user_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	emergency_user_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	emergency_user_config_05	control_00005 - Local and emergency users	No local emergency user with 'algorithm
HIGH	emergency_user_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	emergency_user_config_05	control_00015 - Local user and enable secret	Local administrator username 'admin' not match corporate standard 'admin'.
HIGH	hostname_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	hostname_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	hostname_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	hostname_config_02		

PRIORITY	DEVICE	CONTROL	FINDING
		control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	hostname_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	hostname_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	hostname_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	hostname_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	hostname_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	hostname_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	local_admin_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	local_admin_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	local_admin_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
			'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	local_admin_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	local_admin_config_02	control_00015 - Local user and enable secret	Local administrator 'admin': privile
HIGH	local_admin_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	local_admin_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	local_admin_config_03	control_00015 - Local user and enable secret	'enable secret' uses a weak/guess
HIGH	local_admin_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	local_admin_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	local_admin_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	local_admin_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	local_admin_config_05	control_00015 - Local user and enable secret	Local administrator username 'admin' does not match corporate standard 'admin'.
HIGH	ntp_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured 'transport output' is not restricted to
HIGH	ntp_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured 'transport output' is not restricted to
HIGH	ntp_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured 'transport output' is not restricted to
HIGH	ntp_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured 'transport output' is not restricted to
HIGH	ntp_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
			'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_encryption_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	password_encryption_config_01	control_00007 - Global password encryption	'key config-key password-encrypt' 'password encryption aes' is missi
HIGH	password_encryption_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_encryption_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	password_encryption_config_02	control_00007 - Global password encryption	'key config-key password-encrypt
HIGH	password_encryption_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_encryption_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	password_encryption_config_03	control_00007 - Global password encryption	'password encryption aes' is missi
HIGH	password_encryption_config_03		

PRIORITY	DEVICE	CONTROL	FINDING
		control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	password_encryption_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	password_encryption_config_04	control_00007 - Global password encryption	'key config-key password-encrypt' key value.
HIGH	password_encryption_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	password_encryption_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	password_encryption_config_05	control_00007 - Global password encryption	'key config-key password-encrypt
HIGH	password_encryption_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	password_policy_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	password_policy_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_01	control_00013 - Passwords	'security passwords min-length' is encryption' is missing.
HIGH	password_policy_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	password_policy_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	password_policy_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_02	control_00013 - Passwords	'security passwords min-length' is minimum of 10.
HIGH	password_policy_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_policy_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_03' not match the corporate TACACS 'tacacs server ACME_TACACS_03' not match the corporate TACACS
HIGH	password_policy_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_03	control_00013 - Passwords	'security passwords min-length' is minimum of 10.
HIGH	password_policy_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_policy_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_04' not match the corporate TACACS 'tacacs server ACME_TACACS_04' not match the corporate TACACS
HIGH	password_policy_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_04	control_00013 - Passwords	'security passwords min-length' is
HIGH	password_policy_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_policy_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_05' not match the corporate TACACS 'tacacs server ACME_TACACS_05' not match the corporate TACACS
HIGH	password_policy_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_05		'security passwords min-length' is

PRIORITY	DEVICE	CONTROL	FINDING
		control_00013 - Passwords	
HIGH	password_policy_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not found, 'transport output' is not restricted to local connections.
HIGH	snmp_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS server, 'tacacs server ACME_TACACS_02' not match the corporate TACACS server.
HIGH	snmp_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_01	control_00011 - SNMP	SNMPv3 group with 'priv' is not configured, created with SHA/AES configuration, 'snmp-server enable traps' command not found, community string ('snmp-server community') not found, SNMPv3 configuration.
HIGH	snmp_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not found, 'transport output' is not restricted to local connections.
HIGH	snmp_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS server, 'tacacs server ACME_TACACS_02' not match the corporate TACACS server.
HIGH	snmp_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_02	control_00011 - SNMP	'snmp-server enable traps' command not found, community string ('snmp-server community') not found, SNMPv3 configuration.
HIGH	snmp_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not found, 'transport output' is not restricted to local connections.
HIGH	snmp_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS server, 'tacacs server ACME_TACACS_02' not match the corporate TACACS server.
HIGH	snmp_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_03	control_00011 - SNMP	SNMPv3 group with 'priv' is not configured, references group 'acme_snmp_group', 'snmp-server group acme_snmp_group' not found, community string ('snmp-server community') not found, SNMPv3 configuration.
HIGH	snmp_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not found, 'transport output' is not restricted to local connections.

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	snmp_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	snmp_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_04	control_00011 - SNMP	'snmp-server user' references group has no matching 'snmp-server group' definition.
HIGH	snmp_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	snmp_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	snmp_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_05	control_00011 - SNMP	SNMPv3 user is not created with S
HIGH	snmp_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	ssh_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ssh_config_01	control_00006 - SSH	'crypto key generate rsa modulus' function without it.
HIGH	ssh_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	ssh_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ssh_config_02	control_00006 - SSH	'ip ssh version' is set to '1', expected

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	ssh_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	ssh_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_0 not match the corporate TACACS 'tacacs server ACME_TACACS_0 not match the corporate TACACS
HIGH	ssh_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	ssh_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0 not match the corporate TACACS 'tacacs server ACME_TACACS_0 not match the corporate TACACS
HIGH	ssh_config_04	control_00006 - SSH	'ip ssh authentication-retries' is set standard.
HIGH	ssh_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	ssh_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0 not match the corporate TACACS 'tacacs server ACME_TACACS_0 not match the corporate TACACS
HIGH	ssh_config_05	control_00006 - SSH	'ip ssh time-out' is set to '300', exp
HIGH	ssh_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_0 not match the corporate TACACS 'tacacs server ACME_TACACS_0 not match the corporate TACACS
HIGH	syslog_config_01		

PRIORITY	DEVICE	CONTROL	FINDING
		control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	syslog_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	syslog_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	syslog_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	syslog_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	tacacs_config_01	control_00004 - TACACS	

PRIORITY	DEVICE	CONTROL	FINDING
			Fewer than two 'tacacs server' defined. ACME_TACACS_01: address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
HIGH	tacacs_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	tacacs_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS No 'ip tacacs source-interface' configured. No 'aaa group server tacacs+ ACME_
HIGH	tacacs_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	tacacs_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_03' not match the corporate TACACS 'tacacs server ACME_TACACS_03' not match the corporate TACACS corporate standard '10'.; 'tacacs server address '192.168.100.101' does not match the corporate standard server address '192.168.100.102'.
HIGH	tacacs_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	tacacs_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_04' not match the corporate TACACS 'tacacs server ACME_TACACS_04' not match the corporate TACACS
HIGH	tacacs_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	tacacs_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_05' not match the corporate TACACS 'tacacs server ACME_TACACS_05' not match the corporate TACACS 'aaa group server tacacs+ ACME_

PRIORITY	DEVICE	CONTROL	FINDING
			references server 'ACME_TACACS_02' but not 'tacacs server ACME_TACACS_02'
HIGH	tacacs_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication tacacs' is not restricted to 'transport output' is not restricted to
HIGH	vty_lines_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	vty_lines_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication tacacs' is not restricted to 'transport input' is not restricted to 'transport output' is not restricted to
HIGH	vty_lines_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	vty_lines_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_02	control_00014 - VTY Lines	'line con 0': 'exec-timeout 0 0' disabled (sessions never expire).; 'line vty 0 15': 'exec-timeout 0 0' missing.; 'line vty 0 15': 'exec-timeout 0 0' missing entirely (sessions never expire).; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
HIGH	vty_lines_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	vty_lines_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication tacacs' is not restricted to 'transport output' is not restricted to
HIGH	vty_lines_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	vty_lines_config_04		

PRIORITY	DEVICE	CONTROL	FINDING
		control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_04	control_00014 - VTY Lines	'line con 0': 'exec-timeout 20 0' (20 policy maximum of 10 minute(s).; ' default' is missing.; 'line vty 0 15': exceeds the corporate policy maxi 15': 'transport output' is not restrict
HIGH	vty_lines_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	vty_lines_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t 'access-class ACME_VTY_MGMT direction keyword.
MEDIUM	aaa_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	aaa_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	aaa_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	aaa_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_04	control_00009 - NTP	

PRIORITY	DEVICE	CONTROL	FINDING
			'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_01	control_00012 - Banners	'banner motd' is not configured.
MEDIUM	banner_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_03	control_00012 - Banners	'banner motd' opening delimiter '\$' banner is malformed/incomplete.
MEDIUM	banner_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_05	control_00012 - Banners	'banner motd' is not configured.
MEDIUM	domain_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	domain_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	domain_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	domain_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	domain_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	local_admin_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	local_admin_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	local_admin_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	local_admin_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	local_admin_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	ntp_config_01	control_00009 - NTP	NTP server configuration is missing 'ntp authentication-key' / 'ntp trusted-key' (key missing).
MEDIUM	ntp_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.
MEDIUM	ntp_config_03	control_00009 - NTP	'prefer' keyword is missing on the 'ntp server 10.10.10.100': missing a 'key' / 'authentication-key' / 'ntp trusted-key' reference to the NTP authentication key.
MEDIUM	ntp_config_04	control_00009 - NTP	NTP authentication is not configured on the 'ntp server 10.10.10.100' (missing 'authentication-key' / 'ntp trusted-key').
MEDIUM	ntp_config_05	control_00009 - NTP	'ntp trusted-key 2' does not match the 'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	password_policy_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	password_policy_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	password_policy_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	password_policy_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	password_policy_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	ssh_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	ssh_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	ssh_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	ssh_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server' reference to the NTP authentication
MEDIUM	ssh_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server' reference to the NTP authentication
MEDIUM	syslog_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server' reference to the NTP authentication
MEDIUM	syslog_config_01	control_00010 - Syslog	'logging on' command is missing.; missing.; Logging trap level is not set to 'info' source-interface' is not configured
MEDIUM	syslog_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server' reference to the NTP authentication
MEDIUM	syslog_config_02	control_00010 - Syslog	Logging host IP address is missing
MEDIUM	syslog_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server' reference to the NTP authentication
MEDIUM	syslog_config_03	control_00010 - Syslog	Logging trap level is not set to 'info'
MEDIUM	syslog_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server' reference to the NTP authentication
MEDIUM	syslog_config_04	control_00010 - Syslog	'logging source-interface' ('source-interface' not match the corporate standard
MEDIUM	syslog_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server' reference to the NTP authentication
MEDIUM	syslog_config_05	control_00010 - Syslog	Logging host '30.30.30.101' does not match server '30.30.30.100'.
MEDIUM	tacacs_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server' reference to the NTP authentication
MEDIUM	tacacs_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server' reference to the NTP authentication

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	tacacs_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	tacacs_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	tacacs_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
LOW	domain_config_01	control_00002 - Domain	No 'ip domain name' command fou
LOW	domain_config_02	control_00002 - Domain	Domain 'name othercorp.net' does 'name acme.com'.
LOW	domain_config_03	control_00002 - Domain	Domain 'acme.com' does not matc acme.com'.
LOW	domain_config_04	control_00002 - Domain	Domain 'name acem.com' does no 'name acme.com'.
LOW	domain_config_05	control_00002 - Domain	Domain 'name acme.org' does not 'name acme.com'.
LOW	hostname_config_01	control_00001 - Hostname	Hostname 'Router' is generic.; Hos COMPANY_COUNTRY_TYPE_FU convention (expected at least 6 un

PRIORITY	DEVICE	CONTROL	FINDING
LOW	hostname_config_02	control_00001 - Hostname	Hostname 'ACME_USA_RT' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION convention (expected at least 6 underscores)
LOW	hostname_config_03	control_00001 - Hostname	Hostname 'ACME-USA-RT-INT-GW' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION convention (expected at least 6 underscores)
LOW	hostname_config_04	control_00001 - Hostname	Hostname 'ACME_USA_Router_1' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION convention. 'Router' should be a short device-category (e.g., 'AP', 'PBX', 'FW'), not a spelled-out name.