

Network Configuration Compliance

Assessed 75 device(s) against 15 controls · Generated 2026-09-15T19:38:46 · Controls version 320e51b


Executive Summary

Overall Configuration Posture: HIGH RISK. 75 network device(s) were evaluated against 15 configuration controls. Strict verified compliance is 68.9% with 100.0% assessment coverage. 75 device(s) contain unresolved deviations. TACACS represents the largest systemic gap.

Key Metrics

68.9% STRICT COMPLIANCE	100.0% ASSESSMENT COVERAGE
75 DEVICES ASSESSED	0 FULLY COMPLIANT DEVICES
75 DEVICES WITH FINDINGS	0 CRITICAL FINDINGS
350 FAILED CHECKS	0 APPROVED EXCEPTIONS
0 ASSESSMENT ERRORS	

Device Posture



- Fully Compliant: 0
- Compliant With Approved Exceptions: 0
- Needs Remediation: 75
- Critical Non-Compliant: 0
- Not Fully Assessed: 0

Findings by Severity

Critical		0 finding(s)
High		259 finding(s)
Medium		82 finding(s)
Low		9 finding(s)

Compliance by Control

Sorted lowest compliance first.

control_00004 - TACACS		0.0% (0/75) · 75 affected
control_00008 - ACL for VTY		0.0% (0/75) · 75 affected
control_00014 - VTY Lines		0.0% (0/75) · 75 affected
control_00009 - NTP		1.3% (1/75) · 74 affected
control_00002 - Domain		93.3% (70/75) · 5 affected
control_00005 - Local and emergency users		93.3% (70/75) · 5 affected
control_00006 - SSH		93.3% (70/75) · 5 affected
control_00007 - Global password encryption		93.3% (70/75) · 5 affected
control_00010 - Syslog		93.3% (70/75) · 5 affected
control_00011 - SNMP		93.3% (70/75) · 5 affected
control_00013 - Passwords		93.3% (70/75) · 5 affected
control_00015 - Local user and enable secret		93.3% (70/75) · 5 affected
control_00001 - Hostname		94.7% (71/75) · 4 affected
control_00003 - AAA		94.7% (71/75) · 4 affected
control_00012 - Banners		96.0% (72/75) · 3 affected


Top Failing Controls

CONTROL	FAILURES	CUMULATIVE %	SEVERITY
control_00004 - TACACS	75	21.4%	HIGH
control_00008 - ACL for VTY	75	42.9%	HIGH
control_00014 - VTY Lines	75	64.3%	HIGH
control_00009 - NTP	74	85.4%	MEDIUM
control_00002 - Domain	5	86.9%	LOW
control_00005 - Local and emergency users	5	88.3%	HIGH
control_00006 - SSH	5	89.7%	HIGH
control_00007 - Global password encryption	5	91.1%	HIGH
control_00010 - Syslog	5	92.6%	MEDIUM
control_00011 - SNMP	5	94.0%	HIGH

Top Non-Compliant Devices

DEVICE	COMPLIANCE	FAILED CONTROLS	CRITICAL?
domain_config_01	60.0% (9/15)	6	
emergency_user_config_03	60.0% (9/15)	6	
emergency_user_config_05	60.0% (9/15)	6	
aaa_config_02	66.7% (10/15)	5	
aaa_config_03	66.7% (10/15)	5	
aaa_config_04	66.7% (10/15)	5	
aaa_config_05	66.7% (10/15)	5	
banner_config_01	66.7% (10/15)	5	
banner_config_03	66.7% (10/15)	5	
banner_config_05	66.7% (10/15)	5	

Compliance Trend



4 run(s) in history (compliance_history/).

[illegible]

DEVICE	01	02	03	04	05	06	07	08	09	10	11
											
NTP_CONFIG_03											
NTP_CONFIG_04											
NTP_CONFIG_05											
SSH_CONFIG_03											
TACACS_CONFIG_01											
TACACS_CONFIG_02											
TACACS_CONFIG_03											
TACACS_CONFIG_04											
TACACS_CONFIG_05											
VTY_LINES_CONFIG_01											
VTY_LINES_CONFIG_02											
VTY_LINES_CONFIG_03											
VTY_LINES_CONFIG_04											
VTY_LINES_CONFIG_05											
AAA_CONFIG_01											

Legend:  PASS  FAIL  APPROVED_EXCEPTION  N_A  MANUAL_REVIEW  ASSESSMENT_ERROR  NOT_ASSESSED

Device Detail

domain_config_01 - 60.0% (9/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	No 'ip domain name' command found in device configuration. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	FAIL	HIGH	IP domain-name is not configured. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.

MEDIUM

CONTROL	STATUS	SEVERITY	FINDING
control_00009 - NTP	FAIL		'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

emergency_user_config_03 - 60.0% (9/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA			All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	No local emergency user with 'algorithm-type scrypt' found. Remediation: Configure a local admin user and 'enable secret' using high-security hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	FAIL	HIGH	Local administrator username 'admin_bckp' does not match the corporate standard 'admin'. Remediation: Ensure an 'enable secret' and a privilege 15 local administrator account are present and secured.

emergency_user_config_05 - 60.0% (9/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as

CONTROL	STATUS	SEVERITY	FINDING
			specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	No local emergency user with 'algorithm-type scrypt' found. Remediation: Configure a local admin user and 'enable secret' using high-security hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to

CONTROL	STATUS	SEVERITY	FINDING
			secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	FAIL	HIGH	Local administrator username 'admin_bckp' does not match the corporate standard 'admin'. Remediation: Ensure an 'enable secret' and a privilege 15 local administrator account are present and secured.

aaa_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	FAIL	HIGH	Required AAA command missing (expected to match '^aaa accounting exec default start-stop group \S+').; Required AAA command missing (expected to match '^aaa accounting commands 1 default start-stop group \S+').; Required AAA command missing (expected to match '^aaa accounting commands 15 default start-stop group \S+'). Remediation: Implement the full AAA suite (Authentication, Authorization, and Accounting) pointing to the authorized TACACS group.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as

CONTROL	STATUS	SEVERITY	FINDING
			specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a

CONTROL	STATUS	SEVERITY	FINDING
			password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

aaa_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	FAIL	HIGH	AAA commands reference inconsistent TACACS groups: ['ACME_TACACS_GROUP', 'ACME_TACACS_SERVER_GROUP']. Remediation: Implement the full AAA suite (Authentication, Authorization, and Accounting) pointing to the authorized TACACS group.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

aaa_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	FAIL	HIGH	Required AAA command missing (expected to match '^aaa authentication login default group \S+ local'). Remediation: Implement the full AAA suite (Authentication, Authorization, and Accounting) pointing to the authorized TACACS group.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
FAIL		MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00009 - NTP			'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

aaa_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
	FAIL	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA			Required AAA command missing (expected to match '^aaa authorization commands 1 default group \S+ if-authenticated'). Remediation: Implement the full AAA suite (Authentication, Authorization, and Accounting) pointing to the authorized TACACS group.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	FAIL	MEDIUM	'banner motd' is not configured. Remediation: Configure a 'banner motd' containing approved legal language regarding authorized access and monitoring.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords			'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	FAIL	MEDIUM	'banner motd' opening delimiter '\$' has no matching closing '\$' - the banner is malformed/incomplete. Remediation: Configure a 'banner motd' containing approved legal language regarding authorized access and monitoring.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication

CONTROL	STATUS	SEVERITY	FINDING
			default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found

CONTROL	STATUS	SEVERITY	FINDING
			'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	FAIL	MEDIUM	'banner motd' is not configured. Remediation: Configure a 'banner motd' containing approved legal language regarding authorized access and monitoring.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

domain_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	Domain 'name othercorp.net' does not match the corporate domain 'name acme.com'. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

CONTROL	STATUS	SEVERITY	FINDING
			Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

domain_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	Domain 'acme.com' does not match the corporate domain 'name acme.com'. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
	FAIL	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00004 - TACACS			'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
	PASS	MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00012 - Banners			'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

domain_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	Domain 'name acem.com' does not match the corporate domain 'name acme.com'. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.

CONTROL	STATUS	SEVERITY	FINDING
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication

CONTROL	STATUS	SEVERITY	FINDING
			default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

domain_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	FAIL	LOW	Domain 'name acme.org' does not match the corporate domain 'name acme.com'. Remediation: Apply the correct domain using: ip domain name <company_name>.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.

CONTROL	STATUS	SEVERITY	FINDING
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

emergency_user_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	No local emergency user with 'algorithm-type scrypt' found. Remediation: Configure a local admin user and 'enable secret' using high-security hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two

CONTROL	STATUS	SEVERITY	FINDING
			reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

emergency_user_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02':

CONTROL	STATUS	SEVERITY	FINDING
			address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	Emergency user 'admin_bckp': privilege level is '7', expected 15. Remediation: Configure a local admin user and 'enable secret' using high-security hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords			'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

emergency_user_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	FAIL	HIGH	Emergency user name 'admin_bkup' does not match the corporate standard 'admin_bckp'. Remediation: Configure a local admin user and 'enable secret' using high-security

CONTROL	STATUS	SEVERITY	FINDING
			hashing algorithms like scrypt (type 8/9), consistently across all local accounts.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

hostname_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	FAIL	LOW	Hostname 'Router' is generic.; Hostname 'Router' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts). Remediation: Configure the hostname following the corporate naming convention: hostname <COMPANY>_<COUNTRY>_<TYPE>_<FUNCTION>_<SITE>_<DEVICE>
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate key specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands in the running configuration.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, in the configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference for authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference for authentication key.

CONTROL	STATUS	SEVERITY	FINDING
			reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'ntp authentication' command to specify the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15' 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines on console and 'login authentication default' on VTY; restrict transport to secure protocols; bind VTY lines to a named ACL via 'access-class'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

hostname_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	FAIL	LOW	Hostname 'ACME_USA_RT' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts). Remediation: Configure the hostname following the corporate naming convention: <COMPANY>_<COUNTRY>_<TYPE>_<FUNCTION>_<SITE>_<DEVICE>
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate key-chains specified by the security policy, using Type 6 key encryption instead of Type 7.
	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00005 - Local and emergency users			
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, in the configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the first as the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; apply 'login authentication default' on console and 'login authentication default' on VTY; restrict transport to secure protocols; bind VTY lines to a named ACL via 'access-class'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration

hostname_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
	FAIL	LOW	

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname			Hostname 'ACME-USA-RT-INT-GOLDEN-01' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts). Remediation: Configure the hostname following the corporate naming convention: <COMPANY>_<COUNTRY>_<TYPE>_<FUNCTION>_<SITE>_<DEVICE>
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate key chain specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands in the running configuration.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, in the configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'ntp authentication' command to enable NTP authentication, and use the 'ntp authentication key' command to define the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output in the running configuration.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15' 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines on console and 'login authentication default' on VTY; restrict transport output to secure protocols; bind VTY lines to a named ACL via 'access-class'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

hostname_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	FAIL	LOW	Hostname 'ACME_USA_Router_INT_GOLDEN_01': Type should be a short device-class code (e.g. 'RT', 'SW', 'WL', 'FW'), not a spelled-out word. Remediation: Configure the hostname following the corporate naming convention: <COMPANY>_<COUNTRY>_<TYPE>_<FUNCTION>_<SITE>_<ID>
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate key chain specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
		HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00008 - ACL for VTY	FAIL		ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, in the configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the first as the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15 transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines on console and 'login authentication default' on VTY; restrict transport to secure protocols; bind VTY lines to a named ACL via 'access-class'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

local_admin_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02':

CONTROL	STATUS	SEVERITY	FINDING
			address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	FAIL	HIGH	Local administrator 'admin': privilege level is '1', expected 15. Remediation: Ensure an 'enable secret' and a privilege 15 local administrator account are present and secured.

local_admin_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user	FAIL	HIGH	'enable secret' uses a weak/guessable value. Remediation: Ensure an 'enable secret'

CONTROL	STATUS	SEVERITY	FINDING
and enable secret			and a privilege 15 local administrator account are present and secured.

local_admin_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the

CONTROL	STATUS	SEVERITY	FINDING
			NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	FAIL	HIGH	Local administrator username 'administrator' does not match the corporate standard 'admin'. Remediation: Ensure an 'enable secret' and a privilege 15 local administrator account are present and secured.

password_encryption_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA			All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	FAIL	HIGH	'key config-key password-encrypt <device_master_key>' is missing.; 'password encryption aes' is missing. Remediation: Apply 'key config-key password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.

CONTROL	STATUS	SEVERITY	FINDING
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_encryption_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers

CONTROL	STATUS	SEVERITY	FINDING
			with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	FAIL	HIGH	'key config-key password-encrypt <device_master_key>' is missing. Remediation: Apply 'key config-key password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15':

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines			'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_encryption_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global	FAIL	HIGH	'password encryption aes' is missing. Remediation: Apply 'key config-key

CONTROL	STATUS	SEVERITY	FINDING
password encryption			password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_encryption_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	FAIL	HIGH	'key config-key password-encrypt' uses a weak/guessable master key value. Remediation: Apply 'key config-key password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>'

CONTROL	STATUS	SEVERITY	FINDING
			reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_encryption_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	FAIL	HIGH	'key config-key password-encrypt <device_master_key>' is missing. Remediation: Apply 'key config-key password-encrypt <device_master_key>' and 'password encryption aes' on the device.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
	PASS	MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00012 - Banners			'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
emergency users			
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	FAIL	HIGH	'security passwords min-length' is not configured.; 'service password-encryption' is missing. Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication

CONTROL	STATUS	SEVERITY	FINDING
			default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found

CONTROL	STATUS	SEVERITY	FINDING
			'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	FAIL	HIGH	'security passwords min-length' is set to 4, below the required minimum of 10. Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	FAIL	HIGH	'security passwords min-length' is set to 9, below the required minimum of 10. Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server

CONTROL	STATUS	SEVERITY	FINDING
			address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
	FAIL	HIGH	'security passwords min-length' is not configured.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords			Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

password_policy_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	FAIL	HIGH	'security passwords min-length' is not configured. Remediation: Set a global minimum password length (at least 10) and enable the password encryption service.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

snmp_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard

CONTROL	STATUS	SEVERITY	FINDING
			ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	FAIL	HIGH	SNMPv3 group with 'priv' is not configured.; SNMPv3 user is not created with SHA/AES configuration.; SNMP trap host is missing.; 'snmp-server enable traps' command is missing.; An SNMPv1/v2c community string ('snmp-server community') coexists with the SNMPv3 configuration. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES) exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

CONTROL	STATUS	SEVERITY	FINDING
and enable secret			

snmp_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the

CONTROL	STATUS	SEVERITY	FINDING
			NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	FAIL	HIGH	'snmp-server enable traps' command is missing. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES) exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

snmp_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
	FAIL	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00011 - SNMP			SNMPv3 group with 'priv' is not configured.; 'snmp-server user' references group 'acme_snmp_grp01', which has no matching 'snmp-server group acme_snmp_grp01 v3 priv' definition. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES) exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

snmp_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server

CONTROL	STATUS	SEVERITY	FINDING
			address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	FAIL	HIGH	'snmp-server user' references group 'acme_snmp_group01', which has no matching 'snmp-server group acme_snmp_group01 v3 priv' definition. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES)

CONTROL	STATUS	SEVERITY	FINDING
			exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

snmp_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.

CONTROL	STATUS	SEVERITY	FINDING
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	FAIL	HIGH	SNMPv3 user is not created with SHA/AES configuration. Remediation: Use SNMPv3 with authentication (SHA) and privacy (AES) exclusively; remove any SNMPv1/v2c community strings.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to

CONTROL	STATUS	SEVERITY	FINDING
			secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ssh_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	FAIL	HIGH	'crypto key generate rsa modulus <bits>' is missing - SSH cannot function without it. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

CONTROL	STATUS	SEVERITY	FINDING
---------	--------	----------	---------

and enable secret			
-------------------	--	--	--

ssh_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
---------	--------	----------	---------

control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
-----------------------------	------	-----	---

control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
---------------------------	------	-----	--

control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
------------------------	------	------	--

control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
---------------------------	------	------	---

control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
--	------	------	--

control_00006 - SSH	FAIL	HIGH	'ip ssh version' is set to '1', expected '2' per corporate standard. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.
------------------------	------	------	---

control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
---	------	------	--

control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
--------------------------------	------	------	--

CONTROL	STATUS	SEVERITY	FINDING
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ssh_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	FAIL	HIGH	'ip ssh authentication-retries' is set to '10', expected '3' per corporate standard. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.

CONTROL	STATUS	SEVERITY	FINDING
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ssh_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers

CONTROL	STATUS	SEVERITY	FINDING
			with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	FAIL	HIGH	'ip ssh time-out' is set to '300', expected '60' per corporate standard. Remediation: Generate RSA keys with a minimum modulus of 2048 bits after setting the hostname and domain.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_01 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	FAIL	MEDIUM	'logging on' command is missing.; Logging host IP address is missing.; Logging trap level is not set to 'informational'.; 'logging source-interface' is not configured. Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_02 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard

CONTROL	STATUS	SEVERITY	FINDING
			ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	FAIL	MEDIUM	Logging host IP address is missing. Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_03 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
FAIL		MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00010 - Syslog			Logging trap level is not set to 'informational'. Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_04 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	FAIL	MEDIUM	'logging source-interface' ('source-interface gigabitethernet0/1') does not match the corporate standard ('source-interface loopback0'). Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

syslog_config_05 - 66.7% (10/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	FAIL	MEDIUM	Logging host '30.30.30.101' does not match the corporate syslog server '30.30.30.100'. Remediation: Enable global logging and point it to a secure, external syslog server with an informational trap level.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and

CONTROL	STATUS	SEVERITY	FINDING
			output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	No 'ip access-list extended' block found in the running configuration. Remediation: Apply the corporate-standard

CONTROL	STATUS	SEVERITY	FINDING
			ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; ACL 'ACME_VTY_MGMT_ACL' referenced by access-class was not found in the configuration. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
	PASS	LOW	

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname			The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; 'line vty 0 15': no 'access-class' ACL is bound to this VTY line. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs

CONTROL	STATUS	SEVERITY	FINDING
			server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL name 'ACME_VTY_MGT_ACL' does not match the corporate ACL name 'ACME_VTY_MGMT_ACL'; ACL 'ACME_VTY_MGT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; ACL 'ACME_VTY_MGMT_ACL' referenced by access-class was not found in the configuration. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
emergency users			'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

acl_vty_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule 'permit ip 0.0.0.0 255.255.255.255 any' uses a wildcard mask (255.255.255.255) that is functionally equivalent to 'any', defeating the

CONTROL	STATUS	SEVERITY	FINDING
			purpose of the management ACL.; ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip 0.0.0.0 255.255.255.255 any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

banner_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

hostname_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.

CONTROL	STATUS	SEVERITY	FINDING
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

CONTROL	STATUS	SEVERITY	FINDING
---------	--------	----------	---------

and enable secret			
-------------------	--	--	--

local_admin_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
---------	--------	----------	---------

control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
-----------------------------	------	-----	---

control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
---------------------------	------	-----	--

control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
------------------------	------	------	--

control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
---------------------------	------	------	---

control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
--	------	------	--

control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
------------------------	------	------	---

control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
---	------	------	--

control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
--------------------------------	------	------	--

control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the
------------------------	------	--------	---

CONTROL	STATUS	SEVERITY	FINDING
			NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

local_admin_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
	PASS	MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00012 - Banners			'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
emergency users			
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	NTP server configuration is missing.; NTP authentication is not configured ('ntp authenticate' / 'ntp authentication-key' / 'ntp trusted-key' missing). Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines

CONTROL	STATUS	SEVERITY	FINDING
			to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard

CONTROL	STATUS	SEVERITY	FINDING
			ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
	PASS	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00003 - AAA			All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'prefer' keyword is missing on the primary NTP server.; 'ntp server 10.10.10.100': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as

CONTROL	STATUS	SEVERITY	FINDING
			specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	NTP authentication is not configured ('ntp authenticate' / 'ntp authentication-key' / 'ntp trusted-key' missing). Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication

CONTROL	STATUS	SEVERITY	FINDING
			default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ntp_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found

CONTROL	STATUS	SEVERITY	FINDING
			'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp trusted-key 2' does not match 'ntp authentication-key 1'.; 'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

ssh_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	Fewer than two 'tacacs server' definitions found.; 'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.

CONTROL	STATUS	SEVERITY	FINDING
			Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15':

CONTROL	STATUS	SEVERITY	FINDING
control_00014 - VTY Lines			'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; No 'ip tacacs source-interface' configured under the TACACS server group. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running

CONTROL	STATUS	SEVERITY	FINDING
password encryption			configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_01': timeout '30' does not match the corporate standard '10'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>'

CONTROL	STATUS	SEVERITY	FINDING
			reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

CONTROL	STATUS	SEVERITY	FINDING
			match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

tacacs_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.; 'aaa group server tacacs+ ACME_TACACS_SERVER_GROUP': references server 'ACME_TACACS_2', which has no matching 'tacacs server ACME_TACACS_2' definition. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as

CONTROL	STATUS	SEVERITY	FINDING
			specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a

CONTROL	STATUS	SEVERITY	FINDING
			password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_01 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any

CONTROL	STATUS	SEVERITY	FINDING
			173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport input' is not restricted to secure protocols.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_02 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer'

CONTROL	STATUS	SEVERITY	FINDING
			keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line con 0': 'exec-timeout 0 0' disables session timeout entirely (sessions never expire).; 'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'exec-timeout 0 0' disables session timeout entirely (sessions never expire).; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_03 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
	FAIL	HIGH	

CONTROL	STATUS	SEVERITY	FINDING
control_00004 - TACACS			'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
	PASS	MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00012 - Banners			'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_04 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.

CONTROL	STATUS	SEVERITY	FINDING
emergency users			
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line con 0': 'exec-timeout 20 0' (20 minute(s)) exceeds the corporate policy maximum of 10 minute(s).; 'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'exec-timeout 20 0' (20 minute(s)) exceeds the corporate policy maximum of 10 minute(s).; 'line vty 0 15': 'transport output' is not restricted to secure protocols.

CONTROL	STATUS	SEVERITY	FINDING
			Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

vty_lines_config_05 - 73.3% (11/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.

CONTROL	STATUS	SEVERITY	FINDING
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	FAIL	MEDIUM	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key. Remediation: Configure at least two reliable NTP servers, use the 'prefer' keyword for the primary source, and enable NTP authentication.
control_00010 - Syslog	PASS	MEDIUM	'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; 'line vty 0 15': 'access-class ACME_VTY_MGMT_ACL' is missing the required 'in' direction keyword. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

aaa_config_01 - 80.0% (12/15)

CONTROL	STATUS	SEVERITY	FINDING
control_00001 - Hostname	PASS	LOW	The 'hostname' line in the running configuration.
control_00002 - Domain	PASS	LOW	The 'ip domain name' command in the running configuration.
control_00003 - AAA	PASS	HIGH	All 'aaa' commands in the running configuration.
control_00004 - TACACS	FAIL	HIGH	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'. Remediation: Define the TACACS+ servers with the appropriate keys and timeouts as specified by the security policy, using Type 6 key encryption instead of Type 7.
control_00005 - Local and emergency users	PASS	HIGH	'username' and 'enable secret' lines in the running configuration.
control_00006 - SSH	PASS	HIGH	Output of 'show ip ssh' or absence of zeroize commands.
control_00007 - Global password encryption	PASS	HIGH	'key 6 <encrypted_string>' format on sensitive keys in the running configuration, and 'password encryption aes' present.
control_00008 - ACL for VTY	FAIL	HIGH	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'deny ip any 173.245.48.0 0.0.15.255'. Remediation: Apply the corporate-standard ACL content, in order, inside the VTY configuration module.
control_00009 - NTP	PASS	MEDIUM	'ntp server' lines, 'ntp authenticate'/'ntp authentication-key' lines, and 'show ntp associations' output.
PASS		MEDIUM	

CONTROL	STATUS	SEVERITY	FINDING
control_00010 - Syslog			'logging' commands in the running configuration.
control_00011 - SNMP	PASS	HIGH	'snmp-server' configuration lines and 'show snmp user' output.
control_00012 - Banners	PASS	MEDIUM	'banner motd' section in the running configuration.
control_00013 - Passwords	PASS	HIGH	'security passwords min-length' and 'service password-encryption' commands.
control_00014 - VTY Lines	FAIL	HIGH	'line vty 0 15': password is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols. Remediation: Apply 'exec-timeout' and a password on all access lines; use 'login local' on console and 'login authentication default' on VTY; restrict transport input and output to secure protocols; bind VTY lines to a named ACL via 'access-class <name> in'.
control_00015 - Local user and enable secret	PASS	HIGH	'enable secret' and 'username ... privilege 15' in configuration.

Control Detail

control_00001 - Hostname (94.7% compliant, 4 affected)		
DEVICE	STATUS	FINDING
hostname_config_01	FAIL	Hostname 'Router' is generic.; Hostname 'Router' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts).
hostname_config_02	FAIL	Hostname 'ACME_USA_RT' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts).
hostname_config_03	FAIL	Hostname 'ACME-USA-RT-INT-GOLDEN-01' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION_SITE_DEVICE convention (expected at least 6 underscore-separated parts).
hostname_config_04	FAIL	Hostname 'ACME_USA_Router_INT_GOLDEN_01': Type field 'Router' should be a short device-class code (e.g. 'RT', 'SW', 'AP', 'PBX', 'FW'), not a spelled-out word.

control_00002 - Domain (93.3% compliant, 5 affected)		
DEVICE	STATUS	FINDING
domain_config_01	FAIL	No 'ip domain name' command found in device configuration.
domain_config_02	FAIL	Domain 'name othercorp.net' does not match the corporate domain 'name acme.com'.
domain_config_03	FAIL	Domain 'acme.com' does not match the corporate domain 'name acme.com'.
domain_config_04	FAIL	Domain 'name acem.com' does not match the corporate domain 'name acme.com'.
domain_config_05	FAIL	Domain 'name acme.org' does not match the corporate domain 'name acme.com'.

control_00003 - AAA (94.7% compliant, 4 affected)		
DEVICE	STATUS	FINDING
aaa_config_02	FAIL	Required AAA command missing (expected to match '^aaa accounting exec default start-stop group \S+'); Required AAA command missing (expected to match '^aaa accounting commands 1 default start-stop group \S+'); Required AAA command missing (expected to match '^aaa

DEVICE	STATUS	FINDING
		accounting commands 15 default start-stop group \S+').
aaa_config_03	FAIL	AAA commands reference inconsistent TACACS groups: ['ACME_TACACS_GROUP', 'ACME_TACACS_SERVER_GROUP'].
aaa_config_04	FAIL	Required AAA command missing (expected to match '^aaa authentication login default group \S+ local').
aaa_config_05	FAIL	Required AAA command missing (expected to match '^aaa authorization commands 1 default group \S+ if-authenticated').

control_00004 - TACACS (0.0% compliant, 75 affected)

DEVICE	STATUS	FINDING
aaa_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
aaa_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
aaa_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
aaa_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the

DEVICE	STATUS	FINDING
		corporate TACACS server address '192.168.100.102'.
aaa_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
acl_vty_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs

DEVICE	STATUS	FINDING
		server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
banner_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

DEVICE	STATUS	FINDING
		match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
domain_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
emergency_user_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.

DEVICE	STATUS	FINDING
emergency_user_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
emergency_user_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
emergency_user_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
emergency_user_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
hostname_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
hostname_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the

DEVICE	STATUS	FINDING
		corporate TACACS server address '192.168.100.102'.
hostname_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
hostname_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
hostname_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs

DEVICE	STATUS	FINDING
		server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
local_admin_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

DEVICE	STATUS	FINDING
		match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ntp_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_encryption_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_encryption_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_encryption_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_encryption_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.

DEVICE	STATUS	FINDING
password_encryption_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
password_policy_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the

DEVICE	STATUS	FINDING
		corporate TACACS server address '192.168.100.102'.
snmp_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
snmp_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
snmp_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
snmp_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
snmp_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs

DEVICE	STATUS	FINDING
		server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
ssh_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not

DEVICE	STATUS	FINDING
		match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
syslog_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
tacacs_config_01	FAIL	Fewer than two 'tacacs server' definitions found.; 'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'.
tacacs_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; No 'ip tacacs source-interface' configured under the TACACS server group.

DEVICE	STATUS	FINDING
tacacs_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_01': timeout '30' does not match the corporate standard '10'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
tacacs_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
tacacs_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'; 'aaa group server tacacs+ ACME_TACACS_SERVER_GROUP': references server 'ACME_TACACS_2', which has no matching 'tacacs server ACME_TACACS_2' definition.
vty_lines_config_01	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
vty_lines_config_02	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the

DEVICE	STATUS	FINDING
		corporate TACACS server address '192.168.100.102'.
vty_lines_config_03	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
vty_lines_config_04	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
vty_lines_config_05	FAIL	'tacacs server ACME_TACACS_01': address '192.168.100.100' does not match the corporate TACACS server address '192.168.100.101'; 'tacacs server ACME_TACACS_02': address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.

control_00005 - Local and emergency users (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
emergency_user_config_01	FAIL	No local emergency user with 'algorithm-type scrypt' found.
emergency_user_config_02	FAIL	Emergency user 'admin_bckp': privilege level is '7', expected 15.
emergency_user_config_03	FAIL	No local emergency user with 'algorithm-type scrypt' found.
emergency_user_config_04	FAIL	Emergency user name 'admin_bkup' does not match the corporate standard 'admin_bckp'.
emergency_user_config_05	FAIL	No local emergency user with 'algorithm-type scrypt' found.

control_00006 - SSH (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
domain_config_01	FAIL	IP domain-name is not configured.
ssh_config_01	FAIL	'crypto key generate rsa modulus <bits>' is missing - SSH cannot function without it.
ssh_config_02	FAIL	'ip ssh version' is set to '1', expected '2' per corporate standard.
ssh_config_04	FAIL	'ip ssh authentication-retries' is set to '10', expected '3' per corporate standard.
ssh_config_05	FAIL	'ip ssh time-out' is set to '300', expected '60' per corporate standard.

control_00007 - Global password encryption (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
password_encryption_config_01	FAIL	'key config-key password-encrypt <device_master_key>' is missing.; 'password encryption aes' is missing.
password_encryption_config_02	FAIL	'key config-key password-encrypt <device_master_key>' is missing.
password_encryption_config_03	FAIL	'password encryption aes' is missing.
password_encryption_config_04	FAIL	'key config-key password-encrypt' uses a weak/guessable master key value.
password_encryption_config_05	FAIL	'key config-key password-encrypt <device_master_key>' is missing.

control_00008 - ACL for VTY (0.0% compliant, 75 affected)

DEVICE	STATUS	FINDING
aaa_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'deny ip any 173.245.48.0 0.0.15.255'.

DEVICE	STATUS	FINDING
aaa_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
aaa_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
aaa_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
aaa_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
acl_vty_config_01	FAIL	No 'ip access-list extended' block found in the running configuration.
acl_vty_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
acl_vty_config_03	FAIL	ACL name 'ACME_VTY_MGT_ACL' does not match the corporate ACL name 'ACME_VTY_MGMT_ACL'; ACL 'ACME_VTY_MGT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
acl_vty_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
acl_vty_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule 'permit ip 0.0.0.0 255.255.255.255 any' uses a wildcard mask (255.255.255.255) that is functionally equivalent to 'any', defeating the purpose of the management ACL.; ACL

DEVICE	STATUS	FINDING
		'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip 0.0.0.0 255.255.255.255 any'.
banner_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
banner_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
banner_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
banner_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
banner_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
domain_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any

DEVICE	STATUS	FINDING
		173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
emergency_user_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
hostname_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.

DEVICE	STATUS	FINDING
local_admin_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
local_admin_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
local_admin_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
local_admin_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
local_admin_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ntp_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any

DEVICE	STATUS	FINDING
		173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_encryption_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
password_policy_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
snmp_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.

DEVICE	STATUS	FINDING
snmp_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
snmp_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
snmp_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
snmp_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
ssh_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any

DEVICE	STATUS	FINDING
		173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
syslog_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
tacacs_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
vty_lines_config_01	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
vty_lines_config_02	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.

DEVICE	STATUS	FINDING
vty_lines_config_03	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
vty_lines_config_04	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
vty_lines_config_05	FAIL	ACL 'ACME_VTY_MGMT_ACL' rule #1: expected 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.

control_00009 - NTP (1.3% compliant, 74 affected)

DEVICE	STATUS	FINDING
aaa_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
aaa_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
aaa_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
aaa_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100':

DEVICE	STATUS	FINDING
		missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
acl_vty_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
banner_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
banner_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
banner_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
banner_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
banner_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
domain_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.;

DEVICE	STATUS	FINDING
		'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
emergency_user_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
hostname_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
hostname_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
hostname_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
hostname_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
hostname_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
local_admin_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ntp_config_01	FAIL	NTP server configuration is missing.; NTP authentication is not configured ('ntp

DEVICE	STATUS	FINDING
		authenticate' / 'ntp authentication-key' / 'ntp trusted-key' missing).
ntp_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.
ntp_config_03	FAIL	'prefer' keyword is missing on the primary NTP server.; 'ntp server 10.10.10.100': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ntp_config_04	FAIL	NTP authentication is not configured ('ntp authenticate' / 'ntp authentication-key' / 'ntp trusted-key' missing).
ntp_config_05	FAIL	'ntp trusted-key 2' does not match 'ntp authentication-key 1'; 'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_encryption_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_encryption_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_encryption_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
password_encryption_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_encryption_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
password_policy_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.;

DEVICE	STATUS	FINDING
		'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
snmp_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ssh_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ssh_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ssh_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
ssh_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
ssh_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
syslog_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.;

DEVICE	STATUS	FINDING
		'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
tacacs_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
vty_lines_config_01	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
vty_lines_config_02	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
vty_lines_config_03	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

DEVICE	STATUS	FINDING
vty_lines_config_04	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.
vty_lines_config_05	FAIL	'ntp server 10.10.10.100 prefer': missing a 'key <id>' reference to the NTP authentication key.; 'ntp server 20.20.20.100': missing a 'key <id>' reference to the NTP authentication key.

control_00010 - Syslog (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
syslog_config_01	FAIL	'logging on' command is missing.; Logging host IP address is missing.; Logging trap level is not set to 'informational'.; 'logging source-interface' is not configured.
syslog_config_02	FAIL	Logging host IP address is missing.
syslog_config_03	FAIL	Logging trap level is not set to 'informational'.
syslog_config_04	FAIL	'logging source-interface' ('source-interface gigabitethernet0/1') does not match the corporate standard ('source-interface loopback0').
syslog_config_05	FAIL	Logging host '30.30.30.101' does not match the corporate syslog server '30.30.30.100'.

control_00011 - SNMP (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
snmp_config_01	FAIL	SNMPv3 group with 'priv' is not configured.; SNMPv3 user is not created with SHA/AES configuration.; SNMP trap host is missing.; 'snmp-server enable traps' command is missing.; An SNMPv1/v2c community string ('snmp-server community') coexists with the SNMPv3 configuration.
snmp_config_02	FAIL	'snmp-server enable traps' command is missing.
snmp_config_03	FAIL	

DEVICE	STATUS	FINDING
		SNMPv3 group with 'priv' is not configured.; 'snmp-server user' references group 'acme_snmp_grp01', which has no matching 'snmp-server group acme_snmp_grp01 v3 priv' definition.
snmp_config_04	FAIL	'snmp-server user' references group 'acme_snmp_group01', which has no matching 'snmp-server group acme_snmp_group01 v3 priv' definition.
snmp_config_05	FAIL	SNMPv3 user is not created with SHA/AES configuration.

control_00012 - Banners (96.0% compliant, 3 affected)

DEVICE	STATUS	FINDING
banner_config_01	FAIL	'banner motd' is not configured.
banner_config_03	FAIL	'banner motd' opening delimiter '\$' has no matching closing '\$' - the banner is malformed/incomplete.
banner_config_05	FAIL	'banner motd' is not configured.

control_00013 - Passwords (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
password_policy_config_01	FAIL	'security passwords min-length' is not configured.; 'service password-encryption' is missing.
password_policy_config_02	FAIL	'security passwords min-length' is set to 4, below the required minimum of 10.
password_policy_config_03	FAIL	'security passwords min-length' is set to 9, below the required minimum of 10.
password_policy_config_04	FAIL	'security passwords min-length' is not configured.
password_policy_config_05	FAIL	'security passwords min-length' is not configured.

control_00014 - VTY Lines (0.0% compliant, 75 affected)

DEVICE	STATUS	FINDING
aaa_config_01	FAIL	'line vty 0 15': password is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
aaa_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
aaa_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
aaa_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
aaa_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
acl_vty_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; ACL 'ACME_VTY_MGMT_ACL' referenced by access-class was not found in the configuration.
acl_vty_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; 'line vty 0 15': no 'access-class' ACL is bound to this VTY line.
acl_vty_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.;

DEVICE	STATUS	FINDING
		ACL 'ACME_VTY_MGMT_ACL' referenced by access-class was not found in the configuration.
acl_vty_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
acl_vty_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
banner_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
domain_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.

DEVICE	STATUS	FINDING
domain_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
domain_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
domain_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
domain_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
emergency_user_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15':

DEVICE	STATUS	FINDING
		'transport output' is not restricted to secure protocols.
hostname_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
hostname_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
hostname_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
hostname_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
hostname_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_04	FAIL	'line vty 0 15': 'login authentication default' is

DEVICE	STATUS	FINDING
		missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
local_admin_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ntp_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_encryption_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_encryption_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.

DEVICE	STATUS	FINDING
password_encryption_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_encryption_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_encryption_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
password_policy_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
snmp_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15':

DEVICE	STATUS	FINDING
		'transport output' is not restricted to secure protocols.
snmp_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
snmp_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
snmp_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
snmp_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
ssh_config_05	FAIL	'line vty 0 15': 'login authentication default' is

DEVICE	STATUS	FINDING
		missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
syslog_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
tacacs_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
tacacs_config_02	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
tacacs_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.

DEVICE	STATUS	FINDING
tacacs_config_04	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
tacacs_config_05	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_01	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport input' is not restricted to secure protocols.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_02	FAIL	'line con 0': 'exec-timeout 0 0' disables session timeout entirely (sessions never expire).; 'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'exec-timeout 0 0' disables session timeout entirely (sessions never expire).; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_03	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_04	FAIL	'line con 0': 'exec-timeout 20 0' (20 minute(s)) exceeds the corporate policy maximum of 10 minute(s).; 'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'exec-timeout 20 0' (20 minute(s)) exceeds the corporate policy maximum of 10 minute(s).; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
vty_lines_config_05		

DEVICE	STATUS	FINDING
	FAIL	'line vty 0 15': 'login authentication default' is missing.; 'line vty 0 15': 'transport output' is not restricted to secure protocols.; 'line vty 0 15': 'access-class ACME_VTY_MGMT_ACL' is missing the required 'in' direction keyword.

control_00015 - Local user and enable secret (93.3% compliant, 5 affected)

DEVICE	STATUS	FINDING
emergency_user_config_03	FAIL	Local administrator username 'admin_bckp' does not match the corporate standard 'admin'.
emergency_user_config_05	FAIL	Local administrator username 'admin_bckp' does not match the corporate standard 'admin'.
local_admin_config_02	FAIL	Local administrator 'admin': privilege level is '1', expected 15.
local_admin_config_03	FAIL	'enable secret' uses a weak/ guessable value.
local_admin_config_05	FAIL	Local administrator username 'administrator' does not match the corporate standard 'admin'.

Findings & Remediation

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	aaa_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'd 0.0.15.255'.
HIGH	aaa_config_01	control_00014 - VTY Lines	'line vty 0 15': password is missing not restricted to secure protocols.
HIGH	aaa_config_02	control_00003 - AAA	Required AAA command missing (accounting exec default start-stop command missing (expected to match default start-stop group \S+).; Required AAA command missing (expected to match '^aaa accounting group \S+').
HIGH	aaa_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	aaa_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	aaa_config_03	control_00003 - AAA	AAA commands reference inconsistent ['ACME_TACACS_GROUP', 'ACME
HIGH	aaa_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	aaa_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	aaa_config_04	control_00003 - AAA	Required AAA command missing (authentication login default group '')

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	aaa_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	aaa_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	aaa_config_05	control_00003 - AAA	Required AAA command missing (authorization commands 1 default
HIGH	aaa_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	aaa_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	aaa_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	acl_vty_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_01	control_00008 - ACL for VTY	No 'ip access-list extended' block f
HIGH	acl_vty_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t 'ACME_VTY_MGMT_ACL' referen found in the configuration.
HIGH	acl_vty_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	acl_vty_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t no 'access-class' ACL is bound to
HIGH	acl_vty_config_03		'tacacs server ACME_TACACS_02' not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
		control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_03	control_00008 - ACL for VTY	ACL name 'ACME_VTY_MGMT_ACL' not found in the configuration. ACL name 'ACME_VTY_MGMT_ACL' rule #1: 'deny ip any 0.0.15.255', found 'permit ip any any'.
HIGH	acl_vty_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration. 'transport output' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration.
HIGH	acl_vty_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule #1: 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
HIGH	acl_vty_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration. 'transport output' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration.
HIGH	acl_vty_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	acl_vty_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule #1: 'deny ip any 255.255.255.255 any' uses a wildcard that is functionally equivalent to 'any', could be replaced by 'any' in management ACL.; ACL 'ACME_VTY_MGMT_ACL' rule #2: 'deny ip any 173.245.48.0 0.0.0.0 255.255.255.255 any'.
HIGH	acl_vty_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration. 'transport output' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration.
HIGH	banner_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule #1: 'deny ip any 173.245.48.0 0.0.15.255', found 'permit ip any any'.
HIGH	banner_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration. 'transport output' is not restricted to 'ACME_VTY_MGMT_ACL' referenced in the configuration.
HIGH	banner_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
			'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	banner_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	banner_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	banner_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	banner_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	banner_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	banner_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	banner_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	banner_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	domain_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_01	control_00006 - SSH	IP domain-name is not configured.
HIGH	domain_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	domain_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	domain_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	domain_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	domain_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	domain_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	domain_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	domain_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	domain_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	domain_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	domain_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	emergency_user_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	emergency_user_config_01	control_00005 - Local and emergency users	No local emergency user with 'algo
HIGH	emergency_user_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	emergency_user_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	emergency_user_config_02	control_00005 - Local and emergency users	Emergency user 'admin_bckp': pri
HIGH	emergency_user_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	emergency_user_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	emergency_user_config_03	control_00005 - Local and emergency users	No local emergency user with 'algo
HIGH	emergency_user_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	emergency_user_config_03	control_00015 - Local user and enable secret	Local administrator username 'adr corporate standard 'admin'.
HIGH	emergency_user_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
			'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	emergency_user_config_04	control_00005 - Local and emergency users	Emergency user name 'admin_bkp' not match standard 'admin_bckp'.
HIGH	emergency_user_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured, 'transport output' is not restricted t
HIGH	emergency_user_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	emergency_user_config_05	control_00005 - Local and emergency users	No local emergency user with 'algo
HIGH	emergency_user_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	emergency_user_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured, 'transport output' is not restricted t
HIGH	emergency_user_config_05	control_00015 - Local user and enable secret	Local administrator username 'admin' not match corporate standard 'admin'.
HIGH	hostname_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	hostname_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured, 'transport output' is not restricted t
HIGH	hostname_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	hostname_config_02		

PRIORITY	DEVICE	CONTROL	FINDING
		control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	hostname_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	hostname_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	hostname_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	hostname_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	hostname_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	hostname_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	hostname_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	local_admin_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	local_admin_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	local_admin_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
			'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	local_admin_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	local_admin_config_02	control_00015 - Local user and enable secret	Local administrator 'admin': privile
HIGH	local_admin_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	local_admin_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	local_admin_config_03	control_00015 - Local user and enable secret	'enable secret' uses a weak/guess
HIGH	local_admin_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	local_admin_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	local_admin_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	local_admin_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	local_admin_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	local_admin_config_05	control_00015 - Local user and enable secret	Local administrator username 'admin' does not match corporate standard 'admin'.
HIGH	ntp_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured 'transport output' is not restricted to
HIGH	ntp_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured 'transport output' is not restricted to
HIGH	ntp_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured 'transport output' is not restricted to
HIGH	ntp_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured 'transport output' is not restricted to
HIGH	ntp_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS

PRIORITY	DEVICE	CONTROL	FINDING
			'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ntp_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ntp_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_encryption_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	password_encryption_config_01	control_00007 - Global password encryption	'key config-key password-encrypt' 'password encryption aes' is missi
HIGH	password_encryption_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_encryption_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	password_encryption_config_02	control_00007 - Global password encryption	'key config-key password-encrypt
HIGH	password_encryption_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_encryption_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	password_encryption_config_03	control_00007 - Global password encryption	'password encryption aes' is missi
HIGH	password_encryption_config_03		

PRIORITY	DEVICE	CONTROL	FINDING
		control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	password_encryption_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	password_encryption_config_04	control_00007 - Global password encryption	'key config-key password-encrypt' key value.
HIGH	password_encryption_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	password_encryption_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	password_encryption_config_05	control_00007 - Global password encryption	'key config-key password-encrypt
HIGH	password_encryption_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	password_encryption_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	password_policy_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	password_policy_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_01	control_00013 - Passwords	'security passwords min-length' is encryption' is missing.
HIGH	password_policy_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	password_policy_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	password_policy_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_02	control_00013 - Passwords	'security passwords min-length' is minimum of 10.
HIGH	password_policy_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_policy_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_03' not match the corporate TACACS 'tacacs server ACME_TACACS_03' not match the corporate TACACS
HIGH	password_policy_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_03	control_00013 - Passwords	'security passwords min-length' is minimum of 10.
HIGH	password_policy_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_policy_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_04' not match the corporate TACACS 'tacacs server ACME_TACACS_04' not match the corporate TACACS
HIGH	password_policy_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_04	control_00013 - Passwords	'security passwords min-length' is
HIGH	password_policy_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted t
HIGH	password_policy_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_05' not match the corporate TACACS 'tacacs server ACME_TACACS_05' not match the corporate TACACS
HIGH	password_policy_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	password_policy_config_05		'security passwords min-length' is

PRIORITY	DEVICE	CONTROL	FINDING
		control_00013 - Passwords	
HIGH	password_policy_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not found, 'transport output' is not restricted to
HIGH	snmp_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS, 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	snmp_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_01	control_00011 - SNMP	SNMPv3 group with 'priv' is not created with SHA/AES configuration, 'snmp-server enable traps' command not found, community string ('snmp-server community') not found in SNMPv3 configuration.
HIGH	snmp_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not found, 'transport output' is not restricted to
HIGH	snmp_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS, 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	snmp_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_02	control_00011 - SNMP	'snmp-server enable traps' command not found
HIGH	snmp_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not found, 'transport output' is not restricted to
HIGH	snmp_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_01' not match the corporate TACACS, 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	snmp_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule 173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_03	control_00011 - SNMP	SNMPv3 group with 'priv' is not created, references group 'acme_snmp_group' not found, 'snmp-server group acme_snmp_group' not found
HIGH	snmp_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not found, 'transport output' is not restricted to

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	snmp_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	snmp_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_04	control_00011 - SNMP	'snmp-server user' references group has no matching 'snmp-server group' definition.
HIGH	snmp_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	snmp_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	snmp_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	snmp_config_05	control_00011 - SNMP	SNMPv3 user is not created with S
HIGH	snmp_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	ssh_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ssh_config_01	control_00006 - SSH	'crypto key generate rsa modulus' function without it.
HIGH	ssh_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' 'transport output' is not restricted to
HIGH	ssh_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	ssh_config_02	control_00006 - SSH	'ip ssh version' is set to '1', expected

PRIORITY	DEVICE	CONTROL	FINDING
HIGH	ssh_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	ssh_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_0 not match the corporate TACACS 'tacacs server ACME_TACACS_0 not match the corporate TACACS
HIGH	ssh_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	ssh_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0 not match the corporate TACACS 'tacacs server ACME_TACACS_0 not match the corporate TACACS
HIGH	ssh_config_04	control_00006 - SSH	'ip ssh authentication-retries' is set standard.
HIGH	ssh_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	ssh_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0 not match the corporate TACACS 'tacacs server ACME_TACACS_0 not match the corporate TACACS
HIGH	ssh_config_05	control_00006 - SSH	'ip ssh time-out' is set to '300', exp
HIGH	ssh_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	ssh_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_0 not match the corporate TACACS 'tacacs server ACME_TACACS_0 not match the corporate TACACS
HIGH	syslog_config_01		

PRIORITY	DEVICE	CONTROL	FINDING
		control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	syslog_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	syslog_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	syslog_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	syslog_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	syslog_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	syslog_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t
HIGH	tacacs_config_01	control_00004 - TACACS	

PRIORITY	DEVICE	CONTROL	FINDING
			Fewer than two 'tacacs server' defined. ACME_TACACS_01: address '192.168.100.101' does not match the corporate TACACS server address '192.168.100.102'.
HIGH	tacacs_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	tacacs_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS No 'ip tacacs source-interface' configured. No 'aaa group server tacacs+ ACME_
HIGH	tacacs_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_02	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	tacacs_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_03' not match the corporate TACACS 'tacacs server ACME_TACACS_03' not match the corporate TACACS corporate standard '10'.; 'tacacs server address '192.168.100.101' does not match the corporate standard server address '192.168.100.102'.
HIGH	tacacs_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	tacacs_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_04' not match the corporate TACACS 'tacacs server ACME_TACACS_04' not match the corporate TACACS
HIGH	tacacs_config_04	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_04	control_00014 - VTY Lines	'line vty 0 15': 'login authentication' not configured. 'transport output' is not restricted to
HIGH	tacacs_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_05' not match the corporate TACACS 'tacacs server ACME_TACACS_05' not match the corporate TACACS 'aaa group server tacacs+ ACME_

PRIORITY	DEVICE	CONTROL	FINDING
			references server 'ACME_TACACS_02' but not 'tacacs server ACME_TACACS_02'
HIGH	tacacs_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	tacacs_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication tacacs' is not restricted to 'transport output' is not restricted to
HIGH	vty_lines_config_01	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	vty_lines_config_01	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_01	control_00014 - VTY Lines	'line vty 0 15': 'login authentication tacacs' is not restricted to 'transport input' is not restricted to 'transport output' is not restricted to
HIGH	vty_lines_config_02	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	vty_lines_config_02	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_02	control_00014 - VTY Lines	'line con 0': 'exec-timeout 0 0' disabled (sessions never expire).; 'line vty 0 15': 'exec-timeout 0 0' missing.; 'line vty 0 15': 'exec-timeout 0 0' missing entirely (sessions never expire).; 'line vty 0 15': 'transport output' is not restricted to secure protocols.
HIGH	vty_lines_config_03	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	vty_lines_config_03	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' rule '173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_03	control_00014 - VTY Lines	'line vty 0 15': 'login authentication tacacs' is not restricted to 'transport output' is not restricted to
HIGH	vty_lines_config_04	control_00004 - TACACS	'tacacs server ACME_TACACS_02' not match the corporate TACACS 'tacacs server ACME_TACACS_02' not match the corporate TACACS
HIGH	vty_lines_config_04		

PRIORITY	DEVICE	CONTROL	FINDING
		control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_04	control_00014 - VTY Lines	'line con 0': 'exec-timeout 20 0' (20 policy maximum of 10 minute(s).; ' default' is missing.; 'line vty 0 15': exceeds the corporate policy maxi 15': 'transport output' is not restrict
HIGH	vty_lines_config_05	control_00004 - TACACS	'tacacs server ACME_TACACS_0: not match the corporate TACACS 'tacacs server ACME_TACACS_0: not match the corporate TACACS
HIGH	vty_lines_config_05	control_00008 - ACL for VTY	ACL 'ACME_VTY_MGMT_ACL' ru 173.245.48.0 0.0.15.255', found 'p
HIGH	vty_lines_config_05	control_00014 - VTY Lines	'line vty 0 15': 'login authentication 'transport output' is not restricted t 'access-class ACME_VTY_MGMT direction keyword.
MEDIUM	aaa_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	aaa_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	aaa_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	aaa_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_04	control_00009 - NTP	

PRIORITY	DEVICE	CONTROL	FINDING
			'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	acl_vty_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_01	control_00012 - Banners	'banner motd' is not configured.
MEDIUM	banner_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_03	control_00012 - Banners	'banner motd' opening delimiter '\$' banner is malformed/incomplete.
MEDIUM	banner_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	banner_config_05	control_00012 - Banners	'banner motd' is not configured.
MEDIUM	domain_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	domain_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	domain_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	domain_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	domain_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	emergency_user_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	hostname_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	local_admin_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	local_admin_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	local_admin_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	local_admin_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	local_admin_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	ntp_config_01	control_00009 - NTP	NTP server configuration is missing 'ntp authentication-key' / 'ntp trusted-key' (key missing).
MEDIUM	ntp_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.
MEDIUM	ntp_config_03	control_00009 - NTP	'prefer' keyword is missing on the 'ntp server 10.10.10.100': missing a 'key' / 'authentication-key' / 'ntp trusted-key' reference to the NTP authentication key.
MEDIUM	ntp_config_04	control_00009 - NTP	NTP authentication is not configured on the 'ntp server 10.10.10.100' (missing 'authentication-key' / 'ntp trusted-key').
MEDIUM	ntp_config_05	control_00009 - NTP	'ntp trusted-key 2' does not match the 'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.
MEDIUM	password_encryption_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server 20.20.20.20' reference to the NTP authentication key.

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	password_policy_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	password_policy_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	password_policy_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	password_policy_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	password_policy_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	snmp_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	ssh_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	ssh_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	ssh_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	ssh_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server <id>' reference to the NTP authentication
MEDIUM	ssh_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server <id>' reference to the NTP authentication
MEDIUM	syslog_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server <id>' reference to the NTP authentication
MEDIUM	syslog_config_01	control_00010 - Syslog	'logging on' command is missing.; 'logging trap' command is missing.; Logging trap level is not set to 'info'.; 'logging source-interface' is not configured
MEDIUM	syslog_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server <id>' reference to the NTP authentication
MEDIUM	syslog_config_02	control_00010 - Syslog	Logging host IP address is missing
MEDIUM	syslog_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server <id>' reference to the NTP authentication
MEDIUM	syslog_config_03	control_00010 - Syslog	Logging trap level is not set to 'info'
MEDIUM	syslog_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server <id>' reference to the NTP authentication
MEDIUM	syslog_config_04	control_00010 - Syslog	'logging source-interface' ('source-interface' does not match the corporate standard
MEDIUM	syslog_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server <id>' reference to the NTP authentication
MEDIUM	syslog_config_05	control_00010 - Syslog	Logging host '30.30.30.101' does not match the corporate standard server '30.30.30.100'.
MEDIUM	tacacs_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server <id>' reference to the NTP authentication
MEDIUM	tacacs_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': missing NTP authentication key.; 'ntp server <id>' reference to the NTP authentication

PRIORITY	DEVICE	CONTROL	FINDING
MEDIUM	tacacs_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	tacacs_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	tacacs_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_01	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_02	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_03	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_04	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
MEDIUM	vty_lines_config_05	control_00009 - NTP	'ntp server 10.10.10.100 prefer': m NTP authentication key.; 'ntp serve <id>' reference to the NTP authen
LOW	domain_config_01	control_00002 - Domain	No 'ip domain name' command fou
LOW	domain_config_02	control_00002 - Domain	Domain 'name othercorp.net' does 'name acme.com'.
LOW	domain_config_03	control_00002 - Domain	Domain 'acme.com' does not matc acme.com'.
LOW	domain_config_04	control_00002 - Domain	Domain 'name acem.com' does no 'name acme.com'.
LOW	domain_config_05	control_00002 - Domain	Domain 'name acme.org' does not 'name acme.com'.
LOW	hostname_config_01	control_00001 - Hostname	Hostname 'Router' is generic.; Hos COMPANY_COUNTRY_TYPE_FU convention (expected at least 6 un

PRIORITY	DEVICE	CONTROL	FINDING
LOW	hostname_config_02	control_00001 - Hostname	Hostname 'ACME_USA_RT' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION convention (expected at least 6 underscores)
LOW	hostname_config_03	control_00001 - Hostname	Hostname 'ACME-USA-RT-INT-GW' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION convention (expected at least 6 underscores)
LOW	hostname_config_04	control_00001 - Hostname	Hostname 'ACME_USA_Router_IL' does not follow the COMPANY_COUNTRY_TYPE_FUNCTION convention. 'Router' should be a short device-category (e.g., 'AP', 'PBX', 'FW'), not a spelled-out name.