

Lecture 12, 2/16/26Last week:Monday: • reviewed the rocket problem

- calculated the CM of a cone using $\vec{R} = \frac{1}{M} \int \vec{r} dm$, $p = \frac{H}{r}$
- $$\Rightarrow \vec{R} = \frac{1}{M} \int \vec{r} p dV = \frac{1}{M} \int (x\hat{x} + y\hat{y} + z\hat{z}) p dx dy dz$$
- in Cartesian coordinates

- Introduced angular momentum $\vec{I} = \vec{r} \times \vec{p}$

& showed $\dot{\vec{I}} = \vec{r} \times \dot{\vec{p}} = \vec{\tau} = \text{torque}$

- Only central forces $\Rightarrow \dot{\vec{I}} = 0$
- Showed Kepler's 2nd law results from $\vec{I} = \text{constant}$

Wednesday:

- Showed for a system of particles $\dot{\vec{I}} = \sum_{\alpha \neq \beta} (\vec{r}_\alpha - \vec{r}_\beta) \times \vec{F}_{\alpha\beta} + \vec{r}_\alpha \times \vec{F}_\alpha^{\text{ext}}$

If internal forces are all central, $\dot{\vec{I}} = \vec{r}_\alpha \times \vec{F}_\alpha^{\text{ext}} = \vec{\tau}^{\text{ext}}$

- Moment of inertia $I_z = I\omega$, $I = m r_\alpha^2 = \int r^2 dm = \int r^2 p dV$ for solid objects
where r is distance from \hat{z} -axis

- $\vec{I} = \vec{r}^{\text{ext}}$ about CM, even when CM is accelerating!


- Started Ch. 4: Energy

Work - KE theorem: $\Delta T = T_2 - T_1 = \int_1^2 \vec{F} \cdot d\vec{r} = \omega(1 \rightarrow 2)$

- practiced line integrals

Friday: Review Activity for MIPractice with line integrals:

(continued)



$$\vec{F} = y\hat{x} + 2x\hat{y}$$

$$W_I = \int_I \vec{F} \cdot d\vec{r} = \int_0^Q \vec{F} \cdot d\vec{r} + \int_Q^P \vec{F} \cdot d\vec{r}$$

$$d\vec{r} = dx\hat{x} + dy\hat{y}$$

We did path I last week. ($\omega_I = 2$)

Next, calculate ω_{II} :

$$\omega_{II} = \int_{\text{II}} \vec{F} \cdot d\vec{r} \quad \text{on path II: } x=y \Rightarrow dx=dy$$

$$\omega_{II} = \int_{\text{II}} \vec{F} \cdot (dx\hat{x} + dy\hat{y}) = \int_{\text{II}} (y dx + 2x dy) = \int_{\theta_x}^{P_x} (x dx + 2x dx) = \int_0^1 3x dx = \frac{3}{2} x^2 \Big|_0^1 = \boxed{\frac{3}{2}} = \omega_{II}$$

use $x=y$
 $dx=dy$

ω_{III} : On path III,

$$\omega_{III} = \int_{\text{III}} \vec{F} \cdot d\vec{r}$$

$$= \int_{\text{III}} F_x dx + F_y dy$$

$$= \int_{\text{III}} y dx + 2x dy$$

$$= \int_{\theta_0}^{\theta_P} \left[(\sin\theta) (\sin\theta d\theta) + z(1-\cos\theta)(\cos\theta d\theta) \right]$$


$$= \int_0^{\pi/2} (\sin^2\theta - 2\cos\theta - 2\cos^2\theta) d\theta = 2 \int_0^{\pi/2} \cos\theta d\theta + \int_0^{\pi/2} [(\sin^2\theta - \cos^2\theta) - \cos^2\theta] d\theta$$

$$= 2\sin\theta \Big|_0^{\pi/2} + \int_0^{\pi/2} [(-\cos 2\theta) - \frac{1}{2}(\cos 2\theta + 1)] d\theta$$

$$= 2\sin\pi/2 - 0 + \int_0^{\pi/2} \left(-\frac{3}{2}\cos 2\theta - \frac{1}{2} \right) d\theta$$

$$= z(1) - \frac{3}{2} \frac{1}{2} \sin 2\theta \Big|_0^{\pi/2} - \frac{1}{2} \theta \Big|_0^{\pi/2}$$

$$= 2 - \frac{3}{4} \left(\sin \cancel{\pi} - 0 \right) - \frac{\pi}{4} + 0$$



$$\Rightarrow y = R \sin\theta \quad R = 1$$

$$\begin{aligned} y &= \sin\theta \\ dy &= \cos\theta d\theta \end{aligned}$$

$$\Rightarrow x + R \cos\theta = R \quad R = 1$$

$$\begin{aligned} x + \cos\theta &= 1 \\ dx - \sin\theta d\theta &= 0 \\ dx &= \sin\theta d\theta \end{aligned}$$


$$\boxed{\omega_{III} = 2 - \frac{\pi}{4}}$$

Potential Energy and Conservative forces

Conservative forces : \vec{F} is conservative iff:

(i) \vec{F} depends on the particle's position \vec{r} only

(ii) for any points \vec{r}_1 , and \vec{r}_2 , $W(\vec{r}_1 \rightarrow \vec{r}_2)$ done by \vec{F} is the same for all paths between \vec{r}_1 and \vec{r}_2



Example: charge +q in an electric field $\vec{E} = E\hat{x}$

Let's find the work between any two points P_1 & P_2 .

$$\begin{aligned} W(P_1 \rightarrow P_2) &= \int_{P_1}^{P_2} \vec{F} \cdot d\vec{r} = \int_{P_1}^{P_2} q \vec{E} \cdot d\vec{r} = \int_{P_1}^{P_2} q E \hat{x} \cdot (dx \hat{x} + dy \hat{y} + dz \hat{z}) \\ &= qE \int_{P_1}^{P_2} dx = qE(x_2 - x_1) \Rightarrow \text{only depends on end points! Satisfies (ii)} \end{aligned}$$

Forces we've seen so far:

conservative

$$\vec{F}_G, \vec{F}_g, \vec{F} = q(\vec{E} + \vec{v} \times \vec{B})$$

nonconservative

$$\vec{F}_d, \vec{F}_f$$

$$\text{spring force } \vec{F} = -k\vec{x}$$

Why conservative forces?

Mechanical Energy: $E = KE + PE = T + U(\vec{r})$

Let's define potential energy


Choose a point \vec{r}_0 s.t. $U(\vec{r}_0) = 0$. Then:

$$\underbrace{U(\vec{r})}_{\text{definition}} = -W(\vec{r}_0 \rightarrow \vec{r}) = - \int_{\vec{r}_0}^{\vec{r}} \vec{F}(r') \cdot dr'$$

$U(\vec{r})$ is only well-defined for conservative forces

One can go backwards and find $w(\vec{r}_1 - \vec{r}_2)$ using $u(\vec{r})$:

$$w(\vec{r}_0 - \vec{r}_2) = w(\vec{r}_0 - \vec{r}_1) + w(\vec{r}_1 - \vec{r}_2)$$



$$w(\vec{r}_1 - \vec{r}_2) = w(\vec{r}_0 \rightarrow \vec{r}_2) - w(\vec{r}_0 \rightarrow \vec{r}_1)$$

$$= -u(\vec{r}_2) + u(\vec{r}_1) = -\Delta u$$

$$w(\vec{r}_1 - \vec{r}_2) = -\Delta u$$

Remember : $\Delta T = w(\vec{r}_1 - \vec{r}_2) \Rightarrow \Delta T = -\Delta u$
 $\Delta(T+u) = 0$

$$\Delta E = 0 \Rightarrow \text{energy is conserved!}$$

If \exists several forces, the total work just adds:

$$W = \int (\vec{F}_1 + \vec{F}_2 + \dots) \cdot d\vec{r} = \int \vec{F}_1 \cdot d\vec{r} + \int \vec{F}_2 \cdot d\vec{r} + \dots = w_1 + w_2 + \dots = -\Delta u_1 - \Delta u_2 - \dots$$

Principle of conservation of Energy for one particle :

If all N forces acting on a particle are conservative, each with corresponding $u_i(\vec{r})$, then the total mechanical energy is:

$$E = T + U = T + u_1(\vec{r}) + u_2(\vec{r}) + \dots + u_N(\vec{r}) \quad \text{is conserved} \quad (E \text{ is constant in time})$$

What about nonconservative forces (friction, drag, etc) ?

$$\Delta T = W = W_{\text{cons}} + W_{\text{NC}}$$

$$= -\Delta u + W_{\text{NC}}$$

$$\Rightarrow \underbrace{\Delta T + \Delta u}_{\substack{\text{Change in mechanical} \\ \text{energy of the system}}} = \underbrace{W_{\text{NC}}}_{\substack{\text{energy flowing in} \\ \text{or out of the} \\ \text{system}}} = \text{work done by non-conservative (NC) forces}$$

Example: You apply a constant force \vec{F} on a box and move it a distance D across the carpet with constant speed v .

- How much work did you do on the block?
- How much work did the carpet's friction do on the block?

$$\Delta E = \Delta T + \Delta U = W = W_{\text{you-on-block}} + W_{\text{friction}}$$

$$W_{\text{you-on-block}} = \int \vec{F} \cdot d\vec{r} = \int F dr = F \int dr = FD$$

$$\Delta T = \frac{1}{2}m \Delta(v^2) = \frac{1}{2}m v_f^2 - \frac{1}{2}m v_i^2 = 0 \quad (v = \text{constant})$$

$$\Delta U = 0 \quad (\text{no conservative forces did any work})$$

$$\Delta E = \Delta T + \Delta U = 0 = W_{\text{you-on-block}} + W_f$$

$$0 = FD + W_f$$

$$-FD = W_f$$

This makes sense. $\vec{F}_f = -\vec{F}$ since the block is not accelerating
 $(\sum \vec{F} = \vec{F} + \vec{F}_f = 0)$

$$W_{\text{total}} = \int (\vec{F} + \vec{F}_f) \cdot d\vec{r} = 0$$

Force as the Gradient of PE

Consider a particle acted on by $\vec{F}(\vec{r})$ (conservative) with PE $U(r^2)$. Let's look at how much work is done by \vec{F} in a small displacement: $\vec{r} \rightarrow \vec{r} + d\vec{r}$

$$\begin{aligned} W(\vec{r} \rightarrow \vec{r} + d\vec{r}) &= \vec{F}(\vec{r}) \cdot d\vec{r} \quad \text{---} \quad d\vec{r} = dx \hat{x} + dy \hat{y} + dz \hat{z} \\ &= F_x dx + F_y dy + F_z dz \end{aligned}$$

Also:

$$\begin{aligned} W(\vec{r} \rightarrow \vec{r} + d\vec{r}) &= - [U(\vec{r} + d\vec{r}) - U(\vec{r})] \equiv dU \\ &= - [U(x+dx, y+dy, z+dz) - U(x, y, z)] \end{aligned}$$

Note: for $f(x)$ of one variable, one can write

$$df = f(x+dx) - f(x) = \frac{df}{dx} dx$$

For a fn of 3 variables, we have instead:

$$dU = U(x+dx, y+dy, z+dz) - U(x, y, z)$$

$$= \frac{\partial U}{\partial x} dx + \frac{\partial U}{\partial y} dy + \frac{\partial U}{\partial z} dz$$

↑ ↑ →
partial derivatives