

currency.

- **Turnover Volume** total volume of trading operations (number of lots) for the period specified in the Charge field (day or month).
- **Notional value** the value of a deal, calculated depending on the symbol's margin/profit calculation method.

For the symbols with the Forex calculation type, the value is calculated in the base symbol currency and is equal to the product of the contract size and the volume. For example, for EURUSD with the contract size of 100,000, the value of 1 lot is equal to 100,000 EUR.

For the symbols with the CFD, CFD Leverage, CFD Index and Futures type, the value is also calculated in the base currency. Since the contract size of such instruments is not expressed in money (it can be expressed, for example, in the amount of assets), the contract size is additionally multiplied by the instrument price to obtain the value in monetary terms. For Futures symbols, the final value is additionally multiplied by the ratio of tick value to tick size. For example, if some Futures symbol has USD as the base currency, the contract size is equal to 100, the cost is 33, and the tick value to tick size ratio is 1/0.1, the value of one lot of the position is equal to $100 \times 33 \times 10 = \text{USD } 33,000$. For a CFD symbol with the same parameters, one lot size would be $100 \times 33 = \text{USD } 3,300$.

If the symbol base currency differs from the turnover currency specified in commission settings, the calculated value will be additionally converted using the relevant exchange rate.

Example: levels 0 9,999 and 10,000 1,000,000 are specified. GBP is specified as the currency. Commission is charged instantly. The trader executes a GBPUSD 1.0 Buy deal at 1.34644, with a contract size 10,000. The deal value is $1 \times 10,000 = \text{GBP } 10,000$. No conversion is needed here, as the base currency matches the selected one. The deal falls into the second range of commission.

- **Profit** profit/loss of the deal or the total profit/loss of a client's deals for a day or month, depending on the selected commission charging mode. The currency in which the level will be indicated and to which the profit will be converted, is specified in the field below.
- **Turnover currency** settlement currency. The group deposit currency is used by default (if no other currency is specified).
- The value of the client's deals will be converted to this currency when calculating turnover in money. Accordingly, commission levels will be specified in this currency.
- It is used when setting up levels based on the deal value.

Commission levels are configured at the bottom of the window.

In the **From** and **To** fields, set the minimum and maximum values for the range. The value is specified in selected commission level units: deal volume, turnover, profit, etc. For example, the Range field is set to "Volume". In this case, a level between 0 to 10 will mean that the specified commission will be charged on deals with a volume not

more than 10 lots.

If levels are specified based on profit, the range values can be negative. For example, from -1000 to -100 means that the level will be applied to the corresponding loss.

The ranges must not overlap. If the operation falls into several ranges, the commission is charged according to the first suitable range.

If you do not need multilevel commissions, set one level covering the entire range of values for the selected condition.

Next, specify commission calculation parameters:

- **Commission** volume of commissions, the unit depends on the commission calculation type selected in the appropriate field.
- **Minimal/Maximal** minimum and maximum amount of commission charged. The units in which the value is specified depend on how the commission is calculated. If commission is calculated as a percentage, the values are specified in the client's deposit currency. In all other cases, the values are indicated according to the calculation method in the base currency, the group currency, in points, etc. To disable the minimum or maximum commission limit, set the value to 0.
- **Mode** units of commission calculation:
 - **Deposit ccy** commissions are calculated in the deposit currency specified for this group.
 - **Base ccy** commissions are calculated in the base currency of the symbol the deal was executed for.
 - **Profit ccy** commissions are calculated in the profit currency of the symbol the deal was executed for.
 - **Margin ccy** commissions are calculated in the currency of margin requirements specified for the symbol of the deal.
 - **Points** commissions are charged in points of the symbol price. Point value is calculated as the profit for a position of the same direction (long/short) and size of 1 lot with the difference of close and open prices equal to 1 pips (point).
 - **Percents** the specified percent is charged from the real value of the deal/turnover. The value is calculated in the base currency. For further calculation details please see the description of the Notional value field above. The trade/turnover value calculated in the base currency is converted to the group deposit currency, and the final commission (the specified percentage) is calculated based on this value.
 - **Specified ccy** commissions are calculated in the currency specified in the "Currency" field.
- **Profit percent** commission is calculated as a percentage of the deal profit (if charged instantly) or of the trader's total profit for the day or month (if charged at the end of the day or month). In case of a loss, the corresponding commission value will not be debited from the trader, but will be credited to the trader's account instead. To avoid such charges, set the minimum commission size to 0 and/or set the filter by deal profit.

MetaTrader 5 trading platform

- **Currency** a currency that will be used for commission calculation. This field is active only in the "Specified ccy" mode of commission calculation. A currency has a trilateral representation, for example, EUR, USD, JPY, etc.
- **Type** type of commission charging:
 - **Per trade** commissions are charged from each executed deal.
 - **Per volume** commissions are charged from the volume (from each lot) of executed deals. Only executed (filled) volume of trade operations is considered.

MetaTrader 5 Trading Platform / Platform Setup / Groups / Commission Settings / Commission Calculation

Commission Calculation

The periodicity of calculation and charging of trade operation is specified in the "Charge" field. The following variants possible:

- **Instant** commissions are charged instantly during execution of each deal. The value of a standard commission charged instantly is displayed in the Commission field of a deal. Agent commissions are charged as separate balance operations ("Agent commission" deals).
- **Daily** the commission amount is accumulated during a day in a special field of a client record. At the end of the day the accumulated amount is charged from the account with a separate balance operation (a deal of the Daily commission or Daily agent commission type).
- **Monthly** the commission amount is accumulated during a month in a special field of a client record. At the end of the month the accumulated amount is charged from the account with a separate balance operation (a deal of the Monthly commission or Monthly agent commission type).

This section describes how the daily and monthly calculation of commissions is performed.

Blocking of Assets

The mechanism of asset blocking is implemented only for the standard commissions to guarantee the possibility of paying of commission by clients. It is not used for agent commissions since that are not charged from clients that perform trade operations.

Depending on the option chosen, the preliminary calculated amount of commission is blocked at client account during a day or a month:

- If commission is charged for volume of a single trade operation, then its size can be calculated immediately. The corresponding volume of assets is blocked at the account.
- If commission is charged for turnover (in money of volume), the system considers the volume of trade operations performed earlier during the current day/month. As soon as the client's daily/monthly turnover exceeds a certain level, the amount of the locked commission is immediately recalculated in accordance with the next level.

The volume of blocked assets is displayed in the row of state of client account:

☹ Balance: 10 283.51 Equity: 9 349.91 Commission: -1.00 Margin: 4 397.03 Free Margin: 4 952.88

Blocked assets are excluded from Equity and Free Margin. Thus they cannot be used for trading. The commission that will be blocked for a placed order is also considered when checking the free margin.

- Commission is also blocked when placing all the types of pending orders. At that if a pending order is deleted, the corresponding volume of commission is unblocked. If a pending order is filled, only the commission that corresponds to the filled volume of the order stays blocked.
- Blocked assets are also released for all deleted, closed and canceled trade requests that didn't result in execution of a deal.

Charging of Commissions

The final calculation and charging of commissions are performed at the end of day or month depending on the settings. The turnover of trade operations for the specified period is calculated. Further the final calculation of commissions is performed, and then they are summed up for each client. In case of standard commission, the total amount of commission is withdrawn from client account as a balance operation.

- According to each commission configuration only one balance operation is performed for each client. The entire volume of commissions accumulated during a day/month is charged with a single deal.
- After the deal of charging the standard commission is performed the volume of blocked assets is zeroized.
- The final calculation and charging of commissions are performed at the end of day or month depending on the settings. This peculiarity should be considered when moving accounts between groups with different commission settings. For example, if during a trade day an account is moved from a group with commissions charged daily to a group without commissions, no commission will be charged from that account for all the operations performed on that day.

In case of agent commission, the assets are charged to agent accounts using balance operations. Just the same as the standard commissions, one balance operation is performed according to each commission configuration. Balance operations are performed separately for each account, where an agent account is specified.

Account number, from operations on which an agent gets a commission, is specified as a comment to the corresponding balance deal used for accruing the agent commission. The comment is specified in the following form:

agent from #xxxxxxx

MetaTrader 5 trading platform

Deal #243822693 daily commission -137.28 []

ammu baba, 1835114, demo\demo forex-5-hedged, 1 : 100

Ticket	Time	Type	Volume	Price	Reason	Commission	Profit
⊖ 243822693	2022.09.26 23:59:59.000	daily commission			Client	0.00	-137.28

Details

Journal

Deal: 243822693

DAILY COMMISSION

-137.28

Create time: 2022.09.26 23:59:59.000

Reason: Client

Dealer ID:

Expert ID:

External ID:

Comment:

Modifications:

Report...

Update

Cancel

Help

Commission deals can have the following types:

- **DAILY COMMISSION** standard commission charged daily;
- **MONTHLY COMMISSION** standard commission charged monthly;
- **DAILY AGENT COMMISSION** agent commission charged daily;
- **MONTHLY AGENT COMMISSION** agent commission charged monthly;

The "Comment" field of the deal contains text specified in the "Description" field of the commission configuration or the number of an account, from operations on which an agent commission is charged.

MetaTrader 5 Trading Platform / Platform Setup / Groups / Commission Settings / Commission Examples

Examples of Settings

Let us consider some commission configuration examples.

Standard commission

Commissions
? ×


Adjustment of commissions parameters of the symbol.

Name:
Description:

Symbol:
☒ Standard commission

Range:
Charge:
☐ Agent commission

Turnover currency:
☐ Fee

Deal entry:
Deal action:

Deal profit:
Deal reason:

From	To	Commission	Minimal	Maximal	Mode	Currency	Type
0	10	1	0.00	0.00	deposit ccy		per trade
11	20	0.9	0.00	0.00	deposit ccy		per trade

Add
Edit
Delete

OK
Cancel

MetaTrader 5 trading platform

Such a commission will be applied when any of the clients from the group performs a deal for a symbol from the "Forex" subgroup. Commission will be charged on both entry and exit deals. The amount will be debited from the trader's account immediately after the operation using a balance deal of the "Commission" type.

For each deal with a volume of up to 10 lots, 1 unit in the group's deposit currency will be charged. For deals with a volume of 11 to 20 lots, 0.9 currency units will be charged. No commission will be charged for larger deals.

Profit commission

Commissions



Adjustment of commissions parameters of the symbol.

Name: Profit

Description: Commission for profitable deals

Symbol: *

Range: Profit

Charge: Instant

Turnover currency:

Deal entry: All

Deal action: All

Deal profit: Profit

Deal reason: All

☒ Standard commission

☐ Agent commission

☐ Fee

Add

Edit

Delete

From	To	Commission	Minimal	Maximal	Mode	Currency	Type
0	1000	0.5	0.00	0.00	profit percent		per volume
1001	10000	0.6	0.00	0.00	profit percent		per volume

OK

Cancel

MetaTrader 5 trading platform

Such a commission will be applied when a client from the group performs a profitable trade for a symbol from the "Forex" subgroup. Although no deal direction filter is set, commission will only be charged for exit deals. Entry deals do not have a financial result; therefore, they do not have profit and do not participate in calculations. The amount will be debited from the trader's account immediately after the operation using a balance deal of the "Commission" type.

For each deal with a profit up to 1,000 units of deposit currency, a commission of 0.5% of the profit amount will be charged. For example, if a deal profit is USD 540, the commission will be equal to USD 2.7. For deals with the profit from 1,001 to 10,000 units, commission will be equal to 0.6% of the profit. No commission will be charged for trades with a larger profit.

MetaTrader 5 Trading Platform / Platform Setup / Groups / Group Types

Group Types

The trading platform allows to work with different types of groups of accounts. The system determines the types of groups by their names and processes them respectively. There are following types of groups:

Demo Groups

Demo groups contain demo accounts. They allow to work in a training mode without real money to perfect a trading strategy. This kind of accounts offer the same possibilities as the real ones. The difference is that the demo accounts can be opened without corresponding investment, however such accounts cannot be used for earning real money. Demo accounts can be opened directly from the client terminal, and the real ones are only opened from the manager and administrator terminals.

A created group is considered a demo one if its name (including path) includes "demo" symbols (case sensitive). For example, the "demo\forex", "demo-USD" and "real\demoforex-USD" groups are demo and the "Demoforex" "fx-USD" groups are not.

Add demo groups to the "Account allocation" section to enable your clients to open accounts in these groups directly via client terminals.

Manager Groups

Groups are considered manager ones if their names (including path) include "manager" symbols (case sensitive). For example, "manager_CFD" or "manager_real". Only accounts that belong to the manager groups are able to connect to the trade servers using the manager and administrator terminals and the corresponding APIs. Manager accounts can only be created on the basis of accounts that belong to the manager groups.

Contest Groups

This type is intended for conducting contests among traders. Groups are considered contest ones if their names (including path) include "contest" symbols (case sensitive). For example, "contest_forex" or "contest\USD".

Contest accounts cannot be opened from terminals, as they can only be created by the broker.

Contest accounts are marked with a blue icon in client terminals. When a trader is connected to such an account, the "Contest account" title is displayed in the terminal window header. In some of the reports contest accounts are shown in separate groups. Contest accounts operate similarly to demo ones.

Preliminary Group

One preliminary group called "preliminary" is automatically created on the server. Preliminary accounts are created in it when requests for opening real accounts are sent from the client terminals. Managers can track such accounts and contact the clients using contact details specified during the registration. As soon as an official agreement with a client is made, a manager can move the account to one of the real groups, what allows the client to start working immediately.

- Trading is prohibited for all symbols in the preliminary group.
- All accounts are created with zero balance in the preliminary group.
- When opening an account in such a group, a client receives an email based on the special template.
- Add preliminary groups to the "Account allocation" section to enable your clients to request live accounts directly via client terminals.

Coverage Groups

Groups are considered as coverage ones if their names (including path) include "coverage" symbols (case sensitive). For example, "coverage\forex". This type of groups is intended for creating accounts that are used for covering client positions. Summary rates by such accounts are displayed in the manager terminal. A more detailed information is given in a separate section.

Real Groups

This kind of groups contain account for working with real money. If a group doesn't fall into any category by its name among the ones mentioned above, then the system considers it a real one.

- If the groups in the system have certain hierarchy then their names contain the corresponding paths to them. That path is an essential part of a group name and it is considered when determining its type. For example, all the sub-groups of the "manager" group will be considered as manager ones.
- Do not use indications of different group types within the name of a group. For example, managers\demo.

Recommendations on Naming Groups

For making the work with groups convenient it is recommend to follow several rules when giving the names to groups:

- It is recommended to give sensible names to the demo groups because they will be visible to the clients when opening demo accounts from the client terminals. Only lower-case and upper-case letters, digits and "_" (underline), "-" (hyphen) symbols are allowed in the group names;
- Names of user groups of company offices should end with a certain combination of symbols and should not end with '_' symbol. For example, '_kzn';

MetaTrader 5 trading platform


- It is possible to unite the groups by their regional (country) belonging. For example, one can add certain symbol combinations to the group names. For example, '_ru_'.

MetaTrader 5 Trading Platform / Platform Setup / Groups / Import of Groups

Import of Groups

Using the Administrator terminal, you can import groups from other MetaTrader 4 and MetaTrader 5 servers. In order to proceed with the import, select "🔄 Import" in the context menu of the "Groups" section.

Groups can be imported only if the administrator is connected to the main trade server.




MetaTrader 5 trading platform

The first step is to specify the details of the server from which the groups will be imported, as well as details of the account to connect to it:

- **Server Type** select here the type of the server from which groups will be imported: MetaTrader 5 or MetaTrader 4.
- **Server** the IP address and the port number of the server, separated by a colon.
- **Login** the number of the manager account for authentication on the server.
- **Password** the account password for authentication on the server.
- **Use certificate from file** if accounts are imported from a MetaTrader 5 server with the extended authorization mode enabled, you will need a confirmed certificate to connect using the above specified account details. If the certificate has previously been installed in the storage of the operating system, it will be automatically recognized by the import system. If the certificate has not been installed, you must enable this option and specify the path to it file manually.
- **Certificate File** click "Browse" and specify the pfx-file of the certificate. The certificate file received in the terminal is saved in */terminal data folder/profiles/server name/certificates/*.
- **Certificate Password** the password of the certificate.

- Import in the extended authorization mode is possible only from MetaTrader 5 servers.
 - To import groups, you must have a manager account with the "Configuring Groups" permission on the source server.

Once all the details are specified, press the "Next" button. In the case of a successful connection to the server, the list of available groups appears in the next window:



How to select groups:

- Double click on its icon, and the icon will become bright.
- Double click on the section icon, in this case all groups from the section are selected.
- Click on the "Select All" button.

Here you can also view settings of groups to import. To do this, double click on their names. To start the import, click the "Done".

- After importing, check the settings of all groups.
- All groups are bound to the main trade server. After importing the binding can be changed.
- Only new groups are imported. Settings of existing groups of the same name are not overwritten.

Features of Import from MetaTrader 4

There are some specific features of import from MetaTrader 4 servers:

- When you import groups from the MetaTrader 4 server, existing settings are converted, and default values are assigned to missing settings.
- When you import groups from the MetaTrader 4 server, trade settings of symbols for the groups are not imported.
- Groups from the MetaTrader 4 server are imported into the currently selected groups section. When importing groups from the MetaTrader 5 server, their hierarchy is preserved.

MetaTrader 5 Trading Platform / Platform Setup / Groups / Extended Authentication Setup

Extended Authentication Setup

To ensure a high level of account security, the trading platform is provided with an extended authentication feature. During extended authentication, an SSL certificate is required in addition to a login and password, in order to connect to an account. This certificate can be automatically generated and issued to a client during first connection to the trade server. Also, you can use your own certificate: generate it using third-party software, issue it to the client, and then import to the account on the trade server side.

Extended authentication features:

- Enabled in group settings.
- Used only as an addition to standard authentication. Users need to specify their account login and password in any case.
- Works for all account types - client, manager and administrator.

Extended Authentication Using Certificates Generated on the Server

The trading platform provides a mechanism for automatic generation of client certificates. A certificate can be generated:

- on the basis of the certificate from the license of the trading platform. The license contains a certificate especially issued by MetaQuotes Software Corp. for each individual company.
- on the basis of any other certificate that can be used to generate certificates. Such a certificate must contain a private key.

One of these options can be selected in the "Certificates" section. In any case, the following requirement must be met:

The Certification Authority that has issued the certificate used to generate the client certificates must be added to the trusted CA list. Such a mechanism prevents from the use of fake certificates issued by unknown authorities.

Broker-Demo - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Export Import Apply + Settings X Sort ↑ ↓

Network Cluster
Integrations
Finteza Analytics
VPS
Mail Servers
Messengers
KYC
Web Services
Automations
Security
Certificates
Firewall
Anti DDoS Protection
Time
Holidays
Groups (691)
Clients & Accounts
Orders & Deals
Gateways

Certificates

Client certificates issuing and trusted authorities

Client Certificates

Issuing type: [on the basis of license](#) Issued to: MT5-FOBRO-01-STANDARD

Issued by: MetaQuotes Software Root CA

Trusted authorities

[Add](#)

MT5-FOBRO-01-STANDARD [Disable](#)

Issued by: MetaQuotes Software Corp.


Certificates increase account security. To start using them, enable extended authentication for a client group. [Read more >](#)

For Help, press F1

49.5 / 0.0 M

Configuration of the Client Group

To enable the extended authentication mode for a group of clients, go to its "Common" tab. In the "Authentication" field select "1024-bit RSA SSL Certificate" or "2048-bit RSA SSL Certificate". The 2048-bit encryption is more secure, but the generation of the certificate is slower. In most cases, a 1024-bit encryption is sufficient.



Group: demo\demo forex

Common Company News & Mail Permissions Margin Symbols Commissions Reports

Group is a set of users that have the same permission settings and service conditions. Please specify name of group, deposit currency, trade server, and authentication type.

Name: demo\demo forex Currency: USD

Trade server: Trade Main, 1 Digits: 2

Authentication: 1024-bit RSA SSL certificate Minimum password length: 8

One-time password: Disabled ☐ Force one-time password usage

☒ Enable connections

☐ Enable certificate confirmation

☐ Change password at first login

☒ Show the risk warning window after connection

☐ Enforce country-specific regulatory restrictions for retail clients

OK Cancel Help

Confirmation of Certificates

For additional security, you can enable manual confirmation of certificates generated for clients ("Enable certificate confirming" option).

The first time a user connects in the extended authentication mode, a certificate is generated. However, the below restrictions apply until the generated certificate is confirmed by a manager or an administrator:

- The account cannot be used for connection in the administrator or manager terminal.
- In the client terminal, connection is possible only in the "investor" mode, without the possibility to trade.

After generating a certificate, a special email is sent to the terminal describing the action to be taken to confirm the certificate (for example, call the specified number and identify personality). The email appears on the "Mailbox" tab of the Toolbox window.

After a user performs the action described in the email, an administrator/manager can confirm the certificate on the "Security" tab of the account.

- For demo groups certificates are confirmed automatically immediately after they are generated.
- If during certificate confirmation the user is connected to a trade server using the client terminal, the user will need to re-connect in order to switch to the full-featured operation with an account (with an access to trading functionality).

Certificate Generation


When connecting to the server in the extended authentication mode, the user first completes the standard authentication procedure by specifying the login and password. The server checks if there is a certificate for this account. If a certificate is found, the extended authentication is performed (the client certificate is checked). If it is not found, a new certificate is generated.

The trade server sends to the terminal a request to generate two keys, including a private and a public key. The private key is used for decrypting server messages. It is not sent anywhere, and is only stored in the terminal (in an encrypted form, with reference to the hardware). The public key is sent to a trade server and is saved in the client record. The trade server will use the key to encrypt messages that are sent to the terminal.

Based on the account details (client's name and account number), the server generates a public key certificate and signs it using its private key (which guarantees that the certificate cannot be falsified). This certificate is sent to the terminal. It will be used for authenticating the user on the server, and for encrypting data sent by the terminal to the server.

Next, the terminal packs the previously generated private key and the public key certificate received from the server into one file (container) PFX certificate. The PFX is additionally protected with a password. Thus, even having obtained a PFX certificate, attackers will not be able to use it.

The password for protecting the PFX certificate is set by the user in a special dialog:



The following should be specified here:

- **Password** a password to install the certificate;
- **Confirm Password** confirmation of the password to avoid errors;
- **Add certificate to the Windows System Storage** if this option is enabled, the certificate is automatically added to storage of the operating system. If you install the certificate to the system storage, then you can choose not to keep the PFX file of the certificate on the disk in the folder /terminal_data_folder/config/certificates. The terminal always checks the certificate both in the system storage and in the specified folder on the disk.

The password set for a certificate must contain at least two types of characters (lower case, upper case, digits and special symbols) and be no less than 5 characters long.

PFX certificate protected by the specified password is saved in the directory /profiles/server name/certificates of the administrator (manager) terminals (or in the directory /config/certificates/ of the client terminal) so that it can later be moved. The names of certificates are given according to the following rule: *Login_ID_Name.pfx*, where:

- **Login** is the account number;
- **ID** is the short name of the company in which the account has been opened;
- **Name** is the name of the client specified when creating the account.


MetaTrader 5 trading platform

- Even having obtained the *.pfx file of the certificate, you cannot use it, if you do not know the password. The minimum password length is set in the group settings.
- Certificate is generated only during the first connection of an account or in case a certificate has been reset on the server.
- The certificate is not required when connecting using an investor password.

Extended Authentication Using Custom Certificates

The trading platform allows using custom client certificates for authentication, in case it is required by your company's security policy.

To use custom certificates, disable generation of certificates in the trading platform. In the "Certificates" select "Issue client certificates on the basis of:**disabled**".



MetaTrader 5 trading platform

The list of trusted certification authorities must contain only one CA that issues the company's certificates.

Automatic generation of certificates can be disabled only for separate groups. This can be done on the "Common" tab of a group by setting RSA Custom in the "Authentication" field.

Configuration of the Client Group

To enable the extended authentication mode using custom certificates for a group of clients, go to the "Common" tab of the group settings. In the "Authentication" field, select "Custom SSL Certificate".

If automatic generation of certificates is disabled for the entire platform in the "Certificates" section, any mode of extended authentication (1024-bit, 2048-bit or Custom SSL Certificate) allows the use of custom certificates.

Group: demo\demo forex

Common Company News & Mail Permissions Margin Symbols Commissions Reports

Group is a set of users that have the same permission settings and service conditions. Please specify name of group, deposit currency, trade server, and authentication type.

Name: demo\demo forex Currency: USD

Trade server: Trade Main, 1 Digits: 2

Authentication: Custom SSL certificate Minimum password length: 8

One-time password: Disabled ☐ Force one-time password usage

☒ Enable connections

☐ Enable certificate confirmation

☐ Change password at first login

☒ Show the risk warning window after connection

☐ Enforce country-specific regulatory restrictions for retail clients

OK Cancel Help

The function of additional manual confirmation is not used for custom certificates. Confirmation is performed automatically during import of the certificate to a client account.

Issuing Certificates to Clients

When using custom certificates, their distribution among clients is the entire responsibility of the company. Certificate files must be somehow passed to clients (for example, on a digital medium, including e-token).

To use the certificate for authentication, the client must do one of the following:

- copy the certificate file to the directory /profiles/server name/certificates of the administrator (manager) terminals or in the directory /config/certificates/ of the client terminal.
- install the certificate in the operating system storage of the computer, from which the user will work with the trading platform.
- connect the digital storage (e-token) to the computer.

During authentication the terminal checks the described storages of terminals. It should be noted that the necessary certificate in the folder /certificates of the terminal is searched for by the account number specified in the certificate file name. The account number must be specified at the beginning of the certificate file name, for example, 10034_JohnSmith.pfx.


This requirement does not apply to the certificates installed in the operating system storage or a portable storage.

Import of a Certificate into a Client Account

With the extended authentication, the server compares the certificate of a user with the certificate matched to his or her account on the server. If automatic generation of certificates is used on the server, the issued certificates are automatically imported into the account.

When using custom certificates, it is necessary to import them into client accounts. To do this, go to the "Security" tab of the client account and use the import function:

MetaTrader 5 trading platform



When importing a certificate, it is automatically confirmed. The function of additional confirmation is not used for custom certificates.

MetaTrader 5 Trading Platform / Platform Setup / Groups / Position Accounting Systems

Position Accounting Systems

Two position accounting systems are supported in the trading platform: Netting and Hedging. The system used depends on the group settings:

Group: demo\demo forex

Common Company News & Mail Permissions **Margin** Symbols Commissions Reports

 Please set up the mechanism of margin calculation for the group: choose the method of calculation and margin requirements.

Risk management: for Retail Forex, CFD, Futures

Margin call level: for Retail Forex, CFD, Futures
for Retail Forex, CFD, Futures with hedged positions
for Stock Exchange, based on margin discount rates
☐ Stop out fully hedged accounts

☐ Compensate negative balance after stop out

☐ Withdraw credit after negative balance compensation

Profit/loss in free margin

Unrealized profit: use unrealized profit/loss

Daily fixed profit: use daily fixed profit/loss

☐ Release fixed profit at the end of day

Virtual credit: (applies only to opening new positions)

OK Cancel Help

Different position accounting systems are only supported for the OTC market. On exchange markets, the "netting" system is always used.

Netting System

With this system, you can have only one common position for a symbol at the same time:

- If there is an open position for a symbol, executing a deal in the same direction increases the volume of this position.
- If a deal is executed in the opposite direction, the volume of the existing position can be decreased, the position can be closed (when the deal volume is equal to the position volume) or reversed (if the volume of the opposite deal is greater than the current position).

It does not matter, what has caused the opposite deal – an executed market order or a triggered pending order.

The below example shows execution of two EURUSD Buy deal 0.5 lots each:

Toolbox									
Symbol	Ticket	Time	Type	Volume	Price	S / L	T / P	Pri	
eurusd	207796062	2018.02.12 16:50:55	buy	2.00	1.225935	1.22104 ×	1.23104 ×	1.225	
⚙ Balance: 1 000 000.00 USD Equity: 999 959.00 Margin: 2 451.87 Free Margin: 997 507.13 Margin Level: 40 783.52 %									
Trade	Exposure	History	News	Mailbox 7	Calendar	Company	Market 12	Alerts	Signals
	Code Base	Expert							

Hedging System

With this system, you can have multiple open positions of one and the same symbol, including opposite positions.

If you have an open position for a symbol, and execute a new deal (or a pending order triggers), a new position is additionally opened. Your current position does not change.

The below example shows execution of two EURUSD Buy deal 0.5 lots each:

Toolbox									
Symbol	Ticket	Time	Type	Volume	Price	S / L	T / P	Pri	
eurusd	207769623	2018.02.12 15:58:48	buy	1.00	1.22439	1.21939 ×	1.22939 ×	1.225	
eurusd	207795600	2018.02.12 16:50:12	buy	1.00	1.22554	1.22054 ×	1.23054 ×	1.225	
⚙ Balance: 1 000 000.00 USD Equity: 1 000 121.00 Margin: 2 449.93 Free Margin: 997 671.07 Margin Level: 40 822.43 %									
Trade	Exposure	History	News	Mailbox 7	Calendar	Company	Market 12	Alerts	Signals
	Code Base	Expert							

Impact of the System Selected

Depending on the position accounting system, some of the platform functions may have different behavior:

- Stop Loss and Take Profit inheritance rules change. For more details please read the client terminal Help.
- To close a position in the netting system, you should perform an opposite trading operation for the same symbol and the same volume. To close a position in the hedging system, explicitly select the "Close Position" command in the context menu of the position.
- A position cannot be reversed in the hedging system. In this case, the current position is closed and a new one with the remaining volume is opened.
- In the hedging system, a new condition for margin calculation is available Hedged margin.

MetaTrader 5 Trading Platform / Platform Setup / Clients

Clients

The Client is a separate entity in the trading platform. This is the aggregate information on a trader, including personal data, documents and trading accounts. The client record stores the history of all changes: every version made by any manager is available in the Versions section.

All accounts registered in the platform are automatically connected to an existing or a new client. Thus, the client entity conveniently stores all accounts of a trader, even those opened in different groups or having different types. The new arrangement of data, registers all client performed actions before opening a real account, and allows evaluation of the client's real LTV (Life-Time Value).

All clients are displayed in a separate section:

MetaTrader 5 trading platform

Broker - MetaTrader 5 Administrator

File Edit View Services Help 34.8 / 0.9 MB

Disconnect Refresh Restart Server Import Export Apply + Settings X Left Arrow Right Arrow Sort

ID	Name	Country
1483061	Alverta Fadel	Canada
1483062	Pennie Walter	Estonia
1483063	Nicolasa Waters	

Client: 1001 - Smith John Murray

Client

Type: Individual

Status: Approved

KYC status: Approved

Assigned manager: 1030, Kate Wilson

Preferred trading group: demo\forex-eur

Approved by: 1000, First Admin

Approval date: ☒ 2024.01.18

Close date: ☐

Last contact date: ☒ 2024.01.18 14:39:10

Lead source: www.broker.com

Lead campaign: preliminary-desktop

Introducer: Kate Wilson

Export... Cancel Update

Client Details:

- 1013 Smith John
- 1017 Smith John
- Real Trading Accounts
- 1029 Smith John
- Demo Trading Accounts
- 1001 John Smith
- 1002 John Smith
- 1034 Smith John

MetaTrader 5 trading platform

Before you start, request information on desired clients from the server. At the bottom of the section, specify the first name, last name, phone number, email or client ID, and then click Request. To receive information on all clients, specify the mask "*".

- All clients are stored separately for each trading server. Client records are created on the same server, where the clients' trading accounts are exist (as well as the groups, to which they belong). A manager can only view and manage clients, which exist on the same trade server, where the manager account is created.
- The manager account needs to have appropriate permissions for accessing the Clients section.

Creating clients automatically and manually

All accounts registered in the platform via client terminals are automatically linked to clients. If there is no client record for the newly created account, such a record is created automatically. All information from the account is copied to the client record. Minimum details are required for demo accounts: name, surname, company, email and phone number. More data can be requested during the registration of preliminary accounts via client terminals. Depending on platform settings, the following data may be requested:

- Detailed personal data
- ID and proof-of-address documents
- Nationality and tax ID number
- Social status, employment and education
- Income and its sources
- Trading experience in various financial markets

If you enable the extended account registration form, all the above data will be automatically added to client records. Thus, you will not need to additionally request this information and add it manually to the database.

MetaTrader 5 trading platform

Open an Account

Opening a real account
A real account is required for live trading

First name: John

Second name: Smith

Middle name: Murray

Date of birth: 1989-09-01

Language: Russian

Email: john@smith.com

Phone: +1 (Canada, United States)

If the phone or email is not valid, please use a different one

☒ Use hedge in trading

Country: United States

Account type: Real EUR (Main Trade Account)

Personal details are used for identification
The information is handled in accordance with the law

Client: 1001 - Smith John Murray

Client

Personal

Address

Regulation

Documents

Comments

History

Preliminary Trading Accounts

Real Trading Accounts

Demo Trading Accounts

1013 Smith John

1017 Smith John

Real Trading Accounts

1029 Smith John

Demo Trading Accounts

1001 John Smith

1002 John Smith

1034 Smith John

Personal

Title
Mr.

First name
John

Second name
Smith

Middle name
Murray

Gender
Male

Birthdate
☒ 1998.02.24

Language
English

Preferred language
Not specified

Email
john@smith.com

Mobile
+1 (Canada, United States)

Messengers (skype:username, icq:username)
skype:john-smith


Social Networks (fb:username, twitter:username)
fb:johnsmith

External ID
1249993399

1134

MetaTrader 5 trading platform

To create a client manually, click "+New Client" in the context menu of the client list or press "Ctrl+N".



Then specify required information in sections Personal data, Address and Regulation. Once you save the client record, document and trading account management sections will appear.

When a trading account is created via the Administrator terminal, an appropriate client record is not created automatically. To create it manually based on account data, open the account dialog and click "New Client" in the lower left corner. To create an account linked to a client record, use the "Trading accounts" section in the appropriate client record.

Binding accounts to clients and copying data

The trading platform automatically binds each trading account opened via the client terminal to a client record. Search is based on the comparison of trading account data with data in client records:

- First, a client with the matching First Name, Last Name and E-Mail is searched (all the three should match, case insensitive).
- If no such client is found, the system searches for a client with the matching First Name, Last Name and phone number (all the three fields should match, case insensitive).

If no suitable record is found, a new client is created and a trading account is bound to it.

After that the account data are copied to the client record in accordance with priority. Demo accounts and client records created based on demo accounts have the lowest priority. The highest priority is given to data from real accounts and manually created clients.

- **Demo account** when binding such an account to an existing client record, which was created earlier on the basis of another demo account, only missing data is copied.
- **Preliminary account** when binding such an account to an existing client record, which was created earlier on the basis of a demo account, all data are copied (existing data are overwritten). If the client was created on the basis of a preliminary account, only missing data is copied. If the client was created on the basis of a real account or was added manually, data is not copied.
- **Real account** when binding such an account to an existing client record, which was created earlier on the basis of a preliminary or demo account, all data are copied (existing data are overwritten). If the client was created on the basis of a real account or was added manually, data is not copied.

If the account is linked to a newly created record, all account data are copied.

Data are also copied to clients after each time the account is changed. In this case, the information is only copied to the empty fields of the client. For example, when the manager adds an address to account data. If the address is not filled for the client to whom the account is bound, the data will be copied.

Differentiation of access to clients for managers

A client record is available to the manager account if one of the following conditions is met:

- The client is created by this manager
- The client is explicitly assigned to the manager
- The preferred trading group, set for the client is available to the manager (the manager has permissions for the group)
- Any of the trading accounts bound to the client is available to the manager (the manager has permissions for the group in which the account is located)

General client information

This section displays general information about the client, as well as the responsible employee by whom the client is managed.

Client: 1001 - Smith John Murray

Client

Personal

Address

Regulation

Documents

Comments

History

Preliminary Trading Accounts

1013 Smith John

1017 Smith John

Real Trading Accounts

1029 Smith John

Demo Trading Accounts

1001 John Smith

1002 John Smith

1034 Smith John

Client

Type

Individual

Status

Approved

KYC status

Approved

Assigned manager

1030, Kate Wilson

Preferred trading group

demo\forex-eur

Approved by

1000, First Admin

Approval date

☒ 2024.01.18

Close date

☐

Last contact date

☒ 2024.01.18 14:39:10

Lead source

www.abcbroker.com

Lead campaign

preliminary-desktop

Introducer

Kate Wilson

Export...CancelUpdate

The following information is available:

- **Type** individual or corporate client. An additional tab "Company" is available for corporate clients, in which company details are specified.
- **Status** sets the client status:
 - ◆ Not registered an anonymous client, which was created based on a demo account without any data.
 - ◆ Registered the client has created a demo account with filled contact details.
 - ◆ Not interested the client has created a demo account with filled contact data but is not interested in opening a real account.
 - ◆ Not completed the client has provided data for opening a real account.
 - ◆ Completed the client has provided data for opening a real account and has submitted all the required documents.
 - ◆ Information to open a real account, the client needs to provide additional information.
 - ◆ Rejected the client is denied registration.
 - ◆ Approved a real account has been opened for the client.
 - ◆ Funded the client has deposited money to a real account.
 - ◆ Active the client has trading activity.
 - ◆ Inactive the client does not have trading activity.
 - ◆ Suspended work with the client has been suspended.
 - ◆ Closed the client has left at the client's own decision.
 - ◆ Terminated work with the client was terminated at the initiative of the company.
- **KYC status** the result of the client verification via a KYC service.
- **Assigned manager** the name of the responsible employee. To find all the clients managed by a certain employee, enable the "Assigned manager" column in the client list then sort the list by this column. The list of managers available for selection is formed in accordance with the group settings of the manager who is viewing the client. If a company is specified the the current manager's group, only the managers from groups with the same company specified will be available to this manager. A manager without any company specified in the group, can access all managers on the server.
- **Preferred trading group** the field is used to distribute clients between manager accounts. If this field is empty, the client record will be available to managers regardless of their account group permissions. If the field is filled, the client will only be available to the managers having the specified group permissions.
- **Approved by** different employees can be responsible for creation and final approval of clients. For example, a manager can register a client, fill in necessary data and set the "Registered" status. Then a compliance specialist may verify the data, change the status to "Approved", set the approval date and specify his account in the "Approved by" field.
- **Approval data** data and document verification and approval date. The date is set by the data approving specialist.
- **Close date** the date when the provision of services to the client was terminated.
- **Last contact date** by filling out this field, managers can easily identify which clients should be reminded of the latest promotions and whom to avoid bothering with too frequent emails/calls. Simply enable the display of this

MetaTrader 5 trading platform

column in the list and then sort clients by this field.

- **Lead Source, Lead Campaign** the lead source website or the name of the marketing campaign (lead campaign) the client responded to.

These fields are used for marketing campaigns and allow you to track where a client came from. To receive the data, add the following tags to the client or mobile platform download link:

```
https://download.mql5.com/cdn/web/metaquotes.ltd/mt5/mt5setup.exe?utm_source=YourWe
https://download.mql5.com/cdn/mobile/mt5/ios?server=ABC-Demo,ABC-Real&utm_source=Y
https://download.mql5.com/cdn/mobile/mt5/android?server=ABC-Demo,ABC-Real&utm_sour
```

Here YourCampaign is the company name, and YourWebsite is the address of the website hosting the link. In the 'server' parameter of the mobile platform links, enter the list of your servers to be shown to traders when they open an account.

When opening a demo account and connecting to any trading account via the terminal downloaded using such a link, utm_source and utm_campaign values are written to a client record at the server side. If the fields are already filled, the tag values are not overwritten when re-connecting to the account (even if the terminal used for connection was downloaded by a link containing other labels).

- **Introducer** the login (trading account) of the user, who introduced the client.
- **Visitor ID** a unique identifier assigned to a user when he/she installs your terminal or visits your site, if a Finteza tracker is installed in it. With this tracker, you can trace trader behavior, from the first website visit to a real account deposit. For further details please visit the [Finteza Analytics](#) section.

Lead Source and Lead Campaign data from terminal download links can be written to created accounts only if the broker has a [Finteza license](#).

If you wish to work with client data using third-party software, you can save the relevant data to a file. Click "Export" and select the data which should be exported to a file: documents, history, etc. After that click "Save":

The screenshot shows a 'Network' dialog box. At the top, there's a 'File name' field with 'Client-1050.html' and a 'Save as type' dropdown set to 'HTML Files (*.html)'. To the right are 'Save' and 'Cancel' buttons. Below this is a 'Report parts' section with a grid of checkboxes: 'Client' (checked), 'Trading Accounts' (checked), 'Documents' (checked), 'Files' (checked), 'Comments' (unchecked), and 'History' (unchecked).

Client's Personal Data

Personal details are written in this section: name, date of birth and contact details.

Client: 1001 - Smith John Murray

Client

Personal

Address

Regulation

Documents

Comments

History

Preliminary Trading Accounts

1013 Smith John

1017 Smith John

Real Trading Accounts

1029 Smith John

Demo Trading Accounts

1001 John Smith

1002 John Smith

1034 Smith John

Personal

Title

Mr.

First name

John

Second name

Smith

Middle name

Murray

Gender

Male

Birthdate

☒ 1998.02.24

Language

English

Preferred method

Not specified

Email

john@smith.com

Mobile

+1 (Canada, United States)

2251325673

Messengers (skype:username, icq:useride, etc.)

skype:john-smith

Social Networks (fb:username, twitter:username, etc.)

fb:johnsmith

External ID

1249993399

KYC Check

Cancel

Update

The following information is available:

- **Title** choose Mr. or Mrs.
- **First name** the client's first name.
- **Second name** the client's second name.
- **Middle name** the client's middle name.
- **Gender** the client's gender.
- **Birthdate** date of birth.
- **Language** the language spoken by the client. If the client record is created during the registration of a preliminary account through the client terminal, the language is set automatically based on the value specified in the registration form.
- **Preferred method** means the preferred communication method: email, phone calls, SMS, messengers.
- **Email** client's email address.
- **Mobile** client's mobile phone number.
- **Messengers** the list of the client's instant messenger accounts. You may use any form, but it is recommended to use the unified method: [messenger name]:[account].
- **Social Networks** the list of the client's accounts in social networks. You may use any form, but it is recommended to use the unified method: [network name]:[account].
- **External ID** client ID in an external trading system. This field can be used for integration and creating reports using API.

KYC Check

Brokers can check clients' personal data and documents in the automated mode using the trading platform integration with KYC providers.

The feature requires an appropriate integration configuration.

The trader requests a live account via the desktop or mobile terminal by filling out a form and uploading documents:

MetaTrader 5 trading platform

Open an Account

?

×

Opening a real account
A real account is required for live trading on financial markets

State: New York

City: New York

Zip code: 123456

Address: Wall st, 1

Please take photos of your documents and upload them here without any editing.

Identity: ID Card

image or PDF file for the front side

...

image or PDF file for the back side

...

Address: Utility bill

image or PDF file

...

- Some types of documents require two photos: front and back side

- Utility bill must contain your name and address and be no older than three months

- Bills for mobile services are not accepted as a proof of address

☒ I agree with the terms and conditions for opening an account and the data protection policy

< Back

Next >

Cancel

MetaTrader 5 trading platform

A preliminary account with a zero balance is created for the client. This account along with the relevant data and documents is linked to the client record. The manager clicks the "KYC Check" button in the client personal data section and the platform automatically sends a request to the KYC system.

The platform can be configured to enable automated sending of client data to a KYC provider after the client opens a preliminary account via the client terminal. This allows the full automation of the onboarding process.

The screenshot shows the 'client personal data' form in the MetaTrader 5 platform. On the left is a list of client accounts, and on the right is a form with various fields for client information. A red arrow points from the 'KYC Check' button to the list of accounts.

Account Type	ID	Name
Real Trading Accounts	1017	Smith John
Demo Trading Accounts	1029	Smith John
	1001	John Smith
	1002	John Smith
	1034	Smith John

Form Fields:

- Email: john@smith.com
- Mobile: +1 (Canada, United States) 2251325673
- Messengers (skype:username, icq:useride, etc.): skype:john-smith
- Social Networks (fb:username, twitter:username, etc.): fb:johnsmith
- External ID: 1249993399

Buttons: KYC Check, Cancel, Update

The KYC system checks data and documents and returns the result, which the manager can view in the platform as a report:

Client: 7255 - Parker Gabriel

Client

Personal

Address

Regulation

Documents

Comments

History

Demo Trading Accounts

817394 Parker Gabriel

821164 Parker Gabriel

823635 Parker Gabriel

825304 Parker Gabriel

831191 Parker Gabriel

833050 Parker Gabriel

833384 Parker Gabriel

840011 Parker Gabriel

840020 Parker Gabriel

#3 2019.12.04 16:10

KYC Sum & Substance Report

Name	Parker Gabriel
Create time	2019-12-04 14:09:05
Review start time	2019-12-04 14:09:48
Review end time	2019-12-04 14:09:58
Review result	Accepted

Documents review

Passport front side	Accepted
Passport back side	Accepted
Utility bill	Accepted

Client details update

Birthday	1986.11.26
Document type	Passport
Document number	123456789
Document issue date	2019.12.01
Document valid till	2025.01.01

Applicant - 5de7bb090a975a750f27ac22

Personal

First name	Parker
Last name	Garbriel
Birthday	1986.11.26
Birth place	NY
Birth country	United States
Gender	M
Phone	+1234567890

New Comment...

Cancel

Update

1144

MetaTrader 5 trading platform

Based on the check result, the 'confirmed' or 'rejected' status is automatically assigned to the client and to the documents uploaded to the relevant client record. Furthermore, data from the KYC system can supplement client records on the platform side. These include the details which the system can read from the provided documents: name, date of birth, document type, number and expiration date, among other data. Updated data is indicated in a separate report block.

Client: 7255 - Parker Gabriel

ID	Type	Name	Creation Date	Status
633	Proof of identity	Passport	2019.12.05 12:54	Approved
634	Proof of address		2019.12.05 12:55	Rejected

Document: 633 - Proof of identity - Passport

Proof of identity - Passport

Created by: 1863, John Smith on 2019.12.05 12:54
Last changed by: 1863, John Smith on 2019.12.05 12:54
Approved by: 1863, John Smith on 2019.12.05 12:54

Status:

Document type:

Document subtype:

Issue date:

Expiration date:

Name:

Comment:

MetaTrader 5 trading platform

Once the check is complete, the manager can confirm registration and move the preliminary account to a real group. After that, the client can make a deposit and start trading.

Client's address

Fill in here the client's address of residence and information about the appropriate ID document.

Client: 1001 - Smith John Murray

Client

Personal

Address

Regulation

Documents

Comments

History

Preliminary Trading Accounts

1013 Smith John

1017 Smith John

Real Trading Accounts

1029 Smith John

Demo Trading Accounts

1001 John Smith

Address

Document type

Passport

Document number

14 2669369

Issue date

☒ 2016.10.16

Expiration date

☒ 2026.10.16

Comment

Country

United States

State

New York

City

New York

ZIP code

12446

Address

24 Wall st, 15

Cancel

Update

The following information is available:

- **Document type** the name of the document: passport, driving license, etc.
- **Document number** the number of the above document.
- **Issue date** the date when the document was issued.
- **Expiration date** document expiration date.
- **Comment** an arbitrary comment in addition to the document details.
- **Country** country of residence.
- **State** state (region) of residence.
- **City** city of residence.
- **ZIP code** zip or postal code
- **Address** full address including street name, house or apartment number, etc.

Corporate clients

This section is only available for corporate clients. Company registration data are specified here.

Client: 1008 - ABC Company - Caine Richard

Client

Personal

Company

Address

Documents

Comments

History

Preliminary Trading Accounts

1013 Smith John

1017 Smith John

Real Trading Accounts

1029 Smith John

Demo Trading Accounts

1001 John Smith

Company

Country of registration

Netherlands

Company name

ABC Company

Registration number

1261222992

Registration date

☒ 2016.10.16

Registration authority

Chamber of Commerce

VAT registration number

12226666

LEI number for EMIR reports

69989916

License number

N11229222

License authority

Dutch Central Bank

Legal address

10 Jan Evertsenstraat st, 15, Amsterdam, Netherlands

Website

www.abccompany.com

Cancel

Update

The following information is available:

- **Country of registration** the country the company is registered in.
- **Company name** the name of the company.
- **Registration number** the number assigned to the company by the registration authority.
- **Registration date** date of registration of the company.
- **Registration authority** the name of the body that registered the company.
- **VAT registration number** used for legal entities registered in the European Union.
- **LEI number for EMIR reports** EMIR (European Market Infrastructure Regulation) is a body of European legislation for the regulation of over-the-counter derivatives. EMIR requires from brokers to provide a report on transactions performed by legal entities. The transaction body in such a report must be identified by LEI (Legal Entity Identifier). It consists of a 20-character alphanumeric code.
- **License number** license number of the company.
- **License authority** the name of the authority which issued the license.
- **Legal address** full legal address of the company.
- **Website** company website address.

Regulation

This section contains additional client data that may be required under the KYC (Know Your Customer) regulation.

Client: 1001 - Smith John Murray

Client

Personal

Address

Regulation

Documents

Comments

History

Preliminary Trading Accounts

1013 Smith John

1017 Smith John

Real Trading Accounts

1029 Smith John

Demo Trading Accounts

1001 John Smith

Regulation

Nationality

United States

Tax ID

123465

Employment status

Employed

Employment industry

Agriculture, Food and Natural Resource

Education level

Master degree or equivalent

Source of wealth

Employment or Business proceeds

Net worth, USD

100 000

Annual income, USD

100 000

Annual deposit, USD

10 000

Trading experience

Forex

> 3 years

Stocks

< 1 year

Futures

< 1 year

CFD

> 3 years

Cancel

Update

The following information is available:

- **Nationality** the client's nationality.
- **Tax ID** identification number in the tax service, such as TIN.
- **Employment status** employed, unemployed, self-employed, etc.
- **Employment industry** agriculture, architecture and construction, health care, etc.
- **Education level** secondary, higher, no, degrees, etc.
- **Source of wealth** the source of funds which the client deposited to the account balance: employment, business, savings, income from investments, etc.
- **Net worth** the real value of the client's assets (money and property) less liabilities.
- **Annual income** the amount of annual income received by the client.
- **Annual deposit** the amount which the client plans to deposit to the account during the year.
- **Trading experience** real trading experience relating to different instruments: Forex, stocks, futures, CFD.

Documents

This section allows management of client's documents. Here you can add, edit or delete documents. Documents provided by the client during preliminary account opening are automatically added to this section.

The flexible system of permissions enables multi-level processing of documents. For example, a customer department employee creates a new record and adds documents to it. Further, a compliance specialist may download and check documents, and then set the appropriate status, such as 'approved' (for example, when the client confirms the authenticity of documents by visiting the office), 'rejected' (for example, if the document expired), etc. All document status changes are displayed in the version history.

MetaTrader 5 trading platform

Client: 1001 - Smith John Murray

Client

Personal

Address

Regulation

Documents

Comments

History

Preliminary Tr

1013 Smith

1017 Smith

Real Trading

1029 Smith

Demo Trading

1001 John

ID	Type	Name	Creation Date	Status
4	Proof of address	Smith John.Address.jpg	2018.08.06 13:36	New
5	Proof of identity	Smith John.Person.jpg	2018.08.06 13:36	Approved
11	Proof of identity	Smith John.Person.jpg	2018.08.27 09:31	New
12	Proof of address	Smith John.Address.jpg	2018.08.27 09:31	New

Document: 5 - Proof of identity - Smith John.Person.jpg

Document

Files

History

Comments

Proof of identity - Smith John.Person.jpg

Created by: 1019 on 2018.08.06 13:36

Last changed by: 1031, George Green on 2019.10.16 14:58

Approved by: 1031, George Green on 2018.08.24 16:44

Status

Approved

Document type

Proof of identity

Document subtype

Passport

Issue date

☒ 2018.08.03

Expiration date

☒ 2028.08.03

Name

Smith John.Person.jpg

Comment

Proof of identity from 1019 - 'Smith John Murray'

Cancel

Update

The list shows general information about documents: document ID, type, etc. To view more information about the document, double-click on its line in the list. To view the document, click [↓](#).

Adding and editing documents

To add a document, click "New" at the bottom of the section, to edit a document double click on it in the list. General information is shown in the Documents tab:

- **Created by** the name of the manager who has created the document and the date of creation.
- **Last changed by** the name of the manager who has made the most recent changes to the document and the date of changes.
- **Approved by** the name of the manager who has approved the document and the date of approval.
- **Status** the current document status: new, approved, rejected, in archive, deleted. When the status is changed to "Approved", the name of the manager who approved the document and the date of approval are written to the "Approved by" field.
- **Document type** ID, proof of address, legal address, company registration, etc.
- **Document subtype** a more specific document type: passport, driver's license, utility bill, bank statement, etc.
- **Issue date** the date when the document was issued.
- **Expiration date** document expiration date.
- **Name** the name of the document file. Documents provided by the client during preliminary account registration via terminals are automatically named according to the following rule: [Second Name] [First Name].[Document Type].[Extension]. The document type for proof of identity documents is 'Person', for proof of address it is 'Address'.
- **Comment** an arbitrary comment. For example, here you can specify the reason for rejecting the document.

You can view the document in the Files tab and replace it if necessary. The tab shows the date of document addition, the name of the document author, the file name and size. To view the document file, click [↓](#). If you have appropriate permissions, you can upload new document files by clicking "Attach documents".

MetaTrader 5 trading platform

Document: 5 - Proof of identity - Smith John.Person.jpg ? X

Document

Files

History

Comments

#	Date	Author	Name	Size
1	2018.08.06 13:36	1019	Smith John.Person.jpg	34.80 KB
2	2019.10.16 14:58	1031, George Gre...	john-smith-person.jpg	16.12 KB

Document: 5 - Proof of identity - Smith John.Person.jpg ? X

Proof of identity - Smith John.Person.jpg

Created by: 1019 on 2018.08.06 13:36

Last changed by: 1031, George Green on 2019.10.16 14:58

Approved by: 1031, George Green on 2018.08.24 16:44

Status

Approved

Document type

Proof of identity

Issue date

☒ 2018.08.03

Expiration date

☒ 2028.08.03

Name

Smith John.Person.jpg

Comment

Proof of identity from 1019 - 'Smith John Murray'

Cancel

Update

Document versions

Any changes made to client documents are displayed on the Versions tab:

The screenshot shows the 'Document Versions' window in the MetaTrader 5 trading platform. The window title is 'Document: 5 - Proof of identity - Smith John.Person.jpg'. On the left, there is a sidebar with four tabs: 'Document', 'Files', 'History', and 'Comments'. The 'History' tab is currently selected. The main area displays a list of document versions, each with a version number, a timestamp, and the user who made the change. The versions are listed in descending order of their creation date. The most recent version (5) was created on 2019.10.16 at 14:58 by user 1031, George Green. It shows the issue date as 2012.06.13 and the expiration date as 2022.06.13. The next version (4) was created on the same date and time by the same user, showing that files were added (john-smith-person.jpg, 16.12 KB) and removed (john-smith-address.jpg, 631 bytes). Version 3 was created on 2019.10.16 at 14:57 by the same user. Version 2 was created on 2018.08.24 at 16:44 by the same user, showing an approval date of 2018.08.24 at 16:44, approved by 1031, George Green, with an issue date of 2012.06.13 and an expiration date of 2022.06.13. The status changed from 'New' to 'Approved'. Version 1 was created on 2018.08.06 at 13:36 by user 1019. At the bottom right of the window, there are two buttons: 'Cancel' and 'Update'.

Version	Timestamp	User
5	2019.10.16 14:58	1031, George Green
Issue date: 2012.06.13 → 2018.08.02 Expiration date: 2022.06.13 → 2028.08.02		
4	2019.10.16 14:58	1031, George Green
Files added: john-smith-person.jpg (16.12 KB) Files removed: john-smith-address.jpg (631 bytes)		
3	2019.10.16 14:57	1031, George Green
2	2018.08.24 16:44	1031, George Green
Approval date: 2018.08.24 16:44 Approved by: 1031, George Green Issue date: 2012.06.13 Expiration date: 2022.06.13 Status: New → Approved		
1	2018.08.06 13:36	1019

MetaTrader 5 trading platform


Information on each change contains the number, date and the manager login. To view more information about changes, click on the line. The details show each changed parameter: its name, previous value and new value.

The list of changes can be filtered by the employee who made the changes. Use the Manager field to filter the list.

Document comments

You can add here comments on client documents. If a document is not in order, you can add instructions to managers to contact the client.


All messages from this section are also displayed in the general list of [client comments](#).



Comments

This section stores the client history and working correspondence with other managers. For example, sales managers can keep a call history, and the supervisory department can leave instructions to managers to contact a client if documents are not in order.

Several types of comments are supported for convenience and efficiency: general comments, log records, calls and automatic records. Choose the appropriate type for your messages, and you will be able to easily identify them in general correspondence.



MetaTrader 5 trading platform

All comments on client documents are also displayed in this section.

History

For efficient employee performance monitoring and secure storage of information, all changes in client records are tracked and displayed in the History section. Version support allows you to see all changes made to the client record. You can revert changes if necessary, since all earlier specified data are stored in the platform.

Client: 1001 - Smith John Murray

Client

Personal

Address

Regulation

Documents

Comments

History

Preliminary Trading Accounts

1013 Smith John

1017 Smith John

Real Trading Accounts

1029 Smith John

Demo Trading Accounts

1001 John Smith

16	2019.10.17 14:35	1031, George Green	▼
15	2019.10.16 11:20	1031, George Green	▲
Document Number: 14 2669369			
Document Date: 2016.10.16			
14	2019.10.15 18:10	1031, George Green	▼
13	2019.10.15 18:09	1031, George Green	▲
External ID: 1249993399			
12	2019.08.08 15:12	1058	▲
Preferred Trading Group: demo\forex-eur			
11	2018.08.24 16:25	1000, First Admin	▲
Status: Incompleted → Approved			
Compliance Approved by: 1031, George Green → 1000, First Admin			
Compliance Approval Date: 2018.08.24 → 2018.08.24			
10	2018.08.24 16:25	1000, First Admin	▼
9	2018.08.24 16:22	1000, First Admin	▼
8	2018.08.24 16:21	1000, First Admin	▼
7	2018.08.08 12:16	1023	▼
6	2018.08.07 16:35	1000, First Admin	▼
5	2018.08.07 16:35	1000, First Admin	▼
4	2018.08.06 13:34	1017	▼
3	2018.08.03 14:48	1013	▼
2	2018.07.27 14:59	1000, First Admin	▼
1	2018.07.27 13:25	1001	▼

Cancel

Update

MetaTrader 5 trading platform

Information on each change contains the number, date and the manager login. To view more information about changes, click on the line. The details show each changed parameter: its name, previous value and new value.

The list of changes can be filtered by the employee who made the changes. Use the Manager field to filter the list.

Trading accounts

This section contains information about the client's trading accounts, including demo, preliminary and real ones.

All accounts in the trading platform are automatically connected to clients. If an existing client opens a demo or preliminary account via the terminal, this account will be immediately added to the appropriate client record. If this is a new client, a new client record will be created, to which the newly opened account will be connected.

Also, this section allows you to open accounts for the client. To do this, click "New Account" in the context menu. The account created will be automatically connected to the client record. To edit an existing account, double-click on it in the list. After that, all account parameters will be shown in the right window part.

Using this menu, you can bind or unbind any other accounts:

- Click "Link \ By Login" in the context menu. After that a new row will be added at the end of the table. Specify here the number of the account to bind.
- Select an account and click "Unlink" in the context menu. After confirmation, the selected account will no longer be bind to the client and will be removed from the list.

MetaTrader 5 trading platform

Client: 1001 - Smith John Murray

Client

Personal

Address

Regulation

Documents

Comments

History

Demo Trading Accounts

1001 John Smith

Login	Name	Group	Balance
1001	John Smith	demo\demo forex	3 000.00
1002	John Smith		
1003	John Smith		
1004	John Smith	demo	
1005	John Smith	demo	
1007	John Smith	demo	
1008	John Smith	demo	
1009	John Smith	demo	
1010	John Smith	demo	
1011	John Smith	demo	
1014	John Smith	demo	
1015	John Smith	demo	
1016	John Smith	demo	
1020	John Smith	demo	
1021	John Smith	demo	

New

Edit

Delete

Link

Unlink

Select All

Copy As

Export

Auto Arrange

Grid

Columns

Client: 1001 - Smith John Murray

Client

Personal

Address

Regulation

Documents

Comments

History

Demo Trading Accounts

Overview

Personal

Account

Profile

Security

John Smith, 1010, demo\forex-hedge-usd, 1 : 100

United States, New York, New York, 24 Wall st.

+12251325673 MetaQuotes ID: E243E874

john@smith.com

Registered: 2018.07.27 Last access: 2018.07.27 14:03 Last address: 192.168.1.79

Symbol	Type	Volume	Price	S / L	T / P	Price	Profit
eurusd	sell	1.00	1.15808	0.00000	0.00000	1.10444	5364.00
eurusd	sell	1.00	1.16189	1.17189	1.06189	1.10444	5745.00
eurusd	sell	1.00	1.16067	1.17067	1.06067	1.10444	5623.00
+ Balance: 996 735.00 USD							16 732.00

MetaTrader 5 trading platform

You may also use the context menu to export accounts to a file or to change the list view: show/hide columns and grid or enable/disable auto-size of columns.


MetaTrader 5 trading platform

MetaTrader 5 Trading Platform / Platform Setup / Clients / Import of Clients from MetaTrader 5

Importing clients from the MetaTrader 5 server

You can easily import your client database from one MetaTrader 5 sever to another. You will need administrator accounts having access to clients on these two servers.

Open the clients section and click "Import from server":



Specify connection parameters:

- **Server** the IP address and port of the MetaTrader 5 server separated by a colon.
- **Login** the number of the manager account for authentication on the server.
- **Password** the account password for authentication on the server.
- **Use certificate from file** advanced authentication can be enabled for the manager account on the source server, from which accounts are imported. A certificate is required in this case. If the certificate has previously been installed in the storage of the operating system, it will be automatically recognized by the import system. If the certificate has not been installed, enable this option and specify the path to the file manually.
- **Certificate File** click "Browse" and specify the pfx-file of the certificate. The certificate file received in the terminal is saved in */terminal data folder/profiles/server name/certificates/*.
- **Certificate Password** the password of the certificate.

To import accounts, you will need an administrator account with client access permissions on the source server.

Requesting accounts

Next, specify a string to request clients from an external server. Records are filtered by the "Preferred group" field. The default request is `"!demo*,!manager*,!coverage*,!contest*,*"`. It allows selecting all clients except those from demo and manager accounts, as well as coverage and contest groups.

After the request, the list will display the clients to be imported. Double click on a client to view how it will look like after import. This will open a standard account viewing window.

MetaTrader 5 trading platform

Import

?

✕

Choosing clients
Select clients to be added to your database.

*

Request

ID	Name	Type	Status
☒ ✓ 1000	First Admin	Individual	Approved
☒ ✓ 1001	John Murray Smith	Individual	Approved
☒ ? 1002	Joe Perry	Individual	Unregistered
☒ ? 1003	Sean Martin		
☒ ? 1004	Robert Green		
☒ ? 1005	Steven Black		
☒ ? 1006	Benjamin King		
☒ ? 1007	Katy Perry		
☒ ? 1008	Richard Caine		
☒ ? 1009	John Smith		

☒ Select / deselect all
☒ Import documents and comments

Client: 1003 - Sean Martin

Client

Personal

Address

Regulation

Personal

Title

Mr.

First name

Sean

Second name

Martin

Middle name

Gender

Male

Birthdate

☒ 1998.02.24

MetaTrader 5 trading platform

You can disable import of individual clients from the list. To do this, click on the icon at the beginning of the account row, and then it will change to . You can also select or deselect all clients by using the corresponding option below the list.

If you wish to additionally import client documents and comments, select the appropriate options.

If the IDs of imported clients match the IDs of existing clients, new IDs will be assigned.

Result of Import

The total number and the number of imported clients will be shown on the last step:

Import?×

Importing clients
Results of importing clients to your database.

ID	New ID	Name	Type	Status	Result ▲
● ✓ 1000	1000	First Admin	Individual	Approved	Done
● ✓ 1001	151460	John Murray Smith	Individual	Approved	Done
● ? 1002	151461	Joe Perry	Individual	Unregistered	Done
● 📄 1003	151462	Sean Martin	Individual	Incompleted	Done
● ? 1004	151463	Robert Green	Individual	Unregistered	Done
● ? 1005	151464	Steven Black	Individual	Unregistered	Done
● ? 1006	151465	Benjamin King	Individual	Unregistered	Done
● ? 1007	151466	Katy Perry	Individual	Unregistered	Done
● 📄 1008	151467	Richard Caine	Corporate	Registered	Done
● 📄 1009	59705	John Smith	Individual	Incompleted	Done

Clients: 10 / 10

< BackFinishCancel


MetaTrader 5 trading platform

Import details are also available in the [trade server journal](#).

MetaTrader 5 Trading Platform / Platform Setup / Accounts

Accounts

This section enables management of accounts on the server: creation, setup and control of account trading states. Complete information is available for each client: personal data, all open positions and orders, financial status and security parameters.



MetaQuotes - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Import Export Apply + Settings X Back Forward Sort

Integrations Automations Security Time Holidays Groups (519) Clients & Accounts Allocations Clients Managers **Trading Accounts** Orders & Deals Gateways Data Feeds Plugins Reports ECM

Login	Name	Group	Country	Balance / Checked
916080	Phillips Christopher	demo\demo forex	Finland	4 999 751.58
916081	Harrison Alexander	demo\demo forex	Turkey	4 999 974.94
916082	Richardson Samuel	demo\demo forex	Germany	4 999 787.82
916083	Bennett Andrew	demo\demo forex	Saudi Arabia	4 999 716.49
916084	Murray Michael	demo\demo forex	India	4 999 693.74
916085	Young Brandon	demo\demo forex	Israel	4 999 823.19
916086	Lewis Richard	demo\demo forex	Germany	4 999 710.34
916087	Smith Logan	demo\demo forex	Pakistan	4 999 717.28
916088	Doyle Diego	demo\demo forex	Japan	4 999 699.86
916089	Taylor Kevin	demo\demo forex	India	4 999 924.92
916090	Brown John	demo\demo forex	Indonesia	5 001 189.14
916091	Evans Benjamin	demo\demo forex	Taiwan	4 999 724.22
916092	Cook Dominic	demo\demo forex	Russia	4 999 718.13
916093	Ross Samuel	demo\demo forex	Belarus	4 999 839.03

Q * Current database Request

For Help, press F1 14.8 / 0.2 M

Depending on items selected in the context menu, different account details, time and address of last access to the server, etc. are shown here. Accounts can be sorted out by any of the fields. Click on a column name to sort.


- All accounts are stored separately for each trade server, depending on the server the group, to which the account belongs, is bound to. A manager can see and manage only accounts that belong to the same server, to which the manager's account belongs.
- Account type is determined by the group to which the account belongs.

Requesting Accounts

To request accounts use a line located in the bottom part of the window. In the field to the right of  specify accounts using one of the following methods:

- Specify the precise number of an account or of several accounts comma separated;
- Specify mask "*" to request all accounts;
- Select a group from the dropdown list to request accounts included into a certain group.

In the next field select a data base, from which accounts will be requested: current or archive. You can also specify one of backup databases created on the server by selecting "More backups". The following window will appear at that:



Specify the period for requesting backup copies:

- **Period** in this field you can choose one of the predefined request periods;
- **From** starting date of the selection. A date can be specified manually or using the calendar that is opened by pressing the  button;
- **To** end date of the selection.

Once a period is specified, additional items appear in the field of choosing a database all the backup copies that were made within the specified period of time.

To display the accounts press the "Request" button.

Working with Accounts

To add or modify an account, press the "+ New" and "⚙ Edit" buttons respectively. They can be found in the "Edit" menu, in the standard part of toolbar or in the context menu. You can also open an account for editing by a double click on it with the left mouse button. To delete an account, one should press the "✗ Delete" button.

The accounts can be modified and deleted in groups. To do it, select them in the list with the mouse while holding the "Ctrl" or "Shift" keys.

When an account is deleted its trade history (orders and deals) is not deleted. Do not use logins of deleted account when creating new ones.

Account types

The account type is determined by the type of the group, in which the account is located. For convenience, different icons are used for different types of accounts:

-  demo
-  preliminary
-  live
-  manager
-  technical (the "Show to regular managers" permission disabled)
-  disabled (the "Enable this account" permission disabled)

Context Menu

The context menu of the list of accounts allows executing the following commands:

-  **New** create a new account.
-  **Edit** edit a selected account.
-  **Edit group** edit the group a selected account is located in.
-  **Edit manager** edit the manager account, created on the basis of the selected account.
-  **Delete** delete a selected account. The deletion of an account does not affect orders, trades, or positions associated with this account. Such operations are not deleted immediately, later during optimization, or after any period of time. If necessary, you should delete them manually.
-  **Request** execute the request of accounts.
-  **Move to Archive** move the selected account to the archive database. When an archive or reserve database is selected, this command is changed to " Restore". Using it, you can return the account to the current database.
- **Balance** open the submenu of commands for working with balance and credit assets of an account:
 - ♦ **Check Balance** when this command is executed, the calculation of total profit/loss by all the deals of a selected account is performed. Obtained value is compared with the current balance of the account. In case the values are not equal, the following entry appears in the journal: "account xxx has invalid balance: xxx.xx, valid: xxx.xx".
 - ♦ **Fix Balance** when this command is executed, the calculation of total profit/loss by all the deals of a selected account is performed. Obtained value is written as the current balance of the account. The operations of balance correction are necessary for restoring accounts and for manual

correction of trade history.

- **Copy As** copy accounts selected in the list:
 - ♦  **Lines** copy entire selected information.
 - ♦ **List of Logins** copy the list of logins only.
-  **Export** export the selected accounts as a *.HTM, *.HTML or *.CSV file.
-  **Import from File** import accounts from a CSV file.
-  **Import from Server** import accounts from a MetaTrader 4 or MetaTrader 5 server.
-  **E-Mail** send a message to the account owner via the internal mail system or by email.
-  **Journal** request all journal entries on the selected account.
-  **Find** open the search window.
- **Enabled only** show only enabled accounts in the list. Enable this option to leave only active accounts in the list.
- **Auto Arrange** if this option is enabled the size of columns is selected automatically.
- **Grid** this option shows/hides field separators in the table of accounts.
- **Columns** using this sub-menu, one can choose which details of accounts will be displayed in the list.

MetaTrader 5 Trading Platform / Platform Setup / Accounts / Creating Account

Creating Accounts

To create an account, execute the "+ New" command in the "Edit" menu, standard part of the toolbar or in the context menu of the corresponding section.

The 'New Account' dialog box is shown with the following fields and values:

- Preferred Login:** next
- Group:** demo\demo forex-hedged
- Existing Client:** Type in the client id, name or contacts to search
- First name:** John
- Last name:** Smith
- Middle name:** Jeremy
- Company:** Individual
- Email:** john@smith.net
- Phone:** +12412299314
- Country:** United States
- Zip code:** 123456
- State:** New York
- City:** New York
- Address:** 20 Wall st 15
- Passwords:**
 - Master:** km0hhhk
 - Investor:** nud8vpnb
 - Phone:** (empty)

Buttons: OK, Cancel

For convenience, the account settings in the window of account creation are divided into two boxes.

Details

In this box the client's details are specified:

- **Preferred Login** account number. If you specify "Next" in this field the the closest free number will be assigned to the account. Do not use logins of deleted account when creating new ones.
- **Group** selection of a group the account will be created in.
- **Preferred Client** the client to whom the account should be linked. Specify the ID, name or contact information in the Existing Client field and then click "Request". Then select the required client from the list.
- **Name** first name of the account owner.
- **Last Name** second name of the account owner.
- **Middle Name** middle name of the account owner.
- **Company** name of the client's company.
- **E-Mail** e-mail address.
- **Phone** phone number.
- **Country** country of residence.
- **State** state (region) of residence.
- **City** city of residence.
- **Zip code** postal code.
- **Address** exact address.

Additional account settings can be specified when editing it.

Passwords

In this box the account passwords are specified. At the creation of account the passwords are generated automatically, however they can be manually specified in the corresponding fields:

- **Master** master password of the account.
- **Investor** investor password (without ability to trade).
- **Phone** phone password that is intended for the identification of the account owner when performing trade operations by phone.

All passwords, including master and investor, must contain four character types: lowercase letters, uppercase letters, numbers and symbols (#, @, !, etc.). For example, 1Ar#pqkj. The minimum password length is determined by group settings, while the lowest possible value is 8 characters. The maximum length is 16 characters.

In order to create the account, press the OK button. To cancel the creation press the Cancel button.

MetaTrader 5 Trading Platform / Platform Setup / Accounts / Editing Account

Editing Accounts

To edit an account, press "⚙ Edit" in the "Edit", standard part of the toolbar or in the context menu of the corresponding section. An account can be opened for editing by a double-click with the left mouse button on it. The window of editing an account contains four tabs:

Overview

Account: 932996, Bailey Miguel, USD, 1:100

Overview

Personal

Account

Profile

Security

Bailey Miguel, 932996, Individual, demo\demoforex, 1 : 100
010101, Germany, Berlin
+49-984536 MetaQuotes ID: 54D09D11
Miguel.Bailey@mail.net
Registered: 2019.09.11 Last access: 2019.09.11 19:56 Last address: 78.140.180.6

Symbol	Ticket	Type	Volume	Price	S / L	T / P	Price	Swap	Profit
audcad	12573608	buy	0.06	0.90577	0.00000	0.00000	0.90651	0.00	3.35
audjpy	12570013	sell	1.04	73.900	80.554	0.000	73.995	0.00	-91.36
eurrub_tom	12577852	sell	5.00	72.143	0.000	0.000	70.698	0.00	112.95
gbprub_tom	12580506	sell	7.00	80.805	0.000	0.000	79.600	0.00	0.00
usdjpy	12577317	sell	0.03	107.746	114.211	101.281	108.139	0.00	-10.90
+ Balance: 4 999 897.21 USD Commission: -3.00								0.00	14.04
cadCHF	12572816	buy stop	0.04 / 0.00	0.82057	0.00000	0.86160	0.75045		placed
eurjpy.fix	12567950	buy limit	0.05 / 0.00	107.981	0.000	116.619	119.213		placed
eurUSD	12574265	buy stop	0.05 / 0.00	1.87133	1.70291	0.00000	1.74198		placed

Client Properties...

Update

Cancel

Help

MetaTrader 5 trading platform

This tab contains general information about an account. Upper part contains personal details and the dates of registration and last login with the account. Lower part displays all the open positions of the account and the current state of the account.

If you have an active Finteza subscription, this section can display data for user tracking: Visitor ID and Affiliate. For further details please visit the Finteza Analytics section.

Last access time and address data is updated once per hour. When an account is created, the creation date and time are also recorded in the "Last access" field.

Open Positions

The following information is displayed for positions:

- **Symbol** the trading instrument for which the position was opened.
- **Ticket** the position ticket (unique number). Usually, a position ticket matches the ticket of the order, as a result of which the position was opened.
- **ID** unique identifier of the position in an external system (if the operation is forwarded via a gateway).
- **Time** position open time.
- **Type** type of the position, buy or sell.
- **Volume** the current position volume in lots or units.
- **Price** weighted-average position open price: $(\text{price of deal 1} * \text{volume of deal 1} + \dots + \text{price of deal N} * \text{volume of deal N}) / (\text{volume of deal 1} + \dots + \text{volume of deal N})$. The accuracy of rounding of the average weighted price is equal to the number of decimal places in the symbol price plus three additional digits.
- **S/L** Stop Loss level of a position.
- **T/P** Take Profit level of a position.
- **Price** the current price of the financial instrument for which the position was opened. The Bid price is displayed for short positions, while the Ask price is used for long ones. The price of the last performed deal (Last) is displayed for the positions involving exchange symbols (both directions).
- **Swap** charged swap.
- **Profit** current profit on this position. The profit does not include swap and commission.
- **Comment** comment to the position. On netting accounts, a comment to a position is inherited from the last deal for the symbol of the position. On hedging accounts a comment is inherited from the order with which the position was opened.

Assets

The trading platform supports a special type of non-tradable assets, which can be used as client's assets to provide the required margin for open positions of other instruments. For example, a certain amount of gold in physical form can be available on a trader's account, which can be used as a margin (collateral) for open positions.

Such instruments have calculation type "Collateral". Features of such symbols:

MetaTrader 5 trading platform

- Clients can't perform any operations with these symbols, except for closing. A position can be opened only by a manager.
- No profit can be accrued for the positions of these symbols, they have no stop loss or take profit.
- The value of such a position, and thus the amount of money that a client can use as collateral, is calculated by the below formula:

Such assets are displayed as open positions. Their value is calculated by the formula:
 $\text{Contract size} * \text{Lots} * \text{Market Price} * \text{Liquidity Rate}$.

Liquidity Rate is the share of the asset that a broker allows to use for the margin, it is set in the symbol properties.

The Assets are added to the client's Equity and increase Free Margin, thus increasing the volumes of allowable trade operations on the account.

Toolbox										
Symbol	Ticket	Time	Type	Volume	Price	S / L	T / P	Price	Pro	
eurusd		2015.05.20 13:31:37	buy	1.00	1.11441	0.00000	0.00000	1.11514	73.00	
⊕ Balance: 4 952.25 USD Equity: 6 234.33 Margin: 1 114.41 Free Margin: 5 119.92 Margin Level: 559.43 %										71.52
gold 1oz		2015.05.14 13:32:23	buy	1.00				1210.56		
⊕ Assets: 1 210.56 USD										
Trade Exposure History News 23 Mailbox 7 Calendar Company Alerts Articles 3 Code Base Experts Jour										

In the example above, a trader has 1 ounce of gold having the current market value of 1 210.56 USD. This value is added to the equity and the free margin.

Symbol settings may allow clients and managers close such positions (Trade = Close only). In this case a trader will be able to convert the asset in the deposit currency at the current market rate and use that money for trading. A position can be closed only if the conversion rate of the assets currency into the deposit currency is available.

Account State

The current state of an account is displayed in a gray row under the list of open positions:

- **Balance** amount of money on a client account (deposit);
- **Credit** amount of credit money given to a client by broker (the sum of "Credit" and "Bonus" type operations). The trading platform does not have a function of charging an interest for credit assets. Credit assets can be given and taken away using the manager terminal.
- **Commission** the amount of commission by orders and positions accumulated during a day or a month. Depending on settings, a preliminary calculation of commission is performed during a day or a month. The corresponding amount of assets is blocked on the account and its value is shown in this field. At the end of the day/month, the final calculation of commission is performed and the corresponding amount of money is charged from the account as a balance

MetaTrader 5 trading platform

operation (a separate deal of the Daily/Monthly commission type). Previously blocked assets are unblocked.

If a commission is charged immediately during execution of a deal, its value is written in the "Commission" field of the deal.

- **Swap** the amount of swaps by all open positions.
- **Profit** the amount of profit/loss by all open positions.

The context menu commands of the lower part of the window allow performing the following actions:

- **Time** show/hide the "Time" column;
-  **Check Positions** check the positions of a client based on executed deals;
-  **Fix Positions** recalculate the positions of a client based on executed deals;
- **Auto Arrange** if this option is enabled the size of columns is selected automatically;
- **Grid** this option shows/hides field separators in the table.

Pending orders

The list of the trader's pending orders is shown below the account status bar:

- **Symbol** the trading instrument for which the pending order has been placed.
- **Ticket** the unique order ticket.
- **ID** the unique order identifier in an external trading system (if the order is forwarded via a gateway).
- **Time** time when the order was placed by the client. If the order is passed to an external trading system, this field displays the time of order placing in the external system (not in the MetaTrader 5 platform).
- **Type** order type: "Buy Limit", "Sell Limit", "Buy Stop", "Sell Stop", "Buy Stop Limit" or "Sell Stop Limit".
- **Volume** volume requested in the pending order and the currently filled volume (in lots or units).
- **Price** the order execution price specified by the trader.
- **S/L** Stop Loss level in an order.
- **T/P** the Take Profit level in the order.
- **Price** the current price of a financial instrument for which the order was placed. The Bid price is displayed for sell orders, while the Ask price is used for buy ones. The price of the last performed deal (Last) is displayed for the orders involving exchange symbols (both directions).
- **Comment** text comment to the order. Can be specified by a trader when placing an order.

Checking and Fixing Positions

The Administration terminal allows you to automatically check and fix the positions of a client on the basis of his or her deals. For example, if a dealer makes a mistake, the administrator can delete the wrong deal using the "Deals" section. The position of the client must be properly recalculated and corrected.

To verify the client's positions, use the command " Check Positions" in the context menu. After that, below the account current positions, positions made on the basis of

the client's deals are shown (if there should be positions for the client's deals now).

 Account: 1842137, John Smith, USD, 1:100, Hedge

Overview

Personal

Account

Limits

Profile

Subscriptions

Security

John Smith, 1842137, Individual, [demo\demo forex-5-hedged](#), 1 : 100

123456, Slovakia, Bratislava

+172293399

[smith@mail.com](#)

Registered: 2022.07.07 Last access: 2022.07.07 14:19

Symbol	Ticket	Type	Volume	Price	S / L	T / P	Price	Swap	Profit
eurUSD	304052894	buy	1	1.01848			9	0.00	-1299.00
gbpUSD	304052895	buy	1	1.19709			2	-390.00	-1437.00
• Checked positions									
gbpUSD	304052895	buy	1	1.19709			2	0.00	-1437.00
gbpUSD	304052896	sell	0.5	1.19700			2	0.00	714.00
Balance: 100 046.87 USD								-390.00	-2 741.00

Edit
 Delete

Check Positions
 Fix Positions

Volumes

Profit

Show Milliseconds

Auto Arrange

Grid

Columns

New Client...

Cancel

Help

If the current open position of the client does not match the one recalculated based on his or her deals, it is highlighted in red. You can compare the type, volume and open price of the current calculated position. If the position highlighted in red appears only in the upper or only in the bottom part of the window, it means that the client should not have this position or it lacks, respectively.

The result of position checking also appears in the terminal journal. Entries are as follows:

positions of account 'xxx' have been checked
account 'xxx' has valid positions
or
account 'xxx' has 'yyy' invalid positions

In order to fix the position of a client, select " Fix Positions" in the context menu.

When using the function, keep in mind the swap nuances:

- When restoring an absent position, the swap value is not filled for it. Swap is stored only market exit deals. When you delete a deal closing a position and restore a position by an entry deal, there is nowhere the system can get the swap value from. If required, set the swap in the restored position manually.
- When editing an existing position, the swap is not reset to zero in it.

- When checking and correcting the positions, only the deals of the client are taken into account, orders are not checked. The orders are used to assign tickets to positions created as a result of fixing. If there is no source order ticket and the netting system is used on the account, a new ticket is assigned to the created position. In case of the hedging system, position is not created (fixing is unsuccessful), and the appropriate message is displayed in the journal.
- If the client's position accounting type ever changed (e.g. the account was transferred between groups with different accounting systems), balance check and fixing will not be available, because trades cannot be matched correctly. The platform does not store data about when position accounting type was changed for an account.
- For hedging accounts, check reveals no error if the volume of the deal closing the position is greater than the original volume of the position. This situation is abnormal and can only be the result of manual actions with the trade database.

Personal

MetaTrader 5 trading platform

Account: 851355, Matthew Richardson, USD, 1:100, Netting

Overview Personal Account Profile Subscriptions Security

Name: Matthew

Last name: Richardson Middle name:

Company: Individual

Registered: 2019.02.08 09:07:27

Language: Czech Status: NR

ID number: 6993119945 Lead campaign: web.terminal

MetaQuotes ID: 1A892211 Lead source: www.mql5.com

Email: matthew.richardson@mail.net

Phone: +35796145893

Country: Czech Republic State:

City: Prague Zip code: 010101

Address: Czech Republic

Comment: web terminal

Client Properties... Update Cancel Help

The following information about an account is specified here:

- **Name** name of account owner.
- **Last Name** second name of the account owner.
- **Middle Name** middle name of the account owner.
- **Company** name of company of account owner.
- **Registered** account registration date. The date is added automatically during account creation. Please be careful when changing the registration date manually: the data should fit the account trading history, and thus there should not be any trading operations before the registration date. Otherwise, such operations can be ignored when generating reports.
- **Language** user's language. If the account is created through the client terminal, the language is set automatically based on the terminal's interface language.
- **Status** status of account owner , RE (resident) or NR (non-resident).
- **ID number** passport number, TIN or other unique identifiers of account owner.
- **Lead Source, Lead Campaign** website, from which a client has come (lead source), and a name of a marketing campaign that attracted the client (lead campaign).
These fields are used to analyze marketing campaigns and track where clients come from. To receive the data, add the following labels to the client or mobile platform download link:

https://download.mql5.com/cdn/web/metaquotes.ltd/mt5/mt5setup.exe?utm_source=YourWebsite
https://download.mql5.com/cdn/mobile/mt5/ios?server=ABC-Demo,ABC-Real&utm_source=YourWebsite
https://download.mql5.com/cdn/mobile/mt5/android?server=ABC-Demo,ABC-Real&utm_source=YourWebsite

where YourCampaign is a campaign name, while YourWebsite is a website the link has been placed at. In the 'server' parameter of the mobile platform links, enter the list of your servers to be shown to traders when they open an account.

When opening a demo account and connecting to any trading account via the terminal downloaded using such a link, utm_source and utm_campaign values are set in a client record at the server side. If the fields are already filled, the label values are not overwritten when re-connecting to the account (even if the terminal used for connection was downloaded by a link containing other labels).

Lead Source and Lead Campaign data from terminal download links can be written to created accounts **only if the broker has a Finteza license**.

- **MetaQuotes ID** during installation of the MetaTrader 5 for iPhone or Android, each user is assigned a unique identifier – MetaQuotes ID. This identifier is used like a phone number. By specifying MetaQuotes ID in the desktop terminal settings, a user can send notifications about various trade events on their mobile devices. MetaQuotes is also supported by MQL5.community: by specifying the identifier in profile, a user can receive important notifications from the website and communicate with other members of the community via private messages. For more information please refer to the article MetaQuotes ID in MetaTrader Mobile Terminal.
MetaQuotes ID is added to the client record on the server side, once the client specifies it in the terminal settings.

MetaTrader 5 trading platform

- **E-Mail** email address. You can specify multiple addresses separated by commas. All of them will be used to send reports. The maximum total length of a string is 63 characters.
- **Phone** phone number.
- **Country** country of residence.
- **State** state (region) of residence.
- **City** city of residence.
- **Zip code** postal code.
- **Address** exact address.
- **Comment** text comment to the account.

Country and City fields for demo accounts opened via client terminals are automatically filled on the basis of GeoIP data or, if it is not available, on the basis of the OS locale.

Account

Account: 870753, Parker Ashton, USD, 1:100, Netting

Overview Personal **Account** Limits Profile Subscriptions Security

Group: demo\demo forex

Color: ☐ None Leverage: 1 : 100

Bank account: Agent account:

☒ Enable this account

☒ Enable password change

☒ Enable one-time password

☐ Change password at next login

Trade accounts:

Gateway ID	Account
6, MetaTrader 5 Gateway	123456

Synchronize

Add

Edit

Delete

New Client...

Update Cancel Help

Trading parameters of an account are set up at this tab:

- **Group** name of the group, the account belongs to.
- **Color** color that will be used in the manager terminal for displaying clients' requests for performing trade operations. When exporting to a file, the color is saved in the AABBGRR format. AA defines the value of the alpha channel: FF for completely transparent (None), 00 for completely opaque (color).
- **Leverage** leverage of the account.
- **Bank account** an account in an external bank.
- **Agent account** an account for charging the agent commissions for trading operations on this account.
- **Enable this account** enable/disable the account. If the check mark is removed from this field, the account becomes inactive and its icon becomes gray . Connection to the server using this account is impossible then. Disabling of an account does not disable the sending of daily or monthly reports to this account. This option should be disabled separately. Disabling of an account does not affect the already placed pending orders, as well Stop Loss and Take Profit levels of the current positions since these operations can be passed to external systems. However, the Stop Out procedure is not performed for disabled accounts since this tool is intended for internal broker risk control.
- **Allow to change password** if this field is checked, then the account owner can change the account passwords on their own in the client terminal.
- **Enable one-time password** using this option, you can disable the OTP use for individual clients in the group. If use of OTP is disabled for a group, enabling this option does not have any effect.
- **Change password at next login** if this option is enabled, then the owner of the account will be forced to change the master password at next connection. Any action is prohibited for the account until its master password is changed. Once the password is changed, this options disables automatically.

- Moving accounts to groups with different deposit currencies can only be performed for accounts with zero balances and no open positions.
- It is impossible to move account between groups that belong to different trade server.

Trade Accounts


This section is intended for managing trade account of a client in external systems (for example, a bank or an exchange). Each number is bound to a certain gateway that is used for working with the corresponding external trade system.

The accounts are managed using the following commands:

- **Add** add a new account. Once this button is pressed, a new row appears. In the "Gateway ID" field, select a gateway; and in the "Account" field, specify an account in the external system, interaction with which is performed using the specified gateway.
- **Edit** change a selected account. The same action can be done by double-clicking with the left mouse button on a necessary field.

- **Delete** delete a selected account.

Using the "Synchronize" button, you can synchronize the trade state of a client with an external trading system if such a possibility is implemented in the gateway used by the client. To perform synchronization select the gateway and account row and click "Synchronize".




In the menu choose a suitable mode of synchronization:

- **Synchronize All** synchronize current pending orders, positions and balance;
- **Synchronize Balance** synchronize balance only;
- **Synchronize Positions** synchronize current open positions only;
- **Synchronize Orders** synchronize current pending orders only.

Synchronization of trading data results in the creation of correcting operations, which are displayed accordingly in the client's trading history.

Limits



In this section, you can configure trading account permissions and restrictions:

- **Show to regular managers** this rule allows the convenient working with technical accounts. Disable this option for testing accounts to hide them from all managers who do not have special access to technical accounts. Such technical accounts can be confusing for the managers working with clients, in which case hiding them can be useful.
The permission affects the visibility in the general list of accounts in the Administrator and Manager terminals, as well as in the list of online accounts in the Manager terminal.
- **Include in server reports** using this option, you can exclude the account from server reports. Like the previous permission, it is intended for more convenient work with technical accounts. The ability to edit the previous two options is determined by the "Manage technical accounts" permission.
- **Enable daily reports** enable receiving of the daily and monthly reports. If this option is disabled, HTML reports will not be generated or sent daily/monthly for the account (however, this does not affect the generation of daily data). Account settings take precedence over group settings.
- **Enable API connections** enable connection through Web API using this account. The parameter is obsolete and is not used.
- **Enable sponsored VPS hosting** brokers can pay for the virtual hosting for their client. The service is extremely important for traders, and the opportunity to receive a VPS for free can give them a good reason to choose your company over competitors. The availability of a broker-sponsored VPS is controlled at the individual account level. Only if this option is enabled, the appropriate payment plan will be shown to the trader in the client terminal. For more details, please read the appropriate section.
- **Enable trading** if this options is disabled, trading on the account is impossible: one cannot place new orders or modify existing orders and positions. However, the account can be used to connect to the server and to analyze price dynamics. Disabling trading does not affect the already placed pending orders, as well Stop Loss and Take Profit levels of the current positions since these operations can be passed to external systems. However, Stop out is not performed for accounts with trading disabled since this tool is meant for broker's internal risk management.
- **Enable algo trading by Expert Advisors** permit this account to trade using Expert Advisors. This option can also be specified in the setting of the group;
- **Enable trailing stops** enable using the trailing stops in the client terminal for this account. This option can be specified in the setting of the group;
- **Allow access to subscription data via data feeds** this option provides additional protection for your market data accessed through subscriptions. By default, such data is only available via client terminals. If you are integrating with another service or server and need to access data through a gateway or data feed, enable this permission to allow access for the relevant account. By default, this permission is disabled for all accounts.
- **Limit total value of positions** the maximum value of open positions allowed on the account. Positions are evaluated as follows:

For each symbol, the total value of positions and active pending orders is determined separately for each direction, i.e., separately for buy and sell operations. The platform calculates the difference in value between the buy and

sell sides. Such calculations are performed for every instrument for which the account has open positions and orders.

The obtained values are summed up and the result is compared to the specified limit. Once the limit is reached, the platform will disable the ability to place new orders if their execution could increase the total value of positions.

The value calculation for each position/order depends on the symbol's margin/profit calculation.

For the symbols with the Forex calculation type, the value is calculated in the base symbol currency and is equal to the product of the contract size and the volume. For example, for EURUSD with the contract size of 100,000, the value of 1 lot is equal to EUR 100,000.

For the symbols with the CFD, CFD Leverage, CFD Index and Futures calculation type, the value is also calculated in the deposit currency. Since the contract size of such instruments is not expressed in money (it can be expressed, for example, in the amount of assets), the contract size is additionally multiplied by the instrument price to obtain the value in monetary terms. For Futures symbols, the final value is additionally multiplied by the ratio of tick value to tick size. For example, if some Futures symbol has USD as the base currency, the contract size is equal to 100, the cost is 33, and the tick value to tick size ratio is 1/0.1, the value of one lot of the position is equal to $100 \times 33 \times 10 = \text{USD } 33,000$. For a CFD symbol with the same parameters, one lot size would be $100 \times 33 = \text{USD } 3,300$.


If the symbol base currency differs from the account deposit currency (specified after the field), the calculated value will be additionally converted using the relevant exchange rate.

- **Limit number of active orders** the maximum number of active (placed) pending orders allowed on the account. Once the limit is reached, the client will no longer be able to place new pending orders. If no value is specified (default), a limit defined at the group level will be used. If limits are set both at the account and at the group level, the stricter one of them will be applied.

Subscriptions

This section displays information about active additional trading service subscriptions.

MetaTrader 5 trading platform



Security

Account: 932996, Bailey Miguel, USD, 1:100

Overview
Personal
Account
Profile
Security

Master password is used for full access to the trading account

minimum 8 characters

Investor password is used for limited access to the trading account in read-only mode

minimum 8 characters

API password is used for access to the server using Web API

minimum 8 characters

Phone password allows to identify the account owner when performing trade operations by phone

to view password set focus to field

Shared secret key in combination with the current timestamp is used to generate one-time password

OTP secret key

Client Properties...
Update
Cancel
Help

The account passwords are managed on this tab.

Master Password

In this box you can check or change the master password to an account. To do this, type the password in the Password field and press the Check or Change button, depending on the required action. A click on Check opens the window containing the check result of whether the password matches the checked one or not.

To create a random master password, click Generate. Next, select Change to assign the created password to your account. You can set other passwords in the same way. After generating the password, copy it into the required field.

Investor Password

In this box, one can check or change the investor password (without possibility to trade) to an account. To do it, it is necessary to type it in the "Password" field and press the "Check" or "Check" button, depending on the action you need to perform. A click on Check opens the window containing the check result of whether the password matches the checked one or not.

Web API Password

This password is required when the account is used for authorization in a Web client created using MetaTrader 5 Web API. To check or change the password, type it in the Password field and press the Check or Change button, depending on the action you need to perform. A click on Check opens the window containing the check result of whether the password matches the checked one or not.

- Master, investor, and Web API passwords must contain four character types: lowercase letters, uppercase letters, numbers and symbols (#, @, !, etc.). For example, 1Ar#pqkj. The minimum password length is determined by group settings, while the lowest possible value is 8 characters. The maximum length is 16 characters.
- Once the password is changed, the connection of the account to the trader server is reset. A reconnection with the new password is required.

Phone Password

The phone password is intended for the identification of an account owner when performing trade operations by phone. To view the password put the mouse cursor to the "Password" field. In order to set a new password or change the current one, type it and press the "Update" button.

OTP Secret Key

The key is a link between the account and the one-time password generator it is bound to. The key is a sequence of 16 characters generated based on the data about the device the MetaTrader 5 mobile platform is installed on.


MetaTrader 5 trading platform

Each account can be bound to only one password generator. When trying to rebind the account to a new generator, a one-time code from the previous generator should be entered.

If the user no longer has access to the bound password generator (for example, the mobile device is lost), the current OTP secret key can be deleted. In this case, account authorization via one-time passwords is disabled and the user is able to bind the account to the new generator.

If the user has forgotten the password for the password generator (PIN) while using the same mobile device, they may simply reinstall the mobile platform and rebind the account to the generator. No one-time password is required when rebinding the account to the generator on the same device.

Certificate



This tab displays the authentication type of the group the account belongs to. It is not shown if the standard authentication mode is used. The following information is displayed here:

- **Certificate** information about the certificate if it has been generated or imported for the account. The certificate details include the account number, the owner name and the name of a Certificate Authority that issued the certificate. A window containing detailed information about the certificate will be opened if you click on the certificate name.
- **Confirm** this button is intended for confirming certificates of account that belong to the groups with the corresponding mode enabled. Until the certificate is confirmed, connection using the account in a manager or administrator terminal is impossible, while connection in a client terminal can be established only in the investor mode without the possibility to trade.
- **Reset** if the extended authorization mode is used for the account group then using this button one can reset the certificate that was issued earlier. At that it will be impossible to authorize using it, and at the next attempt of connection to the server using this account a new certificate will be issued.
- **Import** import a certificate for the account. Once this button is pressed, the window where you need to specify a certificate file (*.cer or *.crt) appears. Only the public component of the certificate is imported to the platform. During authorization, the client's certificate is compared to the one uploaded to the data base. In addition, the presence of a private key in the client certificate is checked. The import function is implemented to give the possibility of using custom mechanisms of generation of certificates.

- When a certificated is reset it becomes invalid. At the next attempt of connection the process of generation of a new certificate and further authorization using it will be performed.
- A detailed description of the entire process of the extended authentication is given in a separate section.

MetaTrader 5 Trading Platform / Platform Setup / Accounts / Preliminary Accounts

Preliminary Accounts

Traders can send a request to a broker to open a real account straight from desktop and mobile terminals. The user needs to fill in a simple request form and, if necessary, to attach two documents to confirm their identity and address.


MetaQuotes

REGISTER A NEW ACCOUNT

Real account
 Apply for a new live account by filling a simple form and sending identification documents

>

Demo account
 Register an account to learn trading and test your strategies

>

USE EXISTING ACCOUNT

Server

MetaQuotes

Login

enter login

Password

enter password

Save password

☒

Sign In


MetaQuotes

ADDRESS

State

optional

City

min 2 chars

Zip Code

optional

Address

min 6 chars

IDENTIFICATION DOCUMENT

Document

Passport >

Front Side

☐

Please take photos of your documents and upload them here without any editing.
 Some types of documents require two photos: front and back side.

PROOF OF ADDRESS

Document

Utility bill >

Front Side

☐

Utility bill must contain your name and address and be no older than three months.
 Bills for mobile services are not accepted as a proof of address.

Next

MetaTrader 5 trading platform

After that, a new account with a zero balance is created for the client in the "Preliminary" group. Trading is disabled for this group. After formalizing relations with the client, a manager can easily move the preliminary account to one of real groups, after which the client will be able to trade.


View the video "Increase conversion rate and optimize client management" for more details related to preliminary accounts.

Configuring groups for working with preliminary accounts

During platform installation, only one "preliminary" group is created on the main trade server. Preliminary real accounts requested by traders from the terminals will be created in this group.

Create preliminary groups for different countries, currencies and account types. This will enable automatic distribution of registrations to regional sales departments and will allow clients to select desired trading conditions, for example to request a standard, mini or micro account.

The names of preliminary groups should begin with "preliminary".




The screenshot shows the 'Broker - MetaTrader 5 Administrator' window. On the left, a tree view under 'Groups (44)' lists several categories: 'contest (1)', 'coverage (1)', 'demo (18)', 'funds (3)', 'managers (3)', 'preliminary (4)', and 'real (6)'. A red arrow points from the 'preliminary (4)' category to a table on the right. The table lists four groups, all starting with 'preliminary\'. The status bar at the bottom indicates 'For Help, press F1' and shows a memory usage of '15.0 / 0.2 M'.

Group	Server	Company	Type	Authentication	Marg
preliminary\usd-standard	Main Server	Forex Broker	Netting	Normal	50 / 30
preliminary\usd-mini	Main Server	Forex Broker	Netting	Normal	50 / 30
preliminary\eur-standard	Main Server	Forex Broker	Netting	Normal	50 / 30
preliminary\eur-mini	Main Server	Forex Broker	Netting	Normal	50 / 30

MetaTrader 5 trading platform

Then create account types under the Account allocation section, based on preliminary groups.



The screenshot shows the 'Broker - MetaTrader 5 Administrator' window. In the left sidebar, the 'Allocations' menu item is selected under 'Clients & Accounts'. A red arrow points from this menu item to the 'Group' dropdown in the 'Account allocation group' dialog box.

Account allocation group

Please specify a company and a group with description. This group will be available for opening accounts from the client terminals of this company.

Company: Default

Group: demo\forex-usd

Description: Forex USD

Leverages: 100,50,30,20,10,5

Countries: All countries

☐ Require identity and proof of address documents

☐ Start KYC check automatically

☐ Use advanced registration form

Confirm: Phone & Email

Mail server: Default

Agreement	URL	Mandatory
ab Client agreement	https://broker.com/agreements/account	☒
ab Data Protection Policy	https://broker.com/agreements/data-protection	☒

OK Cancel

MetaTrader 5 trading platform

Select here types of data to be requested from the trader when opening an account, as well as the need to provide documents and other details.

The platform automatically collects relevant information about traders. Every account the trader opens is linked to the appropriate client record. The documents provided by traders during preliminary account request are uploaded to the Documents section.

MetaTrader 5 Trading Platform / Platform Setup / Accounts / Archive and Backup Bases

Archive and Backup Bases

During the operation of a trade server a a lot of unused accounts are accumulated in the system. Most of them cannot be deleted, because they are necessary, for example, for solving disputes with clients. The archive database allows:

- To store the accounts that are not necessary to be maintained at the moment (for example, inactive accounts with insignificant deposits where trading is impossible);
- To quickly restore accounts from the archive for resuming the work with them;
- To decrease the server load for servicing the accounts, because the request to the archive database are not performed while working.

The archive databases are stored on the trade server, in separate files by years.

The archive of accounts does not affect trading operations. Orders, trades and positions are not deleted from current databases.

Working with Accounts Archive


- **Moving account to the archive**
To move an account to archive, select it in the Accounts section and click "👉 Move to archive" in the context menu.
- **Restoring account from the archive**
To restore an account from the archive, navigate to the Account section, select the archive database, and request an account from the database by its number. Once you have found an account, select it in the list and click "👉 Restore" in the context menu. After that, perform balance check and correction for the account.

- Restored accounts are not deleted from the archive.
- If an account is moved to archive again after it has been restored, new information about it will replace the one that is stored in the archive.

Backup Bases of Accounts

Backup copies are copies of the account database at certain points in time. They are created daily on the backup server. To get the list of available backup copies, select "More backups..." and specify a time period:

MetaTrader 5 trading platform



Backups period

Server: Backup Server, 4

Period: Today

From: 9/30/2022 to: 10/ 1/2022

OK Cancel


More backups... Request

As soon as the period is specified, additional items with the dates of creation of backup copies will appear in the list of database selection. After selecting the necessary database, request accounts from it. Using the "🔍 Restore" command of the context menu, any account can be easily returned back to the current database in the same state as when the backup copy was created.

MetaTrader 5 Trading Platform / Platform Setup / Accounts / Import of Accounts from File

Import of Accounts from File

The administrator terminal allows to import accounts to a trade server from CSV files. In order to do it, one should execute the "📄 Import from File" command in the context menu of the "Accounts" section.



File: D:\Accounts.csv Browse...

Separator: ; Begin from line: 0 Columns...

☒ Use selected items only Refresh

Login	Name	Group	Country	Balance
927869	Anderson Ashton	demo\demo forex	Morocco	5000130.16
927870	Wright Thomas	demo\demo forex	Czech Republic	4999436.42
927871	Baker Seth	demo\demo forex	Mexico	4998967.07
927872	Cooper Brian	demo\demo forex	Turkey	4999607.73
927873	Green Luis	demo\demo forex	Denmark	5000368.22
927874	Clark Kevin	demo\demo forex	Germany	4999544.69
927875	James Samuel	demo\demo forex	Israel	4999747.46
927876	Anderson Justin	demo\demo forex	Belarus	4999722.59
927877	Watson Miquel	demo\demo forex	Denmark	4999756.00

Apply Cancel

The following settings and commands are present in the window of account importing:

- **File** path to a *.CSV file, from which accounts will be imported. You can specify the path manually or select the necessary file by pressing the "Browse" button located to the right.
- **Separator** separator of data in the file (comma, semicolon, tab or space);
- **Begin from line** in this field you can specify a line in the file starting from which the data will be imported;
- **Columns** open the window of associating columns in the imported file with the corresponding fields in the system;
- **Use only selected items** if this option is chosen then only the lines that are currently selected in the preview window below will be imported;
- **Refresh** refresh the data in the preview window.


In order to start importing the accounts, one should press the "Apply" button. The process of importing will be displayed at the "Journal" tab of the "Toolbox" window.

By a double-click on a line in the preview window, you can see how the information would look like if the account was imported. The same action can be performed using the "View" command in the context menu. Using this menu you can also enable or disable the automatic arrangement of columns and the displaying of a grid.

- All the accounts are imported as disabled. Further they can be enabled manually at the "Account" tab.
- If passwords for accounts are not imported, set them afterwards.

Associating Columns

The window of associating columns is opened using the "Columns" command.



MetaTrader 5 trading platform

The left part contains the available columns and the right one contains the sequence of columns in the imported file. The following commands are present in the window:

- **Insert** add a selected column to the chosen ones;
- **Remove** remove a selected column from the selected ones. The "Login" field is obligatory, it cannot be removed;
- **Up** move an added column up relatively to the others;
- **Down** move an added column down relatively to the others;
- **Reset** return to default column settings.

Columns can also be moved by a double-click with the left mouse button on their names.

The sequence of selected columns is very important, since it is the way of associating them with the fields in the system. To skip one or several columns in the source file, it is necessary to use the special "Skip column" item. For example, if it is put in the third position from the top, then the third column in the imported file will be skipped.

When importing accounts exported from the MetaTrader 4 platform columns are associated automatically.


MetaTrader 5 Trading Platform / Platform Setup / Accounts / Import of Accounts from MetaTrader 5

Import of Accounts from MetaTrader 5 Server

You can easily import your account database from one MetaTrader 5 sever to another, including accounts' trading operations and history. You will need administrator accounts having access to accounts, groups and trading operations on these two servers.

You can also import accounts and trading operations from the MetaTrader 4 server.

Open the Accounts section in MetaTrader 5 and click "Import from Server":



Specify connection parameters:

- **Server Type** MetaTrader 5.
- **Server** the IP address and port of the MetaTrader 5 server separated by a colon.
- **Login** the number of the manager account for authentication on the server.
- **Password** the account password for authentication on the server.
- **Use certificate from file** advanced authentication can be enabled for the manager account on the source server, from which accounts are imported. A certificate is required in this case. If the certificate has previously been installed in the storage of the operating system, it will be automatically recognized by the import system. If the certificate has not been installed, enable this option and specify the path to the file manually.
- **Certificate File** click "Browse" and specify the pfx-file of the certificate. The certificate file received in the terminal is saved in */terminal data folder/profiles/server name/certificates/*.
- **Certificate Password** the password of the certificate.

To import accounts, you should have an administrator or manager account on the source server, with the following access permissions:

- Connection type: MetaTrader 5 Administrator or MetaTrader 5 Manager
- Accounts section: "Accountant", "Access accounts", "Access account personal details"
- Dealing section: Access to trading orders (if import includes trading history)

For security purposes, you should grant to the manager account the access only to specific trading account groups for import. Also you should disable the entire group of "Configuration settings" permission and allow connections only from a certain address. After the accounts import is complete, you can disable the manager account if it is not used for other purposes.

On the receiving server, you should have an administrator account (Connection type: MetaTrader 5 Administrator) with the same permissions along with the permission to access group settings.

MetaTrader 5 trading platform

Import

?

×

Connection details
Choose server type, fill server address and authorization information.

This wizard will help you to import settings from a MetaTrader 4 or MetaTrader 5 server. Please specify server type, address and authorization details below.

Server Type:

MetaTrader 5

▼

Server:

192.168.1.230:443

Login:

1000

Password:

●●●●●●●●

☐ Use certificate from file

NOTE: When importing settings from a MetaTrader 4 server, part of settings will be set to defaults. For importing settings from a MetaTrader 5 server with the advanced authorization mode, you must have a confirmed certificate for the account.

< Back

Next >

Cancel

MetaTrader 5 trading platform

Requesting accounts

The next step is to request the accounts that you want to import from the source server. Enter your request in the "Choose groups" field. Here you can specify a comma separated list of logins or a more complex query using the "*" masks and the "!" negation symbol.

The "Choose groups" field contains the default request of "!demo*,!manager*,!coverage*,!contest*,*", which allows to select all accounts except from groups of demo and manager accounts, as well as coverage and contest groups.

To execute the request click "Request".

Import ? X

Choosing trading accounts
Select trading accounts to be added to your database.

Choose groups:

Login	New Login	Group	Name	Balance	!
☒ 871318	881318	demo\demo forex	Spencer Jayden	5 000 000.00	
☒ 871319	881319	demo\demo forex	Patterson Landon	5 000 000.00	
☒ 871320	881320	demo\demo forex	Martin Eric	5 000 000.00	
☒ 871321	881321	demo\demo forex	Wood Jordan	5 000 000.00	
☒ 871322	881322	demo\demo forex	Taylor Kevin	5 000 000.00	
☒ 871323	881323	demo\demo forex	Cook Nicholas	5 000 000.00	
☒ 871324	881324	demo\demo forex	Parker Luke	5 000 000.00	
☒ 871325	881325	demo\demo forex	Account login already exists on the current server	0	
☒ 871326	881326	demo\demo forex	Turner Mason	5 000 000.00	
☒ 871327	881327	demo\demo forex	Jones Nicholas	5 000 000.00	
☒ 871328	881328	demo\demo forex	Johnson Jayden	5 000 000.00	

Move to group: Accounts: 63093 Valid: 47578 Selected: 47578

Login shift: ☒ Import balance, trades and trade history

< Back Import Cancel

An account having a red background cannot be imported to the server. The following reasons are possible:

- The group of the account on the source server and the current server have different position accounting types (hedging and netting). Try to select another group in the "Move to group" field.
- The currency of the account deposit does not match the deposit currency of the group to which you want to import the account.
- An account with the same number already exists on the current server or on one of other trade servers of the platform.
- The account number is out of the range of accounts allowed for the current server.
- The symbol, for which the account to import has orders or positions, does not exist on the server.
- The symbol, for which the account to import has orders or positions, had different numbers of decimal places on the source and target servers.
- The group of the account does not match any group on the server. In this case, you should specify in the appropriate field the group to move accounts to.

Information about the reason for not inability to import an account is available in the tooltip that appears when you hover the mouse over the account line.

Double click on an account to view how it would look like after import. This will open a standard account viewing window.

You can disable import of individual accounts from the list. To do this, click on the icon at the beginning of the account row, and then it will change to .

Depending on import settings, the login of a migrated account can be preserved or converted with an offset. For example, login 101980 is converted to 1101980, if the parameter "Login shift" is set to 1 000 000. If login shift is applied, the numbers of agent accounts in client records are shifted by the same value.

Import Settings

To import trading operations of selected clients, enable the "Import balance, trades and trade history" option. All available orders, deals and positions of the client will be imported.

You can also specify additional parameters:

- **Move to group** choose the group to import accounts to. The administrator executing the import procedure only has access to the groups on the server, to which the administrator account belongs. The list of groups available to the administrator can also be limited in manager account settings.
- **Login shift** you can specify a number, by which all numbers of imported account will be shifted. The shift can be wither positive or negative. For example, 1000 or -100.

Result of Import

MetaTrader 5 trading platform

The total number and the number of imported accounts will be shown on the last step:

Import?×

Importing trading accounts
Results of importing trading accounts to your database.

Login	New Login	Group	Name	Status ▲
○ 810911	810911	demo\demo forex-hed...	Lewis Matthew	Done
○ 810912	810912	demo\demo forex-hed...	Smith Thomas	Done
○ 810911	810913	demo\demo forex-hed...	James Brandon	Done
○ 810912	810914	demo\demo forex-hed...	Patterson Lucas	Done
○ 810911	810915	demo\demo forex-hed...	Patterson Michael	Done
○ 810912	810916	demo\demo forex-hed...	Evans Jayden	Done
○ 810911	810917	demo\demo forex-hed...	Green Ashton	Done
○ 810912	810918	demo\demo forex-hed...	James Brandon	Done
○ 810911	810919	demo\demo forex-hed...	Lewis Matthew	Done
○ 810912	810920	demo\demo forex-hed...	Clark Alejandro	Done
○ 810911	810931	demo\demo forex-hed...	Evans Jayden	Done

Accounts: 104 / 104

< BackFinishCancel

MetaTrader 5 trading platform


Import details are also available in the trade server journal.

- After import, the appropriate accounts on the source server must be disabled or set to the "read-only" mode to avoid trading state mismatch with the new MetaTrader 5 server.
- After completing the import for accounts having open positions, you can see the differences in equity and free margin in the Manager terminal. This may happen if quotes in the new MetaTrader 5 platform are significantly different from the ones in the source platform or a data feed is not configured. The Manager terminal calculates these values in real time according to the current prices in the platform. In the Administrator terminal, there are no differences (the values coincide with the source server) since data are taken directly from the accounts and are not recalculated.

Client connection and passwords

Random passwords are generated for imported accounts. Hashes of account passwords that were used on the source server are saved in the client record. They are used for verification during the first account connect in MetaTrader 5.

During the first connection to the imported account, the client will attempt to connect using the old password. Upon entering the incorrect password (since a new random password has been generate), a welcome dialog will be displayed:



Welcome to MetaTrader 5!

Welcome to MetaTrader 5!

Your account has been migrated to the 5th generation trading platform allowing you to trade Forex and CFDs, as well as various exchanges.

Filling orders using multiple deals, multicurrency and multi-threaded strategy tester, integrated MQL5 Cloud Network, and many other features are now available to you.

Confirm your trading account password and set a new one to start trading. All accounts and data transmission in the platforms are encrypted.

The new password must be complex enough, at least 8 different case letters and digits.

Login:

Previous password:

New password: Example: GetBun72

Confirm password:

MetaTrader 5 trading platform

The old account password that was used on the source server should be specified here. The client will not be able to continue without this password. A new password should be set here, which will later be used to connect to the account.

If authenticated successfully, the dialog will not be displayed again, and the client will work as usual.

You can set a new password for the imported account via the administrator or manager terminal and provide it to the client. The welcome dialog will not be displayed in this case. After password change, the hash of the password used on the source server is deleted from the client record.

Import Features

Accounts are imported in packages each containing 100 account. If an account from the package could not be imported, you will need to repeat the import. If errors occur, the previous state will not be restored. The accounts and trading operations from the package successfully imported before the error will not be removed. Before re-import, remove them manually in the following order:

- ORDERS
- Deals
- Positions
- Accounts

Importing may take a long time: it depends on the database size and your Internet connection speed.

MetaTrader 5 trading platform

MetaTrader 5 Trading Platform / Platform Setup / Accounts / Checking and Fixing Balance

Checking and Fixing Balance and Credit Funds

"Accounts" section provides the ability to check clients' balance and credit funds based on deals history. Corrections can be necessary for restoring the accounts and manual correction of trade history.

To perform a check, enable "Balance" and "Credit" columns via the context menu.

Login ▲	Name	Group	Balance / Checked	Credit / Checked	▲
915355	Bennett Joseph	demo\demo forex	4 999 724.26	0.00	
915356	Carter Luke	demo\demo forex	4 999 854.81	0.00	
915357	Jones Gavin	demo\demo forex	4 999 965.35	0.00	
915358	Bailey Aiden	demo\demo forex	4 999 860.77	0.00	
915359	Lee Jackson	demo\demo forex	4 999 841.74	0.00	
915360	Phillips David	demo\demo forex	4 999 752.93	0.00	
915361	Green Alex	demo\demo forex	4 999 814.56	0.00	
915362	Moore Adrian	demo\demo forex	4 999 871.68	0.00	
915363	Lee Dominic	demo\demo forex	4 999 778.24	0.00	
915364	Baker Diego	demo\demo forex	4 999 912.30	0.00	▼
Q * ▼			Current database ▼		Request

Select one or several accounts, for which you want to check the balance and credit funds, and execute "Balance - Check Balance" command in the context menu. If an incorrect balance or credit funds value is revealed, the appropriate account will be highlighted in red.

Login ▲	Name	Group	Balance / Checked	Credit / Checked	▲
915354	Bennett Antonio	demo\demo forex	4 999 710.79	0.00	
915355	Bennett Joseph	demo\demo forex	4 999 724.26	0.00	
915356	Carter Luke	demo\demo forex	4 999 854.81	0.00	
915357	Jones Gavin	demo\demo forex	4 999 965.35	0.00	
915358	Bailey Aiden	demo\demo forex	4 999 860.77	0.00	
915359	Lee Jackson	demo\demo forex	4 999 841.74	0.00	
915360	Phillips David	demo\demo forex	4 999 752.93	0.00	
915361	Green Alex	demo\demo forex	4 999 814.56	0.00	
915362	Moore Adrian	demo\demo forex	4999871.68 / 4999865.98	0.00	
915363	Lee Dominic	demo\demo forex	4 999 778.24	0.00	▼
Q * ▼			Current database ▼		Request

MetaTrader 5 trading platform

Two values will be displayed in "Balance" and "Credit" columns: the current balance/credit funds value will be displayed on the left, while the value calculated using the deals history - on the right.

Credit funds are checked by deals of "Credit" type (specified in "Action" field).

Check result is also displayed in the journal. If the calculated value differs from the current one, the following message will appear in the journal:

account xxx has invalid balance: xxx.xx, valid: xxx.xx

To correct the balance/credit funds value, execute "Balance - Fix Balance" command in the context menu. The calculated value will be inserted as the current one. Correction results are also shown in the journal:

balance of account '1030390' has been fixed from 9 968.70 to 9 999.80

MetaTrader 5 Trading Platform / Platform Setup / Accounts / Account Allocation Settings

Account Allocation Settings

Clients can only open new demo and preliminary real accounts from their terminals. Parameters for the allocation of such accounts can be specified in section "Clients and Orders Allocation of accounts":

- Groups, in which clients can open accounts depending on their country of residence (such groups may have different deposit currencies)
- Different leverage size for groups
- Groups with an extended registration form, which clients need to fill when requesting a real account
- Agreements, which clients need to accept when opening new accounts

MetaTrader 5 trading platform

Broker - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server + Import Export Apply

Groups (341)

Clients & Accounts

Allocations

Clients

Managers

Trading Accounts

Corporate links

Orders & Deals

Demo account allocation... https://broker.com/open_account

Deposit URL [https://www.broker.com/\[lang:ru|en|zh\]/deposit](https://www.broker.com/[lang:ru|en|zh]/deposit)

Withdrawal URL [https://www.broker.com/\[lang:ru|en|zh\]/withdraw](https://www.broker.com/[lang:ru|en|zh]/withdraw)

Group	C.	Type	Server	Countries	Leverag...
Default					
demo\demofor...	USD	Netting	Trade Secondary	CY,FR,DE,NL,PL,RU	100,50,3...
demo\demofor...	USD	Hedg...	Trade Secondary	All countries	10,50,100

Account allocation group

Please specify a company and a group with description. This group will be available for opening accounts from the client terminals of this company.

Company: Default

Group: demo\forex-usd

Description: Forex USD

Leverages: 100,50,30,20,10,5

Countries: All countries

☐ Require identity and proof of address documents

☐ Start KYC check automatically

☐ Use advanced registration form

Confirm: Phone & Email

Mail server: Default

Agreement	URL	Mandatory
ab Client agreement	https://broker.com/agreements/account	☒
ab Data Protection Policy	https://broker.com/agreements/data-protection	☒

OK Cancel

General settings are available in the upper part:

- **Demo account allocation URL** if you want to enable opening of demo accounts only from your web site, specify the address of the appropriate page in this field. When a client selects the demo account creating option in the terminal, they will be redirected to the specified page. If you fill in the URL address, all other account allocation settings become inactive. See "[Account Redirection](#)" for details.
- **Deposit URL, Withdrawal URL** URLs of your website pages in which traders can deposit or withdraw money from their trading accounts. If these fields are filled, all the "Deposit" and "Withdraw" commands in the terminals will be available to all accounts on your server (regardless of the group). A click on these commands opens the relevant pages of your website. Links to withdrawal and deposit pages are only displayed for real accounts. These links are hidden for demo accounts. For details, please see the [appropriate section](#).

- Opening of accounts from the terminal is preferable since a demo account is opened as quickly and convenient for a trader as possible.
- Any changes to account allocation settings are saved only after you click the "✓Apply" button in the context menu or on the toolbar.
- The 'Demo account allocation URL' option only affects the registration of demo accounts. The preliminary account opening option will be available in client terminals if there is at least one 'preliminary' group in the list of account allocation groups.
- The 'Demo account allocation URL' option is only used in the desktop client terminal versions. Redirection to an external site is not supported in mobile terminals.

Further you should configure groups, in which clients can open demo and preliminary accounts. Each entry of this table is displayed as a separate item in the "Account type" field of the account opening dialog in the client terminal. Only demo groups are shown during the opening of a demo account, and only preliminary groups are shown when opening preliminary accounts.

Prior to configuring groups, please make sure that [demo account allocation](#) is enabled for the trade server. Then, add a group by selecting  in the context menu or on the toolbar, and specify the settings:

- **Company** the name of the company (White Label), in which terminals the group will be available.
- **Group** the group of accounts. You can only select the demo group or a group of preliminary accounts. You can specify several groups to ensure [balanced distribution of accounts](#).
- **Description** the description of the group, which will be shown in the "Account type" field in client terminals.
- **Leverages** the list of available leverage options, which a client can choose from when opening an account. This list is ignored if the default leverage is

specified in [group settings](#).

- **Countries** the list of countries: the group will be available to clients from these countries. If the client's country does not match any group (taking into account the group availability by the "Company" field), the client will be shown the first group from the list.
When opening a demo account, the country is determined automatically on the client terminal side. When opening a preliminary account, the country is also detected automatically, but the client can specify another country in the registration form. To select/deselect all countries in the list, right-click on it.
- **Require identity and proof of address documents** by default, the client is requested to provide ID and proof of address documents, when opening a [preliminary account](#) from the terminal. If you disable this option, documents will not be required when opening an account. The block for loading documents will be hidden from the corresponding dialog in this case.
- **Start KYC check automatically** if this option is enabled, client data and documents will be automatically sent to the [KYC service](#) once a preliminary account is opened and linked to a client. After the check, the system provides a report which can be viewed under the [client comments section](#).
- **Use advanced registration form** if the option is enabled, clients need to fill in an extended form when opening a preliminary account. In addition to standard personal data, the extended form requires specifying information on citizenship, employment, income and trading experience.
- **Confirm** the option enables verification of phone numbers and emails which traders specify when opening demo and preliminary accounts from client terminals. Please see [below](#) for details.
- **Mail sever** [the mail server configuration](#), which will be used for email confirmation when opening this type of accounts. Please see [below](#) for details.

If no account allocation group is specified, clients will not be able to open demo or preliminary accounts from client terminals.

Agreements in the account opening form

In the field below, you can add links to agreements, which clients need to accept when opening a preliminary or demo account. Specify the name of the agreement or select one of the predefined values, and then add a link.

Confirm: Phone & Email Mail server: ABC Broker

Agreement	URL	Mandatory
ab Complaints handling procedure	https://abcbroker.com/client_agreement	☐
ab Client agreement	https://abcbroker.com/risk_disclosure	☒
ab Risk disclosure	https://abcbroker.com/gdpr	☐
ab Client agreement and risk disclosure		
Complaints handling procedure		
Order execution policy		
Client categorisation notice		
Conflicts of interest policy		
Data Protection Policy		

OK Cancel

MetaTrader 5 trading platform

Agreements are displayed as links in the account opening dialog:

Open an Account

Opening a demo account
A demo account allows trading with virtual money

First name: Joe
Second name: Black
Email: smith@mail.com
Phone: +357 (Cyprus)

☐ Use hedge in trading

Server: Meta-Trade

Account type: Demo-EUR
Demo-Netting
Demo-OTP
Demo-OTP+RSA
Demo-1024
Demo-2048
Demo-EUR

Deposit:
Leverage:

By continuing, you agree to receive information by email and phone

< Back Next > Cancel

Open an Account

Opening a real account
A real account is required for live trading on financial markets

Country: Cyprus
State: optional
City: Nicosia
Zip code: 3125
Address: 28 Oktovriou

Identification documents:
Identity: Joe Black.Person.jpg
Address: Joe Black.Address.jpg

☐ Use hedge in trading

Account type: Real EUR

[Account opening agreement](#)
☒ I agree with the terms of opening an account

< Back Next > Cancel

Up to two types of agreements can be displayed in a normal account opening form:

- Client Agreement (or Client Agreement and Risk Notification) and Data Protection Policy, in case both types of agreement are specified. If the Client Agreement is not specified, the first user agreement from the list (if any) will be shown instead. A user agreement is the one, which name has been specified manually (rather than selected from the predefined list).
- Client Agreement (or Client Agreement and Risk Notification) or Data Protection Policy, in case only one of them is specified.
- If no agreements are specified, only the following check box will be displayed in the account opening dialog: "I agree with the terms of opening an account and the data protection policy".

Up to ten types of agreements are shown in the expanded form.

Use the [lang] macro in the links to show to users the agreements in the desired language. The macro substitutes the language identifier into the link depending on the language of the client terminal interface. For example, you can specify the link as follows: [https://abcbroker.com/\[lang\]/client_agreement](https://abcbroker.com/[lang]/client_agreement). If the client uses the English interface of the terminal, the following link will be generated for this user: https://abcbroker.com/en/client_agreement. For the Spanish interface, the link will be https://abcbroker.com/es/client_agreement. The following languages are supported: en, ru, es, pt, zh, ar, cs, fr, it, de, el, id, ja, pl, tr.

- You cannot add a disabled group to the list of groups for opening demo accounts. Allocation of demo accounts is impossible in such groups. If there is a disabled group among the previously selected ones, a warning is displayed when closing the dialog window.
- You can set the expiration time of demo accounts in each trade server's parameters.

Agreements can be marked as mandatory. For example, the acceptance of account opening rules and Privacy Policy is required by law and is therefore considered as mandatory. Such agreements require a separate, explicitly set checkbox in the account registration window, while the acceptance of the agreement will be additionally displayed in the trade server log.

MetaTrader 5 trading platform

Open an Account: Forex Broker

?

×

Opening a real account
A real account is required for live trading on financial markets

Real trading experience:

Forex: < 1 year ▾

CFD: < 1 year ▾

Futures: < 1 year ▾

Stocks: < 1 year ▾

☒ I agree with the terms and conditions for opening an account

☒ [Client agreement](#)

☒ [Risk disclosure](#)

 [I agree to receive newsletters and company news](#)

< Back

Next >

Cancel

MetaTrader 5 trading platform

Similar behavior is implemented in mobile terminals for iOS and Android.

When the user accepts each mandatory agreement, a relevant event is added to the trade server log:

'27904969': accepts mandatory agreement 'Risk disclosure' -
<https://abcbroker.com/legal/risk>

A relevant comment is also added to the client record:

Accepts agreements on account '1092' allocation :

Client agreement

Risk disclosure

Segmentation of accounts by groups

The distributed architecture of the trading platform enables the management of a huge number of accounts, without compromising performance. Performance optimization is supported both at the cluster level and at the database level.

To ensure efficient server operation, it is recommended not to use huge groups that include several thousand accounts. Instead, it is better to create several smaller groups and to evenly distribute accounts among them. This will improve the quality of your services.

The platform provides the automated distribution of accounts into different groups, at the moment the account is opened via a client terminal.

To enable this feature, create account groups with indexes in the name, such as:

- demo\forex-hedge-usd-01
- demo\forex-hedge-usd-02
- demo\forex-hedge-usd-03

These groups must have the same settings.

Next, in the account allocation settings, specify the group as follows:
demo\forex-hedge-usd-01 .03.

Account allocation group

Please specify a company and a group with description. This group will be available for opening accounts from the client terminals of this company.

Company: Default

Group: demo\forex-hedge-usd-01..03

Description: Demo-Hedging

Leverages: 50,100

Countries: All countries

☐ Require identity and proof of address documents

☐ Start KYC check automatically

☐ Use advanced registration form

Confirm: None

Mail server: MetaQuotes.net

All accounts will be evenly distributed into three groups.

Distribution of accounts is performed by access servers. Accounts are distributed evenly, but not necessarily sequentially, i.e. not necessarily from the first to the last group in the list.

Automatic selection of account type based on the client's country

You can configure allocation of demo and preliminary accounts in groups with different deposit currencies on the server. These groups are displayed as different account types in client terminals. You can configure allocation of accounts with expected deposit currency for clients. This possibility is provided by a special mechanism, which is implemented in the side of desktop and mobile terminals. If possible, a group with the deposit currency corresponding to the region/country is selected by default in the account allocation form:

- EUR for clients from Europe
- CHF for clients from Switzerland
- JPY for clients from Japan
- GBP for clients from the UK

If groups with such currencies are not available, the first group with USD currency will be selected by default.

When opening a demo account, the country is determined automatically on the client terminal side. When opening a preliminary account, the country is also detected automatically, but the client can specify another country in the registration form.

Phone and Email Verification

The trading platform provides built-in features for the verification of phone numbers and emails which traders specify when opening demo and preliminary accounts via client terminals. Configure verification and access wider opportunities in working with

potential clients by collecting valid contact information.

Verification Setup

To verify data, small confirmation codes are sent to traders by SMS and email.

- To send SMS, you should configure messenger integration. Mail server integration is required for email confirmation.
- For each account type, in the Confirm parameter select which data should be verified: phone number, email of both of them.
- Specify the mail server, which will be used to confirm emails during the registration of this account type.
- The SMS provider is selected based on group and country settings, as well as the working statistics.

You can additionally specify your own email and SMS text to be sent to traders for confirmation. Use standard templates on the trade server:

- [main server installation directory]\templates\verify_email HTM files with email templates.
- [main server installation directory]\templates\verify_phone text files for SMS templates. Do not use too large messages. If the allowed length is exceeded (depending on the provider), a message may be cropped or split into several SMS.

Confirmation on the client side

During demo or preliminary account registration, traders provide their contact data, including phone number and email. If verification is enabled for the selected account type (group), confirmation codes are automatically sent to the trader and special code fields appear in the dialog box:

MetaTrader 5 trading platform

Open an Account

?

×

Opening a demo account
A demo account allows trading with virtual money and learn without risk

First name: John

Second name: Smith

Email: trader@mail.net

Phone: +1 United States 123126999

confirmation code

confirmation code

We have sent confirmation codes to your phone and email. Please specify them.

☒ Use hedge in trading

Server: MetaQuotes-Demo

Account type: Demo-Hedging

Deposit: 1000000 USD, virtual money to be deposited to your account

Leverage: 1:100 virtual credit funds to be provided by the broker for trading

☒ I agree with the terms and conditions for opening an account and the data protection policy

< Back

Next >

Cancel

MetaTrader 5 trading platform

Confirmation codes are valid for three hours. If the code is not entered in the field within this time frame, the trader will need to repeat the procedure.

Before sending codes, the system checks whether the specified phone/email was previously confirmed. If the trader has already passed verification from his or her computer in the last 72 hours, an account will be opened without additional confirmation. Thus, there will be no additional burden for traders and no additional costs for brokers.

The system automatically controls the correctness of specified phone numbers on the client terminal side. This prevents the sending of codes to incorrect numbers and thus saves you costs for the SMS provider services.

- The phone number must be specified in the international format: +[country code][number], for example: +79171113594. The number should be specified without spaces.
- This must be a mobile phone number, not landline.

In addition, the system checks the correctness of email addresses. Temporary addresses and unreliable mail services are not allowed.

The number of confirmations of different phone numbers and email addresses that a trader can request from one computer is limited for security purposes. When the limit is reached, confirmation codes are no longer sent, and the following messages is printed in the server log:


too many phone confirmation requests from IP

too many email confirmation requests from IP

Account Redirection

To disable opening demo accounts from the client terminals, but redirect a client to your own web page, specify "Demo account allocation URL". The list of groups will be deactivated and the client will be redirected to the specified page when trying to open a demo account from the terminal:

MetaTrader 5 trading platform



Request parameters separated by "&" symbol are additionally passed in the address line:

<https://www.accountallocation.url/?type=demo&acp=1251&label=CompanyName&server=9>

- **first_name** the first name specified in the registration form on the client terminal side.
- **second_name** the last name specified in the registration form on the client terminal side.
- **email** the email specified in the registration form on the client terminal side.
- **phone** the phone number specified in the registration form on the client terminal side.
- **age** the number of days elapsed since client terminal installation.
- **type** the type of the account requested: demo or real.
- **acp** code page used by a trader.
- **label** the name of the company which owns the terminal White Label.
- **server** the name of the server selected by the trader when opening an account.
- **interface** the UI language of the client terminal.
- **cid** trader unique computer ID.

When forming a request, the presence of "?" symbol in Account allocation URL parameter is checked. In other words, it is checked whether the specified address contains its own request parameters:

- If there is no "?" symbol in the address, it is formed with the standard set of parameters described above. For example, <https://www.mycompany.com>.
- If "?" symbol is present in the address, standard parameters are added to the specified custom ones. For example, if https://www.mycompany.com?utm_campaign=terminal address is specified, the final line has the following look:
https://www.mycompany.com?utm_campaign=terminal&type=demo&acp=....


- The link address must start with "https://" or "http://".
- When opening demo accounts via the website, it is impossible to set different addresses for the main and additional labels. Only a single link can be specified instead. On the website itself, you have to re-direct customers to different web pages depending on what terminal has been used to open an account. The terminal label can be defined by the additional "label" parameter automatically added to the link on the client terminal side.
- The redirect function only works for demo accounts. Preliminary accounts can only be opened from client terminals.
- The 'Demo account allocation URL' option is only used in the desktop client terminal versions. Redirection to an external site is not supported in mobile terminals.

MetaTrader 5 Trading Platform / Platform Setup / Accounts / Corporate Links

Corporate links

Some regulators require brokers to show traders a certain set of agreements and regulatory documents. In particular, one of the NFA requirements is to display a document on providing information about transactions (Transactional Data Request). In order to enable brokers to bring client terminals into compliance with the requirements, the trading platform provides a mechanism for adding custom links.

Set a list of corporate links and they will automatically appear in the desktop, mobile and web client terminal menus.




MetaTrader 5 trading platform

Go to "Clients & Accounts \ Corporate links", add a new entry and specify the settings:

- **Company** name of a company (White Label) displaying the links.
- **Group** group of accounts the links are to be displayed for.
- **Description** description to be displayed in the list of settings.
- **Countries** list of countries the links are to be displayed for. A country is taken from the account settings.

Using these settings, you can create different sets of links. They will be displayed depending on what account the client is connected to in the terminal.



Specify the agreements and links to them at the bottom. They will be displayed in client terminals.

Use the [lang] macro in the links to show to users the agreements in the desired language. The macro substitutes the language identifier into the link depending on the language of the client terminal interface. For example, you can specify the link as follows: [https://broker.com/\[lang:en|es|de|zh\]/client_agreement](https://broker.com/[lang:en|es|de|zh]/client_agreement). If the client uses the English interface of the terminal, the following link will be generated for this user: https://broker.com/en/client_agreement. For the Spanish interface, the link will be https://broker.com/es/client_agreement, etc.

Languages are specified in the ISO 639-1 format. The following values are supported: en|ru|es|pt|zh|ar|cs|fr|it|de|el|id|jp|pl|tr. If the interface language does not match any of the values specified in the macro, the first language from the list will be used.

Settings check order

Link settings are checked from top to bottom. The first suitable setting is applied to the account, while further settings will be ignored. For example, you have created the following sets of links:

1. Groups: real*; Countries: Spain, France, Portugal
2. Groups: real*; Countries: USA, Canada
3. Groups: All; Countries: All

The second set of links will be shown to a real account from Canada. Any account created outside of the real* groups will see the third set of links.

If you change the settings order as follows:

1. Groups: All; Countries: All
2. Groups: real*; Countries: Spain, France, Portugal
3. Groups: real*; Countries: USA, Canada

The first set of links will be shown to all accounts. Sets 2 and 3 will not be used.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Accounts](#) / Links to Depositing and Withdrawing

Links to Depositing and Withdrawing


You can redirect traders to your deposit and withdrawal pages directly from client terminals. By enabling this option you eliminate the need for you traders to search for the necessary pages in their trader's rooms, while they will be able to simply click an appropriate command in the account or trading section menu.

You can set up full platform integration with [payment systems](#) and accept payments directly through client terminals.

How to set up

You can add deposit and withdrawal links using [account allocation settings](#) and [group settings](#):

MetaTrader 5 trading platform



MetaTrader 5 trading platform

Links in account allocation section apply globally, to all groups. Thus, added deposit and withdrawal links will be available for all accounts within the platform. Links in groups allow overriding global settings or enabling this option only for separate accounts. If you do not want to enable deposit and withdrawal commands for all accounts, leave appropriate account allocation settings unchanged and add links only to the specific group settings. Links to withdrawal and deposit pages are only displayed for real accounts. These links are hidden for demo accounts.

Trader parameters separated by "&" symbol are additionally passed in the address line. Analyze the parameters to direct the traders to the required page and to automatically fill deposit/withdrawal form fields.

`https://www.deposit.url/?login=1815985&email=john@smith.net&type=real¤cy=USD`

The following parameters are supported:

- login account login
- type account type: demo, contest or real
- currency account deposit currency
- acp code page used by a trader
- label name of the company which owns the terminal White Label
- server the name of the server on which the account is open
- interface the current language of the client terminal interface
- cid trader PC's unique ID
- age the number of days elapsed since client terminal installation.
- email the email address specified in the trading account
- utm_campaign the name of the marketing campaign from the Lead Campaign field of the trading account. The parameter is filled automatically in accordance with the UTM used in the installation link of the relevant terminal, from which the commands are clicked.
- utm_source the source name from the Lead Source field of the trading account. The parameter is filled automatically in accordance with the UTM used in the installation link of the relevant terminal, from which the commands are clicked.

You can use the [lang: ...] macro in the address line to forward a trader to the desired language page. The list of languages in ISO 639-1 format should be specified here. If one of the listed languages matches the interface language of the client terminal, it will be used for the news language. Otherwise, the first language in the list is used.
Example:

`https://www.deposit.url/[lang:ru|en|es]`

Additional link parameters are not supported. If necessary, you can use the redirect option on your site.


For example, you use the same page for deposit and withdrawal
`https://www.abcbroker/balance`. If you specify it in both parameters on the MetaTrader 5 side, your site will not know which action was requested by the user. To solve this issue, set different deposit and withdrawal URLs on the platform side

<https://www.abcbroker/balance/deposit> and <https://www.abcbroker/balance/withdraw>. The user can then be redirected to the appropriate page on the platform side, while the additional parameters will be registered.

How the option appears on the client terminal side

If deposit and withdrawals URLs are configured for an account, appropriate commands appear in client terminals:

- in the account context menu in Navigator
- in the context menu of the trading section in Toolbox
- in the account status bar in the trading section Toolbox




If payment systems integration is configured in the platform, these commands will redirect the user to the payments section. Links to deposit and withdrawal pages will not be used.

MetaTrader 5 Trading Platform / Platform Setup / Payments

Integrated Payment Processing System

MetaTrader 5 features a built-in payment receiving and sending system. Your clients do not have to leave the platform in order to deposit or withdraw funds. The relevant operations can be performed straight through the trading terminal. The platform is integrated with various payment providers and thus your traders can access all the necessary deposit/withdrawal methods, including bank cards, popular wallets, and bank transfers. All transactions are securely encrypted and are completely safe.

Payment system integration with the platform ensures that you always work with a single database. All transactions are linked to accounts and client records. For example, by opening client data, you can easily see all payments along with transaction amounts, dates, cards, etc. You won't need complex and expensive integrations with payment systems and third-party CRMs.



The benefits of built-in services for your company:

- Streamlined onboarding. Since the need for additional registration on your website is eliminated, users can download the trading platform, open an account, make a deposit, and start trading. This accelerates the account opening process for potential customers and enables a seamless transition to real trading for demo users.
- Cost reduction. You don't need to invest in the development, configuration, and maintenance of infrastructure for customer registration, payment processing and transaction management. This might be especially relevant for start-up companies which possess limited resources.
- Increased deposit volumes. The natively integrated payment option simplifies the deposit process. Thus, users can faster respond to market situations by adding funds to their accounts. This contributes to overall growth in user deposits.
- Higher deposit frequency. With all the required features available within the trading environment, your traders can maintain trading focus and engagement for longer periods. By eliminating distractions and the need for additional authentications in third-party resources, you can increase decision-making speed and achieve higher deposit frequencies.

Configure integrated payments for your traders to eliminate extra costs, increase demo to real conversion rates, implement seamless onboarding procedures and boost deposits from existing clients.

How it works

- You set up integration with the payment system on the server side.
- A special section for deposits and withdrawals will become available in client terminals.
- Your client makes a payment via the terminal and the transaction is forwarded to your payment provider for processing. Depending on the rules configured on the server, the transaction may be additionally confirmed by the manager.
- If the transaction is successfully processed in the payment system, the corresponding balance operation is performed on the client's account in MetaTrader 5.
- All deposit and withdrawal operations are stored in the platform database and are available in the Active and History sections. Transactions are linked to client records and trading accounts, so you can easily access all the necessary information whenever you need it.

How to start the service

- Select a payment provider. The platform currently supports Unlimit, ECOMMPAY, APS, AstroPay, EU Paymentz and Kora. If your preferred payment provider is not currently available in the service, please reach out to us for possible integration options. Contact the selected provider and sign their service agreement.
- Configure a wallet in the platform. After you sign the agreement with the payment provider, they will send you all the necessary data to set up service integration. Usually, the data includes a login, a password and a special access

MetaTrader 5 trading platform

key. Connecting the provider in the platform will take 10-15 minutes.

- Set payment processing rules. The system enables flexible configuration of deposit and withdrawal processing rules depending on transaction parameters. For example, you may set all bank transfers to be processed manually and card payments up to 1000 USD to be confirmed automatically.

MetaTrader 5 Trading Platform / Platform Setup / Payments / Payment Gateways

Payment Gateways

To enable payments in MetaTrader 5, choose a provider company that will receive and send payments on your behalf. All currently available providers are featured in the showcase:

The screenshot shows the MetaTrader 5 Administrator interface. On the left, the 'Payments' menu is expanded, and 'Providers' is selected. The main window displays the 'Payment Service Providers' section, which includes a search bar and a list of providers. Each provider entry includes a logo, name, contact details, and a 'Connect Provider' button.

Provider	Contact Information	Connect Button
Advanced Payment Solutions (aps) Advanced Payment Solutions (APS) empowers businesses globally with online and corporate payment solutions. As a leading Payment Service Provider (PSP), we offer a turnkey payment processing...	Ip.aps.money Cyprus sales-pd@aps.money +35725580734 206 1 2	Connect Provider
Bitronum Ltd (EUPaymentz.com) EUPaymentz is an authorized partner of MetaQuotes and a preferred payment service provider of MetaTrader 5 Payments. Our latest Bitronum payment technology combines advanced encryption an...	www.eupaymentz.com United States of America info@eupaymentz.com +441244941125 249 12 198	Connect Provider
Unlimit Unlimit is a global fintech company that was established in the year 2009. The company offers an...	unlimit.com Cyprus sales@unlimit.com +35725388616 176 19 198	Connect Provider
AstroPay	www.astropay.com United Kingdom sales@astropay.com +4422567839 249 12 198	Connect Provider

MetaTrader 5 trading platform

If your preferred payment provider is not currently available in the service, please [reach out to us](#) for possible integration options.

To start working with a provider, you will need to sign an agreement with the selected company. Click 'Connect Provider' and fill out a short form. The company representative will contact you and will provide further instructions. Upon finalizing the agreement with the payment provider, you will receive the necessary details to configure integration in the platform. Typically, this includes a login and a password or a special access key.

Go to Payments \ Wallets and create a new wallet. Please note that you should configure separate wallets for each trading server. Thus, if you have multiple trading servers, create wallets for each of them.

You can create multiple wallets for each payment provider (gateway), by dividing the configurations by payment methods, currencies, etc. This will allow more flexible customization of the service. For example, you can provide access to different payment methods for different categories of traders.

MetaTrader 5 trading platform

MetaQuotes - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Import Export Apply + Settings X Back Forward Sort

Payments

- Active
- History
- Accounts
- Wallets
 - Trade Main
- Deposit
- Withdrawal
- Gateways
- Data Feeds
- Plugins
- Reports
- ECN
- Routing
- Funds & ETF
- Symbols (88)

For Help, press F1

Name	Provider	Actions	Type
HSBC Hong Kong, USD	Bank Transfer	deposit	wire transfer
Unlimit - WebMoney	Unlimit - WebMoney	deposit, withdrawal	webmoney
Unlimit - PayPal	Unlimit - PayPal	deposit, withdrawal	paypal
ECOMMPAY - Card	ECOMMPAY - Card	deposit, withdrawal, a...	card

Payment Wallet: Unlimit - Card

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: Unlimit - Card

Gateway: Unlimit Trade Main, 1

Type: Card

☒ Deposit ☒ Push notification

☒ Withdrawal ☒ Email notification

☒ Account creation

Login: 123456

Password:

OK Cancel Help

Specify general settings:

- **Name** the name of the wallet. Set clear names that include the name of the payment system and other details, such as available payment methods, currencies, etc. Appropriate naming will ensure efficient wallet management.
- **Gateway** payment provider: Unlimit, ECOMMPAY, APS, AstroPay, EU Paymentz, Kora, emerchantpay, Pay.com, Exactly, Ozow, AK Remit, The Kingdom Bank, OpenPayd, STICPAY, ChipPay, Uniwire or Bank Transfer.
- **Trading server** the server for which the wallet is configured. Payments through this wallet will only be available to accounts running on the same server.
- **Type** payment method type: bank card, electronic wallet, etc. The list of available options depends on the selected provider.
- **Allowed operations** deposits, withdrawals, payment accounts. At the moment, payment accounts are used only for transactions with bank cards. If the creation of payment accounts is disabled, users can still:
 - ◆ Deposit funds using a new card. Upon completion of the transaction, the card details partially masked will be automatically saved in MetaTrader 5 as a payment account.
 - ◆ Deposit funds using previously saved cards.
 - ◆ Withdraw funds using previously saved cards. The option to withdraw to a new card and the "Add New Card" button will not be displayed in client terminals.
- **Push notification** send notifications about transaction results to traders' mobile devices. Push notifications are sent to MetaQuotes ID specified in account settings. Notification text is customizable via templates.
- **Email notification** send email about transaction results to traders' email addresses specified in account properties. At least one default mail server must be configured in the platform to enable email sending. Notification text is customizable via templates.

Further settings depend on the provider:

- Unlimit
- ECOMMPAY
- APS
- AstroPay
- EU Paymentz
- Kora
- emerchantpay
- Pay.com
- Exactly
- Ozow
- AK Remit
- The Kingdom Bank
- OpenPayd
- STICPAY
- ChipPay
- Uniwire

- Bank Transfer

If you need additional payment providers or payment methods, please contact our support team.

Currency

Use this section to configure the currencies that will be available for transactions through this wallet. To make a currency available, add a new line and specify the parameters:

- **Currency** the name of the currency. The list of available currencies depends on the selected provider and payment method. Check with the provider if the desired currency is supported.
- **Min. Deposit** the minimum amount in the specified currency that can be deposited via this wallet.
- **Max. Deposit** the maximum amount in the specified currency that can be deposited via this wallet.
- **Min. Withdrawal** the minimum amount in the specified currency that can be withdrawn via this wallet.
- **Max. Withdrawal** the maximum amount in the specified currency that can be withdrawn via this wallet.

Payment Wallet: Unlimit - Card

Common Currencies Parameters Countries Groups Commissions Information

Please specify the currencies that will be processed by this payment wallet. Empty list means the wallet is unavailable to clients.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
USD	0.00	unlimited	0.00	10 000.00
EUR	0.00	unlimited	0.00	10 000.00
GBP	0.00	unlimited	0.00	10 000.00
+ click to add...				

Add Edit Delete

OK Cancel Help

The settings in this section affect the display of deposit and withdrawal pages in client terminals for this wallet. In particular, the list of currencies and restrictions on transaction amounts.

Deposit to account 3805827: John Smith

[Back to Payments](#)

Choose a payment method:

☒  Unlimit - Card

☐  Unlimit - WebMoney

☐  Unlimit - PayPal

Email:*

Bank card:

[Add new card](#)

Choose the payment system currency:

USD

▼

USD

EUR

GBP

...

The payment amount will be converted to your trade account currency (USD) automatically

Selected deposit amount:

USD

Commission: 10 USD

The approximate amount to be charged: 1 010 USD

[Continue](#)

MetaTrader 5 trading platform

If the payment currency is different from the deposit currency, the amount will be automatically converted when credited/debited from the account. Conversion follows the same rules that are applied for trading profit conversions. For deposits, the conversion is made at the rate of purchasing the account currency for the transaction currency, while the relevant selling rate is used for withdrawals. For example, if the account currency is EUR and the transaction currency is USD, then the deposit amount will be converted at the EURUSD Ask price and the withdrawal amount will be converted at EURUSD Bid price.

If no currency is specified for the wallet, this means that it accepts payments in any currency. If the setting does not fit the provider requirements and a client requests a payment in an unsupported currency, the operation is rejected.

Parameters

This section specifies additional options specific to each payment provider. They are described in the respective subsections.


- Unlimit
- ECOMMPAY
- APS
- AstroPay
- EU Paymentz
- Kora
- emerchantpay
- Pay.com
- Exactly
- Ozow
- AK Remit
- The Kingdom Bank
- OpenPayd
- STICPAY
- ChipPay

- Uniwire

- Bank Transfer

Countries

Specify the list of countries in which this wallet will be used. For example, if you are setting up transactions through a payment system that is used only in Brazil, specify this particular country in the wallet settings. Thus, all other users for whom this system is irrelevant will not see it in terminals.




If no country is specified, the wallet will be available to clients from any country.

When opening a preliminary account, the country is determined automatically on the client terminal side, but the client can specify another country in the registration form. You can change the country manually in account properties.

Groups


Specify the list of groups for which this wallet will be used. Using this feature, you can organize work with your White Label partners. For example, they can select the preferred payment providers and pay for their services, or vice versa, they may opt not to use the integrated payment system.

The payments section is only available for real accounts and is not shown for other account types.



Commissions

Configure commissions for operations through this wallet. For deposits, the amount indicated in the terminal will be credited to the user's account, while the user will pay more in the payment system, taking into account the commission. For withdrawals, the amount including the commission will be debited from the user's account, while the actually received amount in the payment system (card or wallet) will be smaller and will be equal to the withdrawal amount specified in the terminal.



Commissions can be multilevel, i.e. vary depending on the transaction amount. Create amount ranges and specify your own parameters for each of them:

- **From/To** minimum and maximum transaction amount to apply the setting. Commission units depend on the Mode field. For the "interest" mode, the values are set in the client's deposit currency. In all other cases, they are set in accordance with the specified currency.
- **Commission** commission amount. Commission units depend on the Mode field.
- **Minimal/Maximal** minimum and maximum amount of commission. Commission units depend on the Mode field. For the "interest" mode, the values are set in the client's deposit currency. In all other cases, they are set in accordance with the specified currency. To disable the minimum or maximum commission limit, set the value to 0.
- **Mode** commission calculation units:
 - ◆ **Deposit currency** the deposit currency of the account that makes the payment.
 - ◆ **Wallet currency** one of the available wallet currencies. The amount will be charged in the currency selected by the user on the client terminal side. The setting makes sense for wallets with one currency or currencies with a similar rate. Otherwise, the actual commission amount may vary significantly depending on the currency that the user selects.
 - ◆ **Specified currency** the currency specified in the Currency field.
 - ◆ **Percent** percentage of the transaction amount. The maximum value is 100%.

MetaTrader 5 trading platform

- **Currency** commission currency. The parameter is only used for the "Specified currency" mode. The currency has a three-letter representation, e.g. EUR, USD, JPY, etc.
- **Direction** the type of transactions for which the commission will be charged: deposits, withdrawals, or all.

The commission amount in client terminals is displayed next to the transaction amount:

Deposit to account 3805827: John Smith

[Back to Payments](#)

Choose a payment method:

☒  Unlimit - Card

☐  Unlimit - WebMoney

☐  Unlimit - PayPal

Email:*

Bank card:

[Add new card](#)

Choose the payment system currency:

USD ▼

The payment amount will be converted to your trade account currency (USD) automatically

Specify the desired deposit amount:

USD


Commission: 10 USD

The approximate amount to be charged: 1 010 USD

[Continue](#)

Information

This section displays general information about the payment provider, supported currencies, and payment methods. It also specifies the name and version of the integration module (DLL).



Notification Templates

You can send push or email notifications to traders about transaction results. Notifications are enabled in common wallet settings. They are provided for the following cases:

- Successful deposit
- Failed deposit
- Deposit operation completed in the payment system and is awaiting manager's confirmation
- Successful withdrawal
- Failed withdrawal
- Withdrawal is awaiting confirmation by a manager after which it will be sent to the payment system

Notification templates are located in [trade server directory]\templates\payment\. You can customize them.

Macros in the templates allow substituting payment details, user data, and company information in the notification text.

Payment Macros

- <!--PAYMENT_ID--> payment identifier.
- <!--PAYMENT_DATE_CREATED--> payment creation date.
- <!--PAYMENT_TIME_CREATED--> payment creation time.
- <!--PAYMENT_LOGIN--> client's login (account number).
- <!--PAYMENT_ACTION--> payment type: deposit or withdrawal.
- <!--PAYMENT_TYPE--> payment method: card, bank transfer, etc.
- <!--PAYMENT_USER_AMOUNT--> amount requested by the user in the deposit currency.
- <!--PAYMENT_USER_COMMISSION--> broker commission to be charged on the transaction in accordance with the wallet settings. Indicated in the deposit currency.
- <!--PAYMENT_USER_CURRENCY--> user deposit currency.
- <!--PAYMENT_WALLET_AMOUNT--> transaction amount on the payment system side.
- <!--PAYMENT_WALLET_COMMISSION--> payment system commission. The macro is reserved for future use. Currently, all supported providers withhold commission from the broker, so the value of this macro is always 0 for the user.
- <!--PAYMENT_WALLET_CURRENCY--> payment system currency.

Also supported in emails:

- General macros substituting user data.
- <!--SUBJECT=..--> email subject variable.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / Unlimit

Integration with Unlimit

Unlimit offers a wide range of digital payments services. Accept payments with any debit and credit cards, including Visa, Mastercard, Maestro, UnionPay, etc. Offer customers alternative payment systems, such as PayPal, Alipay and WebMoney. The system works with many currencies around the world. Unlimit provides extensive transaction control capabilities: event tracking, cash flow reports and much more.

To connect Unlimit payments, fill out a short [online form](#), after which their representative will contact you and will provide further instructions. After registration, you will receive system connection details.

Unlimit will create a wallet through which your payments will be processed. This wallet has:

- Number or terminal code
- Password
- Callback Secret a special password with which the payment system [signs its callbacks](#)

The wallet number is available in your account, under the Settings\Wallet settings section. It is indicated in the ID field. You receive the data you once when creating a wallet. If you lose or need to change the credentials, you should contact Unlimit support.

The screenshot shows the Unlimit user interface. At the top, there's a navigation bar with the Unlimit logo, a 'back to Dashboard' link, and tabs for 'PROFILE' and 'SETTINGS'. The 'SETTINGS' tab is active. On the right, a user profile dropdown menu is open, showing options: Profile, Settings, Help Center, Contact Support, and Logout. The main content area is titled 'Wallet settings' and contains a table with the following data:

ID	URL	METHOD	CURRENCIES
12345	broker.com	7eleven, BR001, abc, ac...	EUR
12345	broker.com	7eleven, BR001, abc, ac...	USD

On the left sidebar, there are links for 'Two-factor auth', 'Notification Settings', 'Wallet settings' (which is highlighted), 'Company account', 'Change password', and 'Language'.

MetaTrader 5 trading platform

Also, request from Unlimit to enable Payment page mode for your account. In this mode, all the details of the payment method (card, wallet, etc.) should be specified on a separate page on the provider's side. This is the procedure adopted in the MetaTrader 5 payment system. It is not possible to receive and store all payment method details on the platform side due to legal restrictions. This would require brokers to have a special license.

Create a payment gateway configuration, select Unlimit as the gateway, and then specify the wallet number in the Login field and the password:

Payment Wallet: Unlimit - Card

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: Unlimit - Card

Gateway: Unlimit Trade Main, 1

Type: Card

☒ Deposit ☒ Push notification

☒ Withdrawal ☒ Email notification

☒ Account creation

Login: 12345

Password: ••••••••••

OK Cancel Help

MetaTrader 5 trading platform

In the "Type" field, select the payment method you want to connect:

- Card payments
- Alipay Money Transfer
- UnionPay International
- Boleto
- WebMoney
- PayPal
- Direct Banking Nigeria
- PIX Brasil
- SEPA
- PicPay
- SPEI, Mexico
- CODI, Mexico
- Pago Efectivo, Peru/Ecuador


To use multiple payment methods in parallel, create separate wallet configurations. If you need additional payment methods, please contact our [support team](#).

System limits features

When creating a wallet for the Pago Efectivo payment method, be sure to specify only one currency, USD or PEN, depending on the country in which you will be accepting payments (Ecuador or Peru). If you need both currencies, create two separate wallets.

Setting up the environment

Unlimit supports operations in a [sandbox environment](#). In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox environment, contact Unlimit for a special wallet. When setting up this wallet in the platform, open the Parameters tab and enable the Sandbox option. This option must be disabled for wallets running in a live environment.



Setting up callbacks

Callbacks are used to quickly get transaction processing results. After each transaction, Unlimit sends its status to the URL address which you specify in the wallet settings. Accordingly, to enable the receipt of these notifications at the specified address in the platform, you should configure the platform accordingly.

The use of callbacks is optional. However, if you do not use them, updating payment statuses can take up to three minutes. This may reduce the quality of your customer service.

On the platform side, the callbacks are received and processed by access servers. To set up notifications:

1. Register a domain (or a subdomain for your existing domain). Unlimit will access the platform at this address. Also, endpoint addresses for callbacks will be formed relative to this address.
2. Associate the domain with the public address of one or more access servers. For further information please see [Integration\Web Services](#).
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. For the sandbox environment, you can use a self-signed certificate. The live environment requires a certificate issued by a trusted certification authority. Only the HTTPS protocol is allowed. HTTP is not supported.

4. Select the address for the endpoint where callbacks will be accepted. The address is specified relative to the previously selected domain, taking into account the following rules:

<https://broker.com/api/callback/payments/Unlimit>

- The first part is an example of a domain name.
- The second part is a predefined part of the address that is used for all callbacks related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
- The third part is defined by you. You can enter any address; however, we strongly recommend using a logical and clear naming system.

5. Add the selected address to the allow list in the Web Services section, and also specify the list of IP addresses from which notifications will be allowed. You can request the addresses from Unlimit.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on /api/callback/. The list is used for all access servers.

Callback domain:

Up

Down

Add


Edit

Delete

URL	Allowed IPv4/IPv6	Comment
✓ /api/callback/payments/unlimit	176.56.185.37,18.158.236.50,54.216.23.40	Unlimit payments callbacks

MetaTrader 5 trading platform

6. Specify the callbacks address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. The address is specified without a domain name.



Payment Wallet: Unlimit - Card

Common Currencies **Parameters** Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Parameter	Value
 Sandbox	
 Callback URL	/api/callback/payments/unlimit
 Callback Secret	1ap84IU 1n99

Add ▼

Edit

Delete

OK Cancel Help

7. Specify the callback address in the wallet settings in your Unlimit account. Click on the wallet ID in the [Settings\Wallet settings](#) and find the 'JSON callback URL' field. The address is specified along with the domain.

8. Return to the gateway settings in MetaTrader 5 and specify the password, which Unlimit uses to sign callbacks, in the Callback Secret parameter.

To protect callbacks from changes, Unlimit signs each callback with a special password. The full signature algorithm is described in the [documentation](#). The password is specified on the MetaTrader 5 platform side in order to verify signatures.

Customizing the payment page

Unlimit allows the customization of the page on which the user enters payment details. Design the page in accordance with your corporate style and add a logo. Such a customized appearance can increase customer trust.

To make the setup process more convenient, we have prepared a special style file that fits the payment page into the client terminal:

broker name

Order Number: MT5_1091

Total: **169.00 USD**

Card number*

400000...0085

Cardholder name *

JOHN SMITH

Expires*

12



2026



CVV2/CVC2/CAV2*



Pay Now

Cancel

Order details

Deposit

Deposit to account '2022'

Total amount: 169.00 USD

Unlimit

VISA



© 2009–2023 Unlimit

Download the file and submit it to Unlimit through your manager or technical support, indicating which wallet it should be applied to. Styles will need to be reviewed by Unlimit risk management.

You can use the styles file as is or use it as a basis for your own template. For example, you can add your own logo to the page header by completing the following steps:

- Uncomment the "#merchant-logo" and "#merchant-logo a" styles to enable the logo display
- Specify the logo size and required indents
- In the 'background: url("...")' parameter add a logo image in Base64 format

Example:

```
#merchant-logo {
  position: static;
  width: 100%;
  height: auto;
  text-align: left;
  margin-bottom: 12px;
}
```

```
#merchant-logo a {
  height: 32px;
  width: 120px;
  display: inline-block;
  background: url("data:image/png;base64,iVBORw0KGgoAAAANSUhEUgAAAPA...4fpsl2eS5");
  background-size: 120px 32px;
}
```

The logo will look like this:



broker name

Order Number: MT5_1091

Total: **169.00** USD

Card number*

400000...0085

Cardholder name *

JOHN SMITH

Order details

Deposit

Deposit amount: 169.00 USD

MetaTrader 5 trading platform

For further details about the payment page customization please read the [Unlimit documentation](#).

Other settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / ECOMMPAY

Integration with ECOMMPAY

ECOMMPAY is an international payment service provider and direct card acquirer for mid-sized & large e-commerce businesses. The single gateway allows companies to receive and process transactions through popular payment systems, including Visa, Mastercard, PayPal, Alipay, etc. ECOMMPAY also provides advanced payment protection and a flexible risk management system.


To connect ECOMMPAY payments, fill out a short [online form](#). Their representative will contact you and will provide further instructions. After registration, you will receive system connection details.

ECOMMPAY will create a project through which payments will be processed. This project has:

- ID
- Key

For further details please see the [ECOMMPAY documentation](#).

The project ID can be viewed in your account in the Project\Project Settings section. The key is provided to you once, when the project is created. If you lose or need to change your credentials, you should contact the ECOMMPAY support service.



Create a payment gateway configuration, select ECOMMMPAY as the gateway, and indicate connection details: project ID in the Login fields and the in the API key field:

MetaTrader 5 trading platform

Payment Wallet: ECOMMPAY - Card

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: ECOMMPAY - Card

Gateway: ECOMMPAY Trade Main, 1

Type: Card

☒ Deposit ☒ Push notification

☒ Withdrawal ☒ Email notification

☒ Account creation

Login: 113591

API key: 54x90aq9asx9tb7x1ws2s9ao93xb5ushkl10pos991lxh4678akxnpaixwenj313546sxjhroanxp

OK Cancel Help

In the "Type" field, select the payment method you want to connect:

- Card payments
- Skrill
- Neteller

To use multiple payment methods in parallel, create separate wallet configurations. If you need additional payment methods, please contact our [support team](#).

Select card verification type

For security purposes and to reduce regulatory requirements for the broker, users can withdraw funds only to previously linked cards. MetaTrader 5 provides a relevant procedure for adding a payment account. ECOMMPAY supports the procedure in two modes: card_verify and card_tokenize. The first one is more preferable as it allows 3DS authentication (with an additional payment authorization with a code or through a mobile application) and verification of card details. However, it is not supported for all ECOMMPAY customers. You should check with ECOMMPAY if this mode is available to you. If it is, enable the Verify New Cards option in the gateway settings.

MetaTrader 5 trading platform

Payment Wallet: ECOMMPAY - Card

CommonCurrenciesParametersCountriesGroupsCommissionsInformation

Up

Down

Add

Edit

Delete

Default

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Parameter	Value
ab Callback URL	https://broker.com/api/callback/payments/ecommpay
↗ Verify New Cards	☒
ab Redirect URL	https://broker.com/api/callback/payments/ecommp...

OK

Cancel

Help

1260

Upon successful deposit operations, the card is linked automatically. There is no need to preauthorize it.

Setting up callbacks

Callbacks are used to quickly get transaction processing results. After each operation, ECOMMPAY sends its status to a URL which you specify in the project settings. Accordingly, to enable the receipt of these notifications at the specified address in the platform, you should configure the platform accordingly.

For further details about callbacks on the ECOMMPAY side please visit the [documentation](#).

The use of callbacks is optional. However, if you do not them, updating payment statuses can take up to three minutes. This may reduce the quality of your customer service.

On the platform side, the callbacks are received and processed by access servers. To set up notifications:

1. Register a domain (or a subdomain for your existing domain). ECOMMPAY will access the platform at this address. Also, endpoint addresses for callbacks will be formed relative to this address.
2. Associate the domain with the [public address](#) of one or more access servers. For further information please see [Integration\Web Services](#).
3. [Add an SSL certificate](#) for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a test environment. Only the HTTPS protocol is allowed. HTTP is not supported.
4. Select the address for the endpoint where callbacks will be accepted. The address is specified relative to the previously selected domain, taking into account the following rules:

<https://broker.com/api/callback/payments/ecommpay>

- [The first part](#) is an example of a domain name.
 - [The second part](#) is a predefined part of the address that is used for all callbacks related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
 - [The third part](#) is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.
5. Add the selected address to the allow list in the Web Services section, and also specify the list of IP addresses from which notifications will be allowed. You can request the addresses from ECOMMPAY.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on /api/callback/. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
✓ /api/callback/payments/cryptochill	3.218.251.136,54.157.91.227	CryptoChill callback

Use port 443 to receive callbacks. ECOMMMPAY does not support other ports.

6. Specify the callbacks address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

MetaTrader 5 trading platform

Payment Wallet: ECOMMMPAY - Card

Common Currencies **Parameters** Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
ab Callback URL	https://broker.com/api/callback/payments/ecommpay
↗ Verify New Cards	☒
ab Redirect URL	https://broker.com/api/callback/payments/ecommp...

Add ▼

Edit

Delete

Default

OK Cancel Help

7. Open your ECOMMPAY personal account and go to the Callbacks section in the project. Using the 'Add new' command, create three callbacks with the following parameters:

- Payment type = all, Result type = all (except errors)
- Payment type = all, Result type = error
- Payment type = purchase, Result type = tokenize

In each of them, specify the same address in the 'URL for callbacks' field. The address is specified along with the domain.

The screenshot shows the ECOMMPAY Project Settings interface. On the left, a sidebar contains 'Project Settings' with a dropdown for 'Your projects' showing 'STAGE broker.com (12345)'. Below this are menu items: 'General', 'Payment methods', 'Callbacks' (highlighted), 'Redirect URLs', and 'Payment Page Design'. On the right, there is an 'Add new' button and a table of existing callbacks.

CALLBACK ID	URL	RESULT TYPE	PAYMENT TYPE
163151	https://broker...	all (except errors)	all
163161	https://broker...	error	all
			purchase

A red arrow points from the 'Add new' button to a modal window titled 'Add New Callback URL'. The modal contains the following fields:

- URL for callbacks:**
- Payment type:**
- Result type:**
- Payment method (Optional):** (with a help icon and dropdown arrow)

A 'Save' button is located at the bottom right of the modal.

Redirect URL

Typically, upon completing a payment on its page, the provider redirects the user back to the merchant's website. The provider allows specifying a predetermined redirection page.

In the case of payments in MetaTrader 5, this redirection page is the client terminal itself. Since the terminal does not have a public internet address, a special callback address must be configured within the platform. The provider will send requests to this address upon payment completion, and the platform will intercept these requests to automatically redirect the user to the appropriate page within the terminal.

Create a redirect address in the same way as you do for [callback requests](#). The address must be a subpath to the address for callback requests. For example, the callback address is

`https://broker.com/api/callback/payments/ecommpay`

Then the redirect address can be

`https://broker.com/api/callback/payments/ecommpay/payment-result`

The highlighted part can be anything.

Enter this address in the Redirect URL parameter in the payment gateway settings and inform your ECOMMPAY manager.

MetaTrader 5 trading platform

Payment Wallet: ECOMMPAY - Card

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
ab Callback URL	https://broker.com/api/callback/payments/ecommpay
↗ Verify New Cards	☒
ab Redirect URL	https://broker.com/api/callback/payments/ecommp...

Add ▼

Edit

Delete

Default

OK Cancel Help

The Redirect URL must be a subpath of the Callback URL.

Account configuration

For merchants operating in the Forex and cryptocurrency trading sectors, VISA imposes additional requirements. When processing payment transactions, they must provide not only the customer's full name (entered by the user when specifying card details) but also their address. The ECOMMPAY module supports this requirement and automatically fills in the necessary details based on the information from the trading account:

The screenshot shows the 'Client Properties' window in the MetaTrader 5 trading platform. The window title is 'Account: 3481888, Sau Metz, USD, 1:100, Hedge'. The 'Personal' tab is selected, showing various fields for account configuration. The fields are organized into sections: Name (First, Last, Middle), Company, Registered date/time, Language, Status, ID number, Lead campaign, MetaQuotes ID, Lead source, Email, Phone, Country, State, City, Zip code, Address, and Comment. The 'Country' field is set to 'Austria', 'City' to 'Vienna', and 'Address' to 'Lichtenfelsgasse 2'. The 'Update' button is highlighted with a blue border.

Field	Value
Name	Sau
Last name	Metz
Middle name	
Company	
Registered	2025.02.03 16:50:43
Language	
Status	
ID number	
Lead campaign	
MetaQuotes ID	
Lead source	
Email	sau.metz@gmail.com
Phone	+27664532687
Country	Austria
State	
City	Vienna
Zip code	
Address	Lichtenfelsgasse 2
Comment	

MetaTrader 5 trading platform

To ensure successful payment processing, the following fields must be completed in the account: Country, City, and Address. The State field is required only for U.S. citizens and must specify the state of residence.

Other settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / APS

Advanced Payment Solutions

[Advanced Payment Solutions \(APS\)](#) empowers businesses globally with online and corporate payment solutions. With APS, you can access multiple payment solutions for your clients worldwide, streamlining administrative processes and saving operational costs. The system supports card payments in more than 50 countries, as well as digital currency transactions and [Binance Pay](#) payments.

To connect APS payments, click 'Connect Provider' in the [showcase](#) and fill out a short online form. The company representative will contact you and will provide further instructions. After registration, you will receive system connection details:

- Merchant GUID
- Secret Key
- App Token
- App Secret

APS creates separate accounts to work with [Binance Pay](#) and card payments. Each account has individual connection data.

Create a [payment gateway configuration](#), select APS for the gateway, and specify 'App token' in the 'API Key' field:

MetaTrader 5 trading platform

Payment Wallet: APS

Common Currencies Parameters Countries Groups Commissions Information

 Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name:

Gateway:  APS  Trade Main, 1

Type:  Card

☒ Deposit ☒ Push notification
☒ Withdrawal ☒ Email notification
☐ Account creation ☐ SMS notification

 API key:

OK Cancel Help

MetaTrader 5 trading platform

In the 'Type' field, select a payment method you wish to connect:

- Card
- Binance Pay
- OVO, Dana, LinkAja, QRIS (Indonesia)
- FPX, Boost, DuitNow (Malaysia)
- PromptPay (Thailand)
- Viet QR, Momo, ViettelPay, ZaloPay (Vietnam)

If you want to use several payment methods, create separate wallet configurations.

Go to the 'Parameters' tab and specify Merchant GUID, Secret Key and App Secret:

Payment Wallet: APS

Common Currencies Parameters Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up Down

Parameter	Value
↗ Sandbox	☐
ab Callback URL	https://broker.com:443/api/callback/payments/aps
ab Merchant GUID	98po2-8pio-9781-a8c5-15b7aa4be92c
ab API Secret	47893a31599645277g189cd9986ef48993b7h4e97...
ab Secret Key	LyKas24Jh

Add Edit Delete Default

OK Cancel Help

System limits

Clients use their Binance ID to make transactions through Binance Pay. The system does not disclose this identifier. In the transaction statuses on the MetaTrader 5 side, traders and managers will see Binance Pay ID, which is a different identifier. It does not match the Binance ID.

Setting up the environment

APS supports operations in a sandbox environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox environment, contact APS for a special wallet. When setting up this wallet in the platform, open the Parameters tab and enable the Sandbox option. This option must be disabled for wallets running in a live environment.

Payment Wallet: APS

Common

Currencies

Parameters

Countries

Groups

Commissions

Information

Up

Down

Add

Edit

Delete

Default

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Parameter	Value
Sandbox	☐
Callback URL	https://broker.com:443/api/callback/payments/aps
Merchant GUID	98po2-8pio-9781-a8c5-15b7aa4be92c
API Secret	47893a31599645277g189cd9986ef48993b7h4e97...
Secret Key	LyKas24Jh

OK

Cancel

Help

You can verify the Binance Pay operation in test environment only using real Binance accounts. There are no test accounts.

Currency settings

APS supports payments for a certain list of currencies. Request from the provider a list of available currencies and explicitly specify currencies in the wallet settings. In addition, you will need to set a limit on transaction amounts in accordance with APS requirements.

Payment Wallet: APS

Common Currencies Parameters Countries Groups Commissions Information

Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
USD	5.00	1 000.00	1.00	5 000.00
+ click to add...				

Add Edit Delete

OK Cancel Help

Setting up callback requests

Callbacks are used to quickly get transaction processing results. In each transaction, the platform transmits a special URL to which APS should send the processing result. To ensure proper generation of the addresses, you need to configure the platform accordingly.

The use of callback requests is mandatory. Withdrawal operations do not work correctly without callbacks. Also, without callbacks, Binance Pay ID will not be provided to the platform in operation details.

On the platform side, the callbacks are received and processed by access servers. To set up notifications:

1. Register a domain (or a subdomain for your existing domain). APS will access the platform at this address. Also, endpoint addresses for callbacks will be formed relative to this address.
2. Associate the domain with the public IPv4 address of one or more access servers. For further information please see Integration\Web Services. Please note that only IPv4 addresses are supported. Therefore, the domain must be associated with exactly such an address.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Only the HTTPS protocol is allowed. HTTP is not supported.
4. Select the address for the endpoint where callbacks will be accepted. The address is specified relative to the previously selected domain, taking into account the following rules

<https://broker.com/api/callback/payments/aps>

- The first part is an example of a domain name.
- The second part is a predefined part of the address that is used for all callbacks related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
- The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.

Use different addresses for Callback requests if you create multiple APS wallet configurations.

5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. You can obtain the address list from APS.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on `/api/callback/`. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
 <code>/api/callback/payments/aps</code>	<code>3.72.123.235,18.193.94.157</code>	APS payments callbacks

Use port 443 to receive callbacks. APS does not support other ports.

6. Specify the callbacks address in the 'Callback URL' parameter in the payment gateway settings. This address will be sent to APS in every transaction. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

MetaTrader 5 trading platform

Payment Wallet: APS

CommonCurrenciesParametersCountriesGroupsCommissionsInformation



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add ▼

Edit

Delete

Default

Parameter	Value
 Sandbox	
 Callback URL	https://broker.com:443/api/callback/payments/aps
 Merchant GUID	98po2-8pio-9781-a8c5-15b7aa4be92c
 API Secret	47893a31599645277g189cd9986ef48993b7h4e97...
 Secret Key	LyKas24Jh

OK

Cancel

Help

Other settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details please visit the [Payment Gateways](#) section.


[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / AstroPay

AstroPay

[AstroPay](#) allows deposits and withdrawals directly using their AstroPay wallets. If the user does not have a wallet, the provider will transparently assist in paying/receiving money in any available way. In addition, AstroPay enables direct utilization of the Brazilian PIX money transfer system.

To connect AstroPay payments, click 'Connect Provider' in the [showcase](#) and fill out a short online form. The company representative will contact you and will provide further instructions. Upon entering into the agreement, [a merchant panel](#) will be created for you. It will contain the necessary details for connecting the platform to the provider.

Open 'Credentials \ API Key' and click 'Generate API Key':



The screenshot displays the AstroPay Merchant API Key management interface. The sidebar on the left contains the following navigation items: Dashboard, Transactions, Settlements, Balance Report, Payment Methods, Users, Credentials, API Key (highlighted), Backend API Key, and SDK API Key. The main panel is titled 'Merchant API Key' and features two buttons at the top: 'Generate New API Key' and 'Send Secret Key By Email'. Below these buttons is a table with two columns: 'API Key' and 'Actions'.

API Key	Actions
xgdgZWoIyrN0uB7B5xzCR4TiCNwSdLxgdgZhZ2dFbG1PyIz6eLFbG1PyIYVFUGRK	

MetaTrader 5 trading platform

Next click 'Send Secret By Email' to receive the 'Secret Key' parameter to the email address registered in your merchant panel.

Create a payment gateway configuration, select AstroPay for the gateway, and specify the previously received App Key in the 'API Key' field:

Payment Wallet: AstroPay

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: AstroPay

Gateway: AstroPay Trade Main, 1

Type: AstroPay

☒ Deposit ☒ Push notification

☒ Withdrawal ☒ Email notification


☐ Account creation ☒ SMS notification

API key: xgdgZWoirN0uB7B5xzCR4TICNwSdkxgdgZhZ2dFbG1PyIz6eLFbG1PyIYVFUGRK

OK Cancel Help

MetaTrader 5 trading platform

In the 'Type' field, select AstroPay or PIX Brasil depending on which payment method you wish to connect. If you want to use both payment methods, create two separate wallet configurations. Go to the Parameters tab and specify Secret key from the email:



Payment Wallet: AstroPay

Common Currencies **Parameters** Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up Down

Parameter	Value
 Sandbox	
ab Callback URL	https://broker.com/api/callback/payments/astropay
ab Secret Key	PAHXXLUIINLEFDLKTVVYWG3JO62YHB3GH
ab MCC	6211

Add ▼

Edit

Delete

Default

OK Cancel Help

MetaTrader 5 trading platform

The MCC (Merchant category code) parameter is used to include information about the type of provided services. The default value is '6122 Security Brokers and dealers'. Typically there is no need to change it.

System limits

The payment system has the following limits:

- One MetaTrader 5 account can use no more than two AstroPay wallets. If the limit is exceeded, a corresponding error will be displayed on the payment page which opens in client terminals.
- One AstroPay wallet can be used on no more than two MetaTrader 5 accounts. If the limit is exceeded, a corresponding error will be displayed on the payment page which opens in client terminals.
- Refund operations through the platform are not supported for payments via PIX.
- Payments through PIX are only made in Brazilian reais.

Setting up the environment

Upon connection to the system, you start working in a sandbox environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. For the sandbox environment, you should log into your account using a separate link: <https://merchants-stg.astropay.com>. To configure a wallet for sandbox operations, use API Key and Secret Key from the sandbox account and enable the "Sandbox" parameter in the wallet settings on the MetaTrader 5 side:

MetaTrader 5 trading platform

Payment Wallet: AstroPay

CommonCurrenciesParametersCountriesGroupsCommissionsInformation



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add ▼

Edit

Delete

Default

Parameter	Value
 Sandbox	
 Callback URL	https://broker.com/api/callback/payments/astropay
 Secret Key	PAHXXKLUIINLEFDLKTVVYWG3JO62YHB3GH
 MCC	6211

OK

Cancel


Help

MetaTrader 5 trading platform

To switch to the live operating mode, disable this option and replace the API Key and Secret Key with those available in the provider's main account at <https://merchants.astropay.com/>.

Currency settings

AstroPay supports payments for a certain list of currencies. Request from the provider a list of available currencies and explicitly specify currencies in the wallet settings. In addition, you will need to set a limit on transaction amounts in accordance with AstroPay requirements.



Payment Wallet: AstroPay

Common Currencies Parameters Countries Groups Commissions Information

Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
\$ BRL	0.00	unlimited	0.00	unlimited
+ click to add...				

Add Edit Delete

OK Cancel Help

When setting up payments through the PIX system, specify only Brazilian Real (BRL) as the available currency.

Setting up callback requests

Callbacks are used to quickly get transaction processing results. In each transaction, the platform transmits a special URL to which AstroPay should send the processing result. To ensure proper generation of the addresses, you need to configure the platform accordingly.

The use of callback requests is mandatory. The module does not work correctly without callbacks:

- PIX payments may transition to a successful state after some time following their cancellation or expiration. Without properly functioning callbacks, the platform will be unable to receive the updated status of the operation.
- Refunds to AstroPay wallets through the platform will not be possible since the information needed for the refund (user identifier) is only provided in callbacks.

On the platform side, the callbacks are received and processed by access servers. To set up notifications:

1. Register a domain (or a subdomain for your existing domain). AstroPay will access the platform at this address. Also, endpoints for callbacks will be formed relative to this address.
2. Associate the domain with the public IPv4 address of one or more access servers. For further information please see Integration\Web Services. Please note that only IPv4 addresses are supported. Therefore, the domain must be associated with exactly such an address.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Only the HTTPS protocol is allowed. HTTP is not supported.
4. Select the address for the endpoint where callbacks will be accepted. The address is specified relative to the previously selected domain, taking into account the following rules

<https://broker.com/api/callback/payments/astropay>

- The first part is an example of a domain name.
- The second part is a predefined part of the address that is used for all callbacks related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
- The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.

5. Add the selected address to the allow list in the Web Services section, and also specify the list of IP addresses from which notifications will be allowed. You can request the addresses from AstroPay.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on /api/callback/. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
✓ /api/callback/payments/astropay	18.213.74.167, 3.225.39.22, 3.215.18.6	AstroPay payments callbacks

6. Specify the callbacks address in the 'Callback URL' parameter in the payment gateway settings. This address will be sent to AstroPay in every transaction. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

MetaTrader 5 trading platform

Payment Wallet: AstroPay

CommonCurrenciesParametersCountriesGroupsCommissionsInformation

Up

Down

Add ▼

Edit

Delete

Default

Parameter	Value
 Sandbox	
 Callback URL	https://broker.com/api/callback/payments/astropay
 Secret Key	PAHXXKLUIINLEFDLKTVVYWG3JO62YHB3GH
 MCC	6211

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

OK

Cancel

Help

Other settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / EU Paymentz

EU Paymentz

With [EU Paymentz](#), users can replenish their accounts using bank cards, as well as deposit and withdraw funds using local interbank transfers (EFT, Electronic Fund Transfer), including transactions in African countries.

To connect EU Paymentz payments, click 'Connect Provider' in the [showcase](#) and fill out a short online form. You can also use the registration form on the [provider's website](#). The company representative will contact you and will provide further instructions. EU Paymentz provides three types of accounts:

- CC sent - Direct and 3DS Response: implies that the broker (merchant) will collect and send card data. This option requires special licenses and compliance with the PCI DSS standard, so it is not implemented in MetaTrader 5.
- No CC sent - Hosted: payments are made using banking card, and data is entered on the PSP's page.
- No CC sent - Direct: payments are made using other methods, in particular local interbank transfers.

The last two accounts can be connected to the platform. You can request one or both, depending on your needs.

Upon finalizing the agreement with the payment provider, you will receive the necessary details to connect to the system, including the account id, password and passphrase.

Create a [payment gateway configuration](#), select EU Paymentz for the gateway, and enter the data received previously

- account id in the 'Login' field
- password in the 'Password' field
- passphrase in the 'API Key' field

MetaTrader 5 trading platform

Payment Wallet: EU Paymentz - Card

Common Currencies Parameters Countries Groups Commissions Information

 Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name:

Gateway:  EU Paymentz  Trade Main, 1

Type:  Card

☒ Deposit ☒ Push notification
☐ Withdrawal ☒ Email notification
☐ Account creation ☒ SMS notification

Login:

Password:

API key:

OK Cancel Help

MetaTrader 5 trading platform

In the 'Type' field, select 'Card' or 'Bank transfer' depending on which payment method you wish to connect. If you want to use both payment methods, create two separate wallet configurations.

System limits features

The payment system has the following features:

- Only deposit transactions are supported for card payments.
- EFT (Electronic Fund Transfer) payments can be used for deposits and withdrawals.
- Payment is not possible if the client is connected to the platform access server from the local network. Please take this into account when testing the system.
- EFT payments combine multiple payment methods. When performing a transaction, the user is asked to enter the bank account number, bank code, and bank name. The account number is always required; the need to fill out other parameters depends on the specific payment method.

Setting up the environment

EU Paymentz supports operations in a test (sandbox) environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox environment, contact EU Paymentz for a special wallet. When setting up this wallet in the platform, open the Parameters tab and enable the Sandbox option. This option must be disabled for wallets running in a live environment.

MetaTrader 5 trading platform

Payment Wallet: EU Paymentz - Card

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
 Sandbox	☒
ab Callback URL	https://broker.com/api/callback/payments/eupaym...

Add ▼

Edit

Delete

Default

OK Cancel Help

Currency settings

EU Paymentz supports payments for a certain list of currencies. Request from the provider a list of available currencies and explicitly specify currencies in the wallet settings. In addition, you will need to set a limit on transaction amounts in accordance with EU Paymentz requirements.

Payment Wallet: EU Paymentz - Card

Common Currencies Parameters Countries Groups Commissions Information

 Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
 USD	0.00	unlimited	0.00	unlimited
+ click to add...				

Add

Edit

Delete

OK Cancel Help

Setting up callback requests

Callbacks are used to quickly get transaction processing results. In each transaction, the platform transmits a special URL to which EU Paymentz should send the processing result. To ensure proper generation of the addresses, you need to configure the platform accordingly.

The use of callbacks is optional. However, if you do not them, updating payment statuses can take up to three minutes. This may reduce the quality of your customer service.

On the platform side, the callbacks are received and processed by access servers. To set up notifications:

1. Register a domain (or a subdomain for your existing domain). EU Paymentz will access the platform at this address. Also, address of the endpoint for callbacks will be formed relative to this address.
2. Associate the domain with the public IPv4 address of one or more access servers. For further information please see Integration\Web Services. Please note that only IPv4 addresses are supported. Therefore, the domain must be associated with exactly such an address.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Only the HTTPS protocol is allowed. HTTP is not supported.
4. Select the address for the endpoint where callbacks will be accepted. The address is specified relative to the previously selected domain, taking into account the following rules

<https://broker.com/api/callback/payments/eupaymentz>

- The first part is an example of a domain name.
 - The second part is a predefined part of the address that is used for all callbacks related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
 - The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.
5. Add the selected address to the allow list in the Web Services section, and also specify the list of IP addresses from which notifications will be allowed. You can request the addresses from EU Paymentz.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on /api/callback/. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
✓ /api/callback/payments/eupaymentz	10.15.26.79,15.125.67.3	EU paymentz callbacks

6. Specify the callbacks address in the 'Callback URL' parameter in the payment gateway settings. This address will be sent to EU Paymentz in every transaction. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

Payment Wallet: EU Paymentz - Card

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add ▼

Edit

Delete

Default

Parameter	Value
↕ Sandbox	☒
ab Callback URL	https://broker.com/api/callback/payments/eupaym...

OK Cancel Help

Other settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details please visit the [Payment Gateways](#) section.

MetaTrader 5 Trading Platform / Platform Setup / Payments / Payment Gateways / Kora

Kora

Kora is a Pan-African payment infrastructure offering payment solutions in Nigeria, Kenya and Ghana. With this integration, you can provide the possibility for your traders to top up accounts using cards and bank transfers. In addition, the system provides mobile payment options for Kenya and Ghana.

To connect Kora payments, click 'Connect Provider' in the showcase and fill out a short online form. You can also use the registration form on the provider's website. The company representative will contact you and will provide further instructions. Using the created credential, go to your merchant account, navigate to Account \ Settings \ API Configuration and copy 'Secret Key' provided in this section.

The screenshot displays the 'API Configuration' page of the 'ABC Broker' interface. The left sidebar contains navigation links for Home, Balances, TOOLS (Payment Links, Virtual Accounts, Bulk Payouts), TRANSACTIONS (Pay-ins, Payouts, Disputes, Settlements), and ACCOUNT (Audit Logs, Settings, Support, Documentation). The 'Settings' link is highlighted with a red arrow. The main content area is titled 'API Configuration' and includes tabs for General, Compliance, Settlements, API Configuration (selected), Team, and Security. Sub-tabs under API Configuration include Payment Preferences, Checkout Appearance, and Notifications. The 'Korapay APIs' section explains that Korapay authenticates API requests using account API keys, noting that test mode keys differ from live mode keys. It provides links to 'Generate new API Keys' and 'See our documentation'. Below this, the 'API Keys' section shows a table with two rows: 'Public Key' (pk_test_SJhw*****B8R) and 'Secret Key' (sk_test_6D3Q*****EKO). A red arrow points from the 'Secret Key' in the table to the 'Secret Key' label in the 'API Keys' section. The 'Encryption' section at the bottom shows an 'Encryption Key' (POLJuiDUfnG*****). A 'Generate new Encryption Key' link is also present.

MetaTrader 5 trading platform

Create a payment gateway configuration, select Kora for the gateway, and specify the previously received Secret Key in the 'API Key' field:

Payment Wallet: Korapay Card

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: Korapay Card

Gateway: Kora Trade Main, 1

Type: Card

☒ Deposit ☒ Push notification

☐ Withdrawal ☒ Email notification

☐ Account creation ☒ SMS notification

API key: sk_test_6D3QioW79K28vfaQg2ssop3KGYrzGY4SfWirbpEko

OK Cancel Help

MetaTrader 5 trading platform

In the "Type" field, select "Card", "Mobile Money" or "Bank Transfer" depending on which payment method you connect. If you want to use multiple payment methods, create separate wallet configurations.

System limits features

The payment system has the following features:

- For card payments, only transactions in NGN and KES currencies are supported.
- Deposit transactions via bank transfers are only possible in NGN. Withdrawals to bank cards are available in KES and NGN.
- Mobile payments are only available in the KES and GHS currencies.
- For payments via Mobile Money, the user must indicate a telephone number, which must consist of 12 digits, including the country code. For example, 254700000000.

Setting up the environment

Kora supports operations in a sandbox environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. You can switch between these modes in your personal account. To configure a wallet for sandbox operations, enable the "Sandbox" parameter in the wallet settings on the MetaTrader 5 side:

MetaTrader 5 trading platform

Payment Wallet: Korapay Card

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
 Sandbox	
 Callback URL	https://broker.com/api/callback/payments/kora

Add ▼

Edit

Delete


Default

OK Cancel Help

Currency settings

Kora supports payments for a certain list of currencies. You should explicitly specify the required currencies in the wallet settings. In addition, you will need to set a limit on transaction amounts in accordance with Kora requirements and your company policies.

When configuring payments via Mobile Money with the possibility of withdrawal operations, you can select only one of the currencies supported for this method: KES or GHS. To set up payments in both currencies, create two separate gateway configurations. Similar restrictions apply when configuring withdrawals via Wire Transfer. In this case, specify either the KES or NGN currency. If you only enable deposit transactions, this limitation can be ignored.



Payment Wallet: Korapay Card

Common Currencies Parameters Countries Groups Commissions Information

Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
NGN	100 000.00	15 000 000.00	0.00	unlimited
+ click to add...				

Add Edit Delete

OK Cancel Help

Setting up callback requests

Callbacks are used to quickly get transaction processing results. In each transaction, the platform transmits a special URL to which Kora should send the processing result. To ensure proper generation of the addresses, you need to configure the platform accordingly.

The use of callbacks is optional. However, if you do not them, updating payment statuses can take up to three minutes. This may reduce the quality of your customer service.

On the platform side, the callbacks are received and processed by access servers. To set up notifications:

1. Register a domain (or a subdomain for your existing domain). Kora will access the platform at this address. Also, endpoints for callbacks will be formed relative to this address.
2. Associate the domain with the public IPv4 address of one or more access servers. For further information please see Integration\Web Services. Please note that only IPv4 addresses are supported. Therefore, the domain must be associated with exactly such an address.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Only the HTTPS protocol is allowed. HTTP is not supported.
4. Select the address for the endpoint where callbacks will be accepted. The address is specified relative to the previously selected domain, taking into account the following rules

<https://broker.com/api/callback/payments/kora>

- The first part is an example of a domain name.
 - The second part is a predefined part of the address that is used for all callbacks related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
 - The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.
5. Add the selected address to the allow list in the Web Services section, and also specify the list of IP addresses from which notifications will be allowed. You can request the addresses from Kora.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on /api/callback/. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
✓ /api/callback/payments/kora	10.15.26.79,15.125.67.3	Kora payments callbacks

6. Specify the callbacks address in the 'Callback URL' parameter in the payment gateway settings. This address will be sent to Kora in every transaction. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

Payment Wallet: Korapay Card

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add ▼

Edit

Delete

Default

Parameter	Value
↕ Sandbox	☐
ab Callback URL	https://broker.com/api/callback/payments/kora

OK Cancel Help

Other settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / [emerchantpay](#)

emerchantpay

[emerchantpay](#) is a leading global payment service provider and acquirer for online, mobile, in-store and over the phone payments. By connecting emerchantpay, you will receive a wide choice of payment methods: cards, e-wallets (Google Pay and Apple Pay), real-time bank transfers and many others. By providing more payment options, you will increase deposit conversion and pave the way for entering new markets.

To connect emerchantpay payments, click Connect Provider in the [showcase](#) and fill out a short online form. You can also use the registration form on the [provider's website](#). The company representative will contact you and will provide further instructions.

After registration, you will be given access to your personal account, where you can manage transactions. Also, the company manager will provide you with a special login and password for working via the API. They are required to connect to the provider in MetaTrader 5. Also, ask emerchantpay to allow Credit transactions for your account. They are required for withdrawal operations.

Create a [payment gateway configuration](#), select emerchantpay for the gateway and specify the API login and password:

MetaTrader 5 trading platform

Payment Wallet: emerchantpay - Card

Common Currencies Parameters Countries Groups Commissions Information

 Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name:

Gateway:  emerchantpay  Trade Main, 1

Type:  Card

☒ Deposit ☒ Push notification

☒ Withdrawal ☒ Email notification

☒ Account creation ☒ SMS notification

Login:

Password:

OK Cancel Help

MetaTrader 5 trading platform

In the Type field, select a payment method you wish to connect:

- Card
- Google Pay
- Apple Pay
- MultiBanco
- P24
- Blik
- EPS
- Giropay
- MyBank
- PayU

If you want to use multiple payment methods, create separate wallet configurations.

System features and limitations

The payment system has the following features:

- Withdrawal operations are only available for cards.
- When linking a card, the currency data is saved in the created payment account. This means the funds can be withdrawn to a saved card only in the currency the user selected when linking (when replenishing or adding the card). To withdraw funds to the same card in a different currency, you need to add it again with the desired currency.
- To withdraw funds to a card, you should first add/authorize it.
- Refund operations are supported by all payment methods except Multibanco.

emerchantpay can store customers' payment methods on its side. This is a separate list in no way related to cards/wallets saved on the MetaTrader 5 side. The client and all of his or her payment methods in emerchantpay are linked to an email address. When sending a payment request, MetaTrader 5 transmits to emerchantpay the email address specified in a user account. Based on that data, emerchantpay displays the saved payment methods in the payment dialog:

Payment method

☒ Card



VISA

Saved cards

Add new card



VISA **** 1111



**** 4444



CVC

Billing address

Address 1*

e.g. 123 Main St.

City*

e.g. London

Postcode*

e.g. SE1 9BG

Country*

Select country



Pay \$ 1.00

[← Back](#)

Therefore, it is extremely important that email addresses in user accounts are correct and verified.

Setting up the environment

emerchantpay supports operations in a test (staging) environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the staging environment, contact emerchantpay for a special wallet. You will receive a separate login and password. To work in the test environment, enable the Sandbox option on the Options tab of the gateway settings. This option must be disabled for wallets running in a live environment.

Payment Wallet: emerchantpay - Card

Common Currencies Parameters Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up Down

Parameter	Value
 Sandbox	☐
ab Callback URL	https://broker.com:443/api/callback/payments/emerchantpay

Add Edit Delete Default

OK Cancel Help

Currency settings

emerchantpay supports payments in a variety of currencies. Request a list of available currencies for each payment method from the provider and explicitly specify currencies in the wallet settings. Also, set a limit on transaction amounts in accordance with emerchantpay requirements.

Payment Wallet: emerchantpay - Card

Common Currencies Parameters Countries Groups Commissions Information

 Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
 USD	5.00	5 000.00	10.00	1 000.00
+ click to add...				

Add

Edit

Delete

OK Cancel Help

Setting up callback requests

Callback requests are used to quickly receive transaction processing results. In each transaction, the platform transmits a special URL, to which emerchantpay should send the processing result. To ensure proper generation of the addresses, you need to configure the platform accordingly.

The use of callbacks is optional. However, if you do not configure them, updating payment statuses may take longer. This may reduce the quality of your customer service.

On the platform side, the callbacks are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). emerchantpay will use this address to communicate with the platform, and the endpoint address for callback requests will be formed relative to it.
2. Associate the domain with the public IP address of one or more access servers. For further information, please see Integration\Web Services.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules

<https://broker.com/api/callback/payments/emerchantpay>

- The first part is an example of a domain name.
 - The second part is a predefined part of the address that is used for all callbacks related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
 - The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.
5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. You can obtain the address list from emerchantpay.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on /api/callback/. The list is used for all access servers.

Callback domain:

Up
Down
Add
Edit
Delete

URL	Allowed IPv4/IPv6	Comment
✓ /api/callback/payments/emerchantpay	3.72.123.235,18.193.94.157	emerchantpay payments callbacks

6. Specify the callback address in the Callback URL parameter in the payment gateway settings. This address will be sent to emerchantpay in every transaction. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

Payment Wallet: emerchantpay - Card

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up
Down

Parameter	Value
↕ Sandbox	☐
ab Callback URL	https://broker.com:443/api/callback/payments/emerchantpay

Add
Edit
Delete
Default

OK Cancel Help

Other settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / Pay.com


Pay.com

[Pay.com](#) is a comprehensive provider that simplifies the process of accepting online payments through cards, Google Pay, Apple Pay and PayPal. The provider supports 100+ currencies and 200+ countries, and uses special technology to prevent the most common reasons for rejected transactions.

To connect Pay.com payments, click 'Connect Provider' in the [showcase](#) and fill out a short online form. You can also use the registration form on the [provider's website](#). The company representative will contact you and will provide further instructions.

After registration, you will be given access to your personal account, where you can manage transactions, and a unique Merchant ID. Additionally, request from Pay.com to enable withdrawal transactions operations for your account, as they may not be available.

Open the 'Developers' section in your personal account and copy the API key. You will need it to set up payments in MetaTrader 5. If there is no key, create it by clicking 'Create API Key'.



MetaTrader 5 trading platform

Create a payment gateway configuration, select Pay.com for the gateway and specify the API login and password:

Payment Wallet: Paycom - Card

Common Currencies Parameters Countries Groups Commissions Information

 Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: Paycom - Card

Gateway: Pay. Pay.com Trade Main, 1

Type: Card

☒ Deposit ☒ Push notification

☒ Withdrawal ☒ Email notification

☒ Account creation ☐ SMS notification

API key: staging_spx91yrMqnrpagfb783zdghGbNSpIZG4UG

OK Cancel Help

MetaTrader 5 trading platform

In the 'Type' field, select a payment method you wish to connect:

- Card payments, including support for Google Pay and Apple Pay
- PayPal

If you want to use multiple payment methods, create separate wallet configurations.

Go to 'Parameters' and enter your Merchant ID received from Pay.com:

Payment Wallet: Paycom - Card

Common Currencies **Parameters** Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up
Down

Parameter	Value
Sandbox	
Merchant ID	1799331186314
Webhook Secret	18oit4mx-p97j-3rg7-q98c-hff90llaa
Webhook Address	/api/callback/payments/paycom

Add ▼
Edit
Delete
Default

OK Cancel Help


MetaTrader 5 trading platform

System features and limitations

Users can only withdraw funds via PayPal to the same wallets that they have previously used to deposit funds. A payment account will be created only in this case. There is no separate procedure for linking a wallet.

Setting up the environment

Pay.com supports operations in a sandbox environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox environment, contact Pay.com for a special wallet. You will receive a separate test account. Copy the API key from it and paste it to the appropriate field in the wallet settings in MetaTrader 5. Also enable the 'Sandbox' option on the Parameters tab of the gateway settings. This option must be disabled for wallets running in a live environment.



Payment Wallet: Paycom - Card

Common Currencies Parameters Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up Down

Parameter	Value
 Sandbox	☒
ab Merchant ID	1799331186314
ab Webhook Secret	18oit4mx-p97j-3rg7-q98c-hff90llaa
ab Webhook Address	/api/callback/payments/paycom

Add Edit Delete Default

OK Cancel Help

Due to system limitations, PayPal withdrawals are not supported in the sandbox environment.

Currency settings

Pay.com supports payments in a variety of currencies. Request a list of available currencies for each payment method from the provider and explicitly specify currencies in the wallet settings. Also, set a limit on transaction amounts in accordance with Pay.com requirements.

Payment Wallet: Paycom - Card

Common Currencies Parameters Countries Groups Commissions Information

Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
USD	5.00	5 000.00	10.00	1 000.00
+ click to add...				

Add Edit Delete

OK Cancel Help

Setting up callback requests

Callback requests are used to quickly receive transaction processing results. After each transaction, Pay.com sends its status to the URL address which you specify in the wallet settings. Therefore, to ensure the platform receives these notifications at the specified address, it must be configured accordingly.

The use of callback requests is optional. However, if you do not configure them, payment status updates may take longer. This could negatively impact the quality of your customer service.

On the platform side, the callback requests are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). Pay.com will use this address to communicate with the platform, and the endpoint address for callback requests will be formed relative to it.
2. Associate the domain with the public IP address of one or more access servers. For further information, please see Integration\Web Services.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules

<https://broker.com/api/callback/payments/paycom>

- The first part is an example of a domain name.
 - The second part is a predefined part of the address that is used for all callbacks related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
 - The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.
5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. You can obtain the address list from Pay.com.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on `/api/callback/`. The list is used for all access servers.

Callback domain:

Up	URL	Allowed IPv4/IPv6	Comment
Down	✓ <code>/api/callback/payments/paycom</code>	34.247.41.30, 34.252.201.149	Pay.com payments callbacks
Add			
Edit			
Delete			

6. Specify the callback address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. The address is specified without a domain name.

Payment Wallet: Paycom - Card

Common

Currencies

Parameters

Countries

Groups

Commissions

Information



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
↗ Sandbox	☐
ab Merchant ID	1799331186314
ab Webhook Secret	18oit4mx-p97j-3rg7-q98c-hff90llaa
ab Webhook Address	/api/callback/payments/paycom

Add ▼

Edit

Delete


Default

OK

Cancel

Help

7. Specify the address for callbacks in your Pay.com account Open 'Developers\ Webhooks' and click 'Add Webhook':



Configure the webhook parameters:

- Webhook Name an arbitrary name
- Endpoint URL the address for sending webhooks in accordance with the configurations specified in steps 5 and 6. The address should be specified with the domain included.

Next, select the events that will be sent through this webhook:

- payment_session.completed
- payment_session.failed
- setup_session.completed
- setup_session.failed
- payout.succeeded
- payout.failed

Webhook Management

[Save Changes](#)

Add Endpoint

Create a new webhook here for your chosen events.

Webhook Name

MetaTrader 5

Endpoint URL

https://broker.com/api/callback/payments/paycom

Events to send

Select below the events you want your endpoint to listen to.

☒ Select all

Payment Session 2

☐ Select all

☐ payment_session.open

The payment session was created in the system, but no action has been taken.

☒ payment_session.completed

The payment session was completed and approved and a payment method was successfully attached, a Charge or a Hold is created based on the payment session params.

☒ payment_session.failed

The payment session failed.

Setup Session 2



MetaTrader 5 trading platform

Save your changes. Return to the list of webhooks and click on the newly created webhook to open its settings.

To protect notifications from changes, Pay.com signs each callback request with a special password, which is specified in the 'Secret' field. Copy it into the 'Webhook Secret' parameter in your wallet settings to allow the platform to verify signatures.

Payment Wallet: Paycom - Card

Common Currencies Parameters Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Parameter	Value
↗ Sandbox	☐
ab Merchant ID	1799331186314
ab Webhook Secret	18oit4mx-p97j-3rg7-q98c-hff90llaa
ab Webhook Address	/api/callback/payments/paycom

Up Down

Add Edit Delete Default

OK Cancel Help

Other settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / Exactly

Exactly

The payment provider [Exactly](#) offers a wide range of payment methods, including cards, bank transfers via the Open Banking system for the EU and UK, PIX system for Brazil, and MB Way and Multibanco systems for Portugal. The provider supports payments in 60+ currencies in more than 200 countries.

To connect Exactly payments, click 'Connect provider' in the [showcase](#) and fill out a short form. You can also use the registration form on the [provider's website](#). The company representative will contact you and will provide further instructions.

After registration, you will be given access to your personal account, where you can find settings for connecting the provider in MetaTrader 5. You will need the following parameters:

- 'Project ID' and 'API Key' to connect the wallet
- 'Signing secret' to set up [callback requests](#)

Open the 'Projects' section and copy the 'Project ID' parameter:

Organization

Dashboard

Projects

Transactions

Reports

Finances

Disputes

Payment links

Team

Developers

≡ Projects

Broker Sandbox Project Sandbox

Broker Sandbox Project

Project ID

1b941ae5-5bz7-9182-1bef-55c14599etb3

Environment mode

Sandbox

MetaTrader 5 trading platform

On the right side, go to the 'Api keys' section and copy the API key. If the key does not exist, create a new one by clicking 'Add'.

The screenshot shows the 'Projects' section of the MetaTrader 5 trading platform. On the left, under the 'Broker Sandbox Project' header, the 'Project ID' is displayed as '1b941ae5-5bz7-9182-1bef-55c14599etb3' and the 'Environment mode' is set to 'Sandbox'. On the right, the 'Api keys' tab is selected, showing an 'Add' button and a table with columns 'Name' and 'Token'. A red arrow points from the 'Sandbox' environment mode button to the 'Api keys' tab. Below the table, the 'Project API key' is shown with a 'Reveal API key' button.

Name	Token
Project API key	[REDACTED]

Create a payment gateway configuration, select Exactly for the gateway and specify the API key under the Common section:

MetaTrader 5 trading platform

Payment Wallet: Exactly - Card

Common Currencies Parameters Countries Groups Commissions Information

 Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name:

Gateway:  Exactly  Trade Main, 1

Type:  Card

☒ Deposit ☒ Push notification

☒ Withdrawal ☒ Email notification

☒ Account creation ☒ SMS notification

API key:

OK Cancel Help


MetaTrader 5 trading platform

In the 'Type' field, select a payment method you wish to connect:

- Card payments
- Bank transfers via Open Banking system
- MB Way
- Multibanco
- PIX

If you want to use multiple payment methods, create separate wallet configurations.

Open the Parameters section and copy the Project ID from your personal account to the corresponding parameter:



Payment Wallet: Exactly - Card

Common Currencies **Parameters** Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up
Down

Parameter	Value
ab Project ID	1b941ae5-5bz7-9182-1bef-55c14599etb3
ab Signing secret	akx92lxyyahOHa671bzwPla9e899xbrPHKZmqtkJA...
ab Webhook endpoint	/api/callback/payments/exactly

Add ▼
Edit
Delete
Default

OK Cancel Help

System features and limitations

The payment system has the following features:

- Withdrawal operations are only supported for cards.
- Refund operations are only supported for cards and the MB Way system.

Setting Up the Environment

Exactly supports operations in a sandbox environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox environment, contact Exactly for a special wallet. You will receive a separate project. Copy the API key and Project ID from this project and paste it to the appropriate parameters in the wallet settings in MetaTrader 5.

The payment gateway automatically determines the status of the current project: production or sandbox. All payments made in the sandbox environment are marked as demo transactions on the MetaTrader 5 side.

Currency settings

Exactly supports payments in a variety of currencies. Each payment method supports different sets of currencies. The list of currencies is specified in the project settings in your personal account:

 **Projects**

Broker Sandbox Project Sandbox 

Broker Sandbox Project

Project ID

1b941ae5-5bz7-9182-1bef-55c14599etb3 

Environment mode

Sandbox

Details Api keys Webhook endpoints

Checkout configuration

Merchant name	-
Website	-
Default language	en

Enabled payment methods


 **Card**

Currencies

Settlement	Processing
EUR	EUR
USD	USD

MetaTrader 5 trading platform

In your wallet settings, specify a list of supported currencies in accordance with the information from your personal account. Also, set a limit on transaction amounts in accordance with Exactly requirements.



The screenshot shows the 'Payment Wallet: Exactly - Card' dialog box with the 'Currencies' tab selected. The dialog has a title bar with standard window controls. Below the tabs, there is a yellow folder icon and a text instruction: 'Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.' A table lists the supported currencies with their respective limits. The table has five columns: 'Currency', 'Min. Deposit', 'Max. Deposit', 'Min. Withdrawal', and 'Max. Withdrawal'. The first row shows 'USD' with a minimum deposit of 5.00, a maximum deposit of 5 000.00, a minimum withdrawal of 10.00, and a maximum withdrawal of 1 000.00. Below the table is a button labeled '+ click to add...'. To the left of the table are three buttons: 'Add', 'Edit', and 'Delete'. At the bottom right are 'OK', 'Cancel', and 'Help' buttons.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
USD	5.00	5 000.00	10.00	1 000.00
+ click to add...				

Setting up callback requests

Callback requests are used to quickly receive transaction processing results. After each transaction, Exactly sends its status to the URL address which you specified in the wallet settings. Therefore, to ensure the platform receives these notifications at the specified address, it must be configured accordingly.

The use of callback requests is optional. However, if you do not configure them, payment status updates may take longer. This could negatively impact the quality of your customer service.

On the platform side, the callback requests are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). Exactly will use this address to communicate with the platform, and the endpoint address for callback requests will be formed relative to it.
2. Associate the domain with the public IP address of one or more access servers. For further information, please see Integration\Web Services.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules

<https://broker.com/api/callback/payments/exactly>

- The first part is an example of a domain name.
 - The second part is a predefined part of the address that is used for all callback requests related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
 - The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.
5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. Please contact Exactly for this list of addresses.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on `/api/callback/`. The list is used for all access servers.

Callback domain:

Up	URL	Allowed IPv4/IPv6	Comment
Down	✓ <code>/api/callback/payments/exactly</code>	18.133.132.144, 13.42.169.93	Exactly payments callbacks
Add			
Edit			
Delete			

6. Specify the callback address in the 'Webhook endpoint' parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. The address is specified without a domain name.

Payment Wallet: Exactly - Card

Common

Currencies

Parameters

Countries

Groups

Commissions

Information



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
ab Project ID	1b941ae5-5bz7-9182-1bef-55c14599etb3
ab Signing secret	akx92xyyahOHa671bzwPla9e899xbrpHKZmqTKJA...
ab Webhook endpoint	/api/callback/payments/exactly

Add ▼

Edit

Delete


Default

OK

Cancel

Help

7. Specify the address for Callback requests in your Exactly account. Open the project, go to the 'Webhook endpoints' section and click Add:



Configure the webhook parameters:

- URL the address for sending webhooks in accordance with the settings specified in steps 5 and 6. The address should be specified with the domain included.
- Description an arbitrary name

On the right side, select the events that will be sent through this webhook:

- charge.processed
- charge.failed
- transfer.processed
- transfer.failed
- charge-authorize.processed
- charge-authorize.failed

☰ Add new webhook endpoint

URI

https://broker.com/api/callback/payments/exactly

Description

MetaTrader callback



Events

Charge

Toggle group

- ☒ charge.processed
- ☒ charge.failed
- ☐ charge.settled
- ☐ charge.attributes-required
- ☐ charge.redirect-required
- ☐ charge.attributes-provided
- ☐ charge.iframe-provided
- ☐ charge.rollbacked

Save your changes. Return to the list of webhooks and click on the newly created webhook to open its settings.

To protect notifications from changes, Exactly signs each callback request with a special password, which is specified in the 'Signing secret' field. Click 'Reveal signing secret'.

 **Webhook endpoint details**

https://broker.com/api/callback/payments/exactly

Signing secret

 Reveal signing secret

MT5 callback

Status	Created at	Listening for	Receives events for
 Active	20 May 2024 15:03	6 events	Broker Sandbox Project

Paste this value into the 'Signing secret' parameter in the wallet settings to enable the platform to verify signatures.

MetaTrader 5 trading platform

Payment Wallet: Exactly - Card

CommonCurrenciesParametersCountriesGroupsCommissionsInformation



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add

Edit

Delete

Default

Parameter	Value
ab Project ID	1b941ae5-5bz7-9182-1bef-55c14599etb3
ab Signing secret	akx92xyyahOHa671bzwPla9e899xbrpHKZmqtkJA...
ab Webhook endpoint	/api/callback/payments/exactly

OK

Cancel

Help

8. Request Exactly's technical support to add the "payment-result" domain to the whitelist for your account.

For regular online purchases, after a transaction is completed, the user is redirected from the payment page back to the store (merchant) page. Since MetaTrader 5 is not a web service, it does not have such a page. Instead, the user is redirected to a special address <https://payment-result/Exactly%20Card>. Based on this redirect, the platform understands that the payment is completed and returns the user to the main payment page.

To enable this redirect, the "payment-result" domain must be resolved on the Exactly side.

Other Settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

MetaTrader 5 Trading Platform / Platform Setup / Payments / Payment Gateways / Ozow

Ozow

The Ozow payment provider operates on South Africa, offering the ability to deposit and withdraw funds via local bank transfers. Designed to simplify and accelerate the traditional inter-bank payment process, Ozow provides a seamless, fast, and secure alternative to outdated payment methods. By eliminating the manual steps and significantly reducing transaction times, Ozow empowers merchants to process payments in seconds.

To connect Ozow payments, click 'Connect Provider' in the showcase and fill out a short online form. You can also use the registration form on the provider's website. The company representative will contact you and will provide further instructions.

After registration, you will be given access to your personal account, where you can find settings for connecting the provider in MetaTrader 5.

Create a payment gateway configuration and select 'Ozow' for the gateway:

Payment Wallet: Ozow

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name:

Gateway: Ozow Trade Main, 1

Type: Ozow

☒ Deposit ☒ Push notification

☒ Withdrawal ☒ Email notification

☐ Account creation ☐ SMS notification

OK Cancel Help

MetaTrader 5 trading platform

The "Type" field provides only one payment method – Ozow. The payment system/bank will be selected on the payment provider page, to which the user is redirected from the trading terminal. Next, select the permitted operations: deposits or withdrawals.

All settings for connecting to the provider are configured under the "Parameters" section:

Payment Wallet: Ozow

Common Currencies **Parameters** Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Parameter	Value
Sandbox	☒
Site Code	BROKER-001
Callback URL	https://broker.com/api/callback/payments/ozow/bro...
Payments API Key	JK5898F2C3O7DF39S4F2731D5FF5B
Payments Private Key	781466982AUI7134A94C45IOYT48E
Payouts API Key	785YH6111P1I47567T9C78I9YUUI6
Payouts Webhook Access To...	
Payouts RTC	☐
Payouts Mock API	☐
API Log	☐

Up Down

Add Edit Delete Default

OK Cancel Help

MetaTrader 5 trading platform

Specify 'Site Code' the merchant site code for processing payments, available in the 'Sites' section of your Ozow account. In this case, your platform will act as a website.

The screenshot displays the 'Sites' management page in the Ozow interface. At the top, there is a green header bar with a search bar labeled 'Search Transaction Reference', a 'Back' button, and a 'Welcome' message. Below the header, the breadcrumb 'Home > Sites' is visible. The main section is titled 'Sites' with a globe icon. To the right of the title are 'Filter' and 'Refresh' buttons, and an 'Add S' button. Below this is a table with the following columns: 'Site Code', 'Site Na...', 'Default ...', 'Bank Re...', 'Urls Set' (with sub-columns 'Cancel', 'Error', 'Success', 'Notify'), and 'Notice ...'. A single row is shown with 'Broker-001' as the Site Code and 'Broker' as the Site Name. The 'Urls Set' columns for this row contain radio buttons. A red arrow points from the 'Sites' header to the 'Site Code' column. At the bottom, a pagination bar shows 'Showing 1 to 1 of 1' and a page number '1' in a green box.

Site Code	Site Na...	Default ...	Bank Re...	Urls Set				Notice ...
				Cancel	Error	Success	Notify	
Broker-001	Broker			☐	☐	☐	☐	

MetaTrader 5 trading platform

If you do not have a site yet, or you need an additional one, for example, to set up another wallet, create the site. To do this, click 'Add Site'.

Next, set the access keys in the wallet settings on the MetaTrader 5 side:

- Payments API Key the authorization key for deposit requests, corresponds to the API Key parameter in the merchant panel.
- Payments Private Key the key used to sign deposit requests, corresponds to the Private Key parameter in the merchant panel.
- Payouts API Key authorization and signature key for payout requests.

These parameters are available in your Ozow account, under the [Merchant Details](#) section:



[← Back](#)

Welcome b

[Home](#) > [Merchant Details](#)



Merchant Details

[Edit D](#)

Name: Broker

Merchant Code: BROKER

Default Bank Account: Ozow (ABSA - 1975838517)

Time Zone: (UTC+02:00) South Africa Standard Time (Johannesburg)

Private Key 781466982AUI7134A94C45IOYT48E 

API Key JK5898F2C3O7DF39S4F2731D5FF5B 

Payouts API Key: 785YH611P1I47567T9C78I9YUUI6

Default Password:

Company Registration Number: 000000001

FIC Number:

FSCA Number:

Forex and Remittance license (AD) number:

Gambling License Number :

System Features and Limitations

Payments on the Ozow side can have the PendingInvestigation status. An inconclusive result was received by the bank. The payment needs to be verified manually. The status is used in case of processing issues on the bank's side.

If the payment on the MetaTrader 5 side is displayed as Pending for a long time, find it through your Ozow account and check the status. If the payment is in the PendingInvestigation status, find out more about what happened to the transaction. After that, contact Ozow technical support, requesting them to finalize the payment state: Complete, Error or Cancelled. Be sure to ask for a status update in the API as well, otherwise the payment on the platform side will remain in the pending state.

Ozow requires users to provide their document number (passport, ID, etc.) for every financial transaction. To prevent the submission of false information, the platform does not allow users to enter the document number manually. Instead, the number is automatically filled in using the details from the trading account:

Account: 851355, Matthew Richardson, USD, 1:100, Netting

Overview Personal Account Profile Subscriptions Security

Name: Matthew

Last name: Richardson Middle name:

Company: Individual

Registered: 2019.02.08 09:07:27

Language: Czech Status: NR

ID number: 6993119945 Lead campaign: web.terminal

MetaQuotes ID: 1A892211 Lead source: www.mql5.com

Email: matthew.richardson@mail.net

Phone: +35796145893

Country: Czech Republic State:

City: Prague Zip code: 010101

Address: Czech Republic

Comment: web terminal


Client Properties... Update Cancel Help

MetaTrader 5 trading platform

Therefore, for payments through Ozow to work correctly, the broker must obtain the user's document number and specify it in the account settings.

Setting Up the Environment

Ozow supports operations in a sandbox environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox environment, contact Ozow for a special wallet. You will receive a separate project. Copy the access keys from this project and paste them to the appropriate fields in the wallet settings in MetaTrader 5. Also enable the 'Sandbox' option.



Payment Wallet: Ozow

Common Currencies Parameters Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Parameter	Value
 Sandbox	☒
 Site Code	BROKER-001
 Callback URL	https://broker.com/api/callback/payments/ozow/bro...
 Payments API Key	JK5898F2C3O7DF39S4F2731D5FF5B
 Payments Private Key	781466982AU17134A94C45IOYT48E
 Payouts API Key	785YH6111P1I47567T9C78I9YUUI6
 Payouts Webhook Access To...	
 Payouts RTC	☐
 Payouts Mock API	☐
 API Log	☐

Up Down

Add Edit Delete Default


OK Cancel Help

MetaTrader 5 trading platform

All payments made in the sandbox environment are marked as demo transactions on the MetaTrader 5 side.

Currency Settings

Ozow only supports payments in one currency: South African Rand (ZAR). Specify it in the gateway settings. Also, set a limit on transaction amounts in accordance with Ozow requirements.



The screenshot shows the 'Payment Wallet: Ozow' dialog box with the 'Currencies' tab selected. The dialog has a title bar with standard window controls. Below the title bar is a tabbed interface with tabs for 'Common', 'Currencies', 'Parameters', 'Countries', 'Groups', 'Commissions', and 'Information'. The 'Currencies' tab is active, displaying a folder icon and a message: 'Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.' Below this is a table with five columns: 'Currency', 'Min. Deposit', 'Max. Deposit', 'Min. Withdrawal', and 'Max. Withdrawal'. The table contains one entry for 'ZAR' with a minimum deposit of '0.00', a maximum deposit of 'unlimited', a minimum withdrawal of '0.00', and a maximum withdrawal of 'unlimited'. Below the table is a button labeled '+ click to add...'. To the left of the table are three buttons: 'Add', 'Edit', and 'Delete'. At the bottom right of the dialog are three buttons: 'OK', 'Cancel', and 'Help'.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
 ZAR	0.00	unlimited	0.00	unlimited

+ click to add...

Buttons: Add, Edit, Delete, OK, Cancel, Help

Configuring Callback Requests

Callback requests are used to promptly receive payment statuses ([notify url](#)) and to confirm payouts ([payout webhook](#)). Ozow sends requests to a URL specified by you in your wallet settings. Accordingly, to enable the receipt of these notifications at the specified address in the platform, you should configure the platform.

The use of callback requests is mandatory. Without them, you will not be able to provide withdrawal operations.

On the platform side, the callbacks are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). Ozow will use this address to communicate with the platform, and the endpoint address for callback requests will be formed relative to it.
2. Associate the domain with the [public IP address](#) of one or more access servers. For further information, please see [Integration\Web Services](#).
3. [Add an SSL certificate](#) for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules:

<https://broker.com/api/callback/payments/ozow>

- The first part is an example of a domain name.
 - The second part is a predefined part of the address that is used for all callback requests related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
 - The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.
5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. Please contact Ozow for this list of addresses.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on `/api/callback/`. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
 <code>/api/callback/payments/ozow</code>	18.200.146.129,34.252.239.0	Ozow payments callback

6. Specify the callback address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

Also, indicate 'Payouts Webhook Access Token', the token for authenticating payout confirmation callbacks. This is a unique code that you should choose. It must be long enough and contain different types of characters: numbers, lowercase and uppercase letters.

MetaTrader 5 trading platform

Payment Wallet: Ozow

Common

Currencies

Parameters

Countries

Groups

Commissions

Information



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
 Sandbox	☒
 Site Code	BROKER-001
 Callback URL	https://broker.com/api/callback/payments/ozow/bro...
 Payments API Key	JK5898F2C3O7DF39S4F2731D5FF5B
 Payments Private Key	781466982AUI7134A94C45IOYT48E
 Payouts API Key	785YH6111P1I47567T9C78I9YUUI6
 Payouts Webhook Access To...	
 Payouts RTC	☐
 Payouts Mock API	☐
 API Log	☐

Add

Edit

Delete

Default

OK

Cancel

Help

7. Provide the Callback URL and Payouts Webhook Access Token to Ozow support to enable payout functionality. They will add these parameters to your profile.

Testing Procedure for Connecting Withdrawal Operations

To connect withdrawal operations in a real environment, Ozow requires the Payouts Integration Testing procedure. In simplified form, the procedure is as follows:

1. Enable the API Log parameter in the gateway settings to log raw statuses of operations and callback requests received from Ozow API endpoints.
2. Follow the steps in the "The following scenario needs to be tested" section of the Ozow guide.
3. Enable the Payouts Mock API parameter in the gateway settings; it is a flag indicating the use of the test mode for payments.
4. Follow the steps in the "Simulation records in Mock API" section of the Ozow guide, switching the Mock API to the desired mode using curl or other methods:

Reset to successful payout:

```
curl --request POST
"https://stagingpayoutsapi.ozow.com/mock/v1/settestconfiguration" --header
"Content-Type: application/json" --header "SiteCode: BROKER-001" --header "ApiKey:
785YH6111P1I47567T9C78I9YUUI6" --data-raw "{\"SiteCode\":\"BROKER-001\"}"
```

IsAccountDecryptionFailed:

```
curl --request POST
"https://stagingpayoutsapi.ozow.com/mock/v1/settestconfiguration" --header
"Content-Type: application/json" --header "SiteCode: BROKER-001" --header "ApiKey:
785YH6111P1I47567T9C78I9YUUI6" --data-raw
"{\"SiteCode\":\"BROKER-001\", \"IsAccountDecryptionFailed\":true}"
```

IsNotVerifiedResponse:

```
curl --request POST
"https://stagingpayoutsapi.ozow.com/mock/v1/settestconfiguration" --header
"Content-Type: application/json" --header "SiteCode: BROKER-001" --header "ApiKey:
785YH6111P1I47567T9C78I9YUUI6" --data-raw
"{\"SiteCode\":\"BROKER-001\", \"IsNotVerifiedResponse\":true}"
```

IsAccountDecryptionKeyMissing:

```
curl --request POST
"https://stagingpayoutsapi.ozow.com/mock/v1/settestconfiguration" --header
"Content-Type: application/json" --header "SiteCode: BROKER-001" --header "ApiKey:
785YH6111P1I47567T9C78I9YUUI6" --data-raw
"{\"SiteCode\":\"BROKER-001\", \"IsAccountNumberDecryptionKeyMissing\":true}"
```

Replace the highlighted parts in your requests with your Site Code and Payouts API Key.

5. Collect the API responses needed for the report from the trade server log, screenshots of transactions from your personal account and emails that you will receive from Ozow. The server logs look like this:

Response to a withdrawal request:

```
13:53:23.958 Ozow Withdrawal Payout Request JSON response: { "payoutId" : "",  
  "payoutStatus" : { "status" : 1, "subStatus" : 101, "errorMessage" : "Payout  
amount below minimum amount" } }
```

```
13:53:58.913 Ozow Withdrawal Payout Request JSON response: { "payoutId" :  
"20240920-1000-4a63-a36a-44ef3979042d", "payoutStatus" : { "status" : 1,  
"subStatus" : 201, "errorMessage" : "" } }
```

Response to a withdrawal transaction status request:

```
13:54:01.582 Ozow Withdrawal Payout Status JSON response: { "id" :  
"20240920-1000-4a63-a36a-44ef3979042d", "amount" : 10.0, "merchantReference" :  
"MT5_D67", "customerBankReference" : "4048", "siteCode" : "MET-MET-001", "isRtc"  
: false, "notifyUrl" :  
"https://bkmqdev.webredirect.org/api/callback/payments/ozow?mt5_type=payout_status",  
"bankingDetails" : { "bankGroupId" : "4816019c-3314-4c80-8b6b-b2cd16dcc4ec",  
"branchCode" : "250655", "accountNumber" : "FDrXvOYmHHEb/vHnhCDgWA==" },  
"payoutStatus" : { "status" : 1, "subStatus" : 201, "errorMessage" : "" } }
```

Callback with a withdrawal transaction status:

```
13:54:07.496 Ozow Withdrawal Payout Notification JSON response:  
{ "PayoutId": "20240920-1000-4a63-a36a-44ef3979042d", "SiteCode": "MET-MET-001", "Merch
```

Use these examples to search your server log for similar entries based on keywords.

6. Once you have completed testing, disable the Payouts Mock API and API Log options.

Other Settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

MetaTrader 5 Trading Platform / Platform Setup / Payments / Payment Gateways / AK Remit

AK Remit

AK Remit offers online payments in Malaysia, Indonesia and Vietnam. To accept deposits, you can use fast and regular wire transfers, as well as cryptocurrency payments.

To connect AK Remit payments, click 'Connect Provider' in the showcase and fill out a short online form. You can also use the registration form on the provider's website. The company representative will contact you and will provide further instructions.

After registration, you will receive connection details: API Key and Merchant ID. You will use this data to configure the wallet on the platform side.

Create a payment gateway configuration and select AK Remit as your gateway:

Payment Wallet: AKRemit Fiat

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: AKRemit Fiat

Gateway: AK Remit

Type: Direct Banking

☒ Deposit ☒ Push notification

☐ Withdrawal ☒ Email notification

☐ Account creation ☒ SMS notification

API key:

Automatic refunds are not supported. If a successful transaction is rejected, refunds must be created manually on the AK Remit side.

OK Cancel Help

MetaTrader 5 trading platform

In the 'Type' field, select a payment method:

- Bank Transfer manual bank transfers (Virtual Accounts, VA).
- Direct Banking fast interbank transfers.
- Crypto cryptocurrency payments.

For further details, please see the [Limitations and features of the system](#). If you wish to use multiple payment methods in parallel, create separate wallet configurations.

In the API Key field, enter the corresponding key provided by AK Remit. Next, go to the Parameters tab and specify the Merchant ID:

Payment Wallet: AKRemit Virtual Account

Common Currencies **Parameters** Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up
Down

Parameter	Value
↕ Sandbox	
ab Merchant ID	4759315644572136493
ab Callback URL	https://broker.com/api/callback/payments/akremit_fiat

Add ▼
Edit
Delete
Default

OK Cancel Help

System Features and Limitations

The provider supports transfers in three currencies:

- Malaysian Ringgit (MYR) fast bank transfers via Financial Process Exchange (FPX) and QR codes (DuitNow). Supported banks: Maybank, RHB, HongLeong Bank, Public Bank, CIMB Bank, Affin Bank, QR DuitNow. Manual bank transfers (Virtual Accounts, VA) through any banks are also supported.
- Vietnamese Dong (VND) fast bank transfers via Financial Process Exchange (FPX) and QR codes (Viet QR). Supported banks: Techcom Bank, BIDV, AgriBank, Eximbank, MB Bank, Sacom Bank, VIB, Viet QR. Manual bank transfers (Virtual Accounts, VA) through any banks are also supported.
- Indonesian Rupiah (IDR) manual bank transfers (Virtual Accounts, VA); supported banks: BRI, Mandiri, BNI, Danamon, Permata Bank, Maybank, CIMB.

The system also supports transfers in cryptocurrencies: ETH, BNB and USDT.

Refund operations through the platform are not supported. If you cancel a successful payment on the MetaTrader 5 side, you will need to manually create a refund on the AK Remit side.

The payment system does not support withdrawal operations.

Setting Up the Environment

AK Remit supports operations in a sandbox (test) environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox environment, contact AK Remit for a special wallet. You will receive separate API Key and Merchant ID. Specify them in the wallet settings and enable the 'Sandbox' option.

MetaTrader 5 trading platform

Payment Wallet: AKRemit Virtual Account

Common

Currencies

Parameters

Countries

Groups

Commissions

Information



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
 Sandbox	
 Merchant ID	4759315644572136493
 Callback URL	https://broker.com/api/callback/payments/akremit_fiat

Add

Edit

Delete

Default

OK

Cancel

Help

Currency Settings



AK Remit supports payments in the MYR, VND and IDR currencies, and in cryptocurrencies: ETH, BNB and USDT. Specify the required options in the gateway settings. Also set the transaction amount limit in accordance with AK Remit requirements.



Payment Wallet: AKRemit Virtual Account

Common Currencies Parameters Countries Groups Commissions Information

 Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
 MYR	0.00	500.00	0.00	unlimited
+ click to add...				

The platform supports conversion only for currencies with a three-character code. If you use USDT for payments as is, traders will only be able to top up accounts with the same deposit currency. For other deposit currencies, conversion of the payment amount will not be possible, even if you add the corresponding currency pair to the platform (for example, USDTUSD).

To avoid this limitation, the gateway uses USD as the USDT currency. Accordingly, you need to specify USD in the gateway settings. During a deposit or withdrawal operation, the transaction amount will be converted from the user's account currency to USD and then sent to the payment system as a USDT transaction.

When using USD instead of USDT, please consider possible currency risks associated with the USDTUSD exchange rate.

Configuring Callback Requests

Callback requests are used to promptly receive payment statuses. AK Remit sends requests to a URL that you set in your wallet settings. Accordingly, to enable the receipt of these notifications at the specified address in the platform, you should configure the platform accordingly.

The use of callbacks is optional. However, if you do not configure them, updating payment statuses may take longer. This could negatively impact the quality of your customer service.

On the platform side, the callbacks are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). AK Remit will access the platform at this address. Also, address of the endpoint for callbacks will be formed relative to this address.
2. Associate the domain with the public IP address of one or more access servers. For further information, please see Integration\Web Services.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules:

https://broker.com/api/callback/payments/akremit_fiat

- The first part is an example of a domain name.
- The second part is a predefined part of the address that is used for all callback requests related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.

MetaTrader 5 trading platform

- The **third part** is defined by you. You can specify any address, but we strongly recommend using a logical and clear naming system. Depending on the type of payment method selected, the following addresses are substituted into the Callback URL parameter in the default gateway settings:
 - ♦ Wire Transfer .../api/callback/payments/**akremit_va**
 - ♦ Direct banking .../api/callback/payments/**akremit_fiat**
 - ♦ Crypto .../api/callback/payments/**akremit_crypto**

5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. Please contact AK Remit for this list of addresses.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on /api/callback/. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
 /api/callback/payments/akremit_fiat	8.210.113.234, 8.217.124.80	AK Remit payments callback

6. Specify the callback address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

MetaTrader 5 trading platform

Payment Wallet: AKRemit Virtual Account

CommonCurrenciesParametersCountriesGroupsCommissionsInformation



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add

Edit

Delete

Default

Parameter	Value
 Sandbox	
 Merchant ID	4759315644572136493
 Callback URL	https://broker.com/api/callback/payments/akremit_fiat

OKCancelHelp

Other Settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / The Kingdom Bank

The Kingdom Bank

The Kingdom Bank is a digital-asset friendly international bank based in the Commonwealth of Dominica. The company provides corporate and correspondence banking services, local and global payments in more than 80 countries. Supported payment methods include credit cards, crypto transactions, direct bank transfers, as well as local systems, such as PIX, Efecty, etc.

To connect payments via The Kingdom Bank, click 'Connect provider' in the [showcase](#) and fill out a short online form. You can also use the registration form on the [provider's website](#). The company representative will contact you and will provide further instructions.

After registration, you will be given access to your personal account, where you can find details for connecting the provider. Open your account settings and go to the Developers section. Copy the following parameters:

- API Key
- API Secret
- Signature Key ID
- Signature Key



User management

Developers

Profile settings

Log out

Developers

Access IP Whitelist

API Keys

API Key	API Secret
orue2bxklls9zlkhoosg8lbns	*****

Signature Keys

Signature Key ID	Signature Key
y87yhklop	*****

Settings

MetaTrader 5 trading platform

Create a payment gateway configuration and select 'The Kingdom Bank' as your gateway:

Payment Wallet: The Kingdom Bank Card

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name:

Gateway: The Kingdom Bank Trade Main, 1

Type: Card

☒ Deposit ☒ Push notification

☐ Withdrawal ☒ Email notification

☐ Account creation ☒ SMS notification

API key:

Automatic refunds are not supported. If a successful transaction is rejected, refunds must be created manually on the The Kingdom Bank side.


OK Cancel Help

In the 'Type' field, select a payment method:

- Wire Transfer (manual)
- Card
- PIX Brasil
- Efecty, Colombia
- Przelewy24
- MoMo
- Direct Banking fast interbank transfers
- Crypto cryptocurrency payments
- The Kingdom Bank Wallet The Kingdom Bank wallet
- Any other methods supported by the provider and available for your account, but not explicitly supported by the payment gateway. When using this option, the payment method will be selected during payment in the client terminal.

For further details, please see the [Limitations and features of the system](#). If you wish to use multiple payment methods in parallel, create separate wallet configurations.

In the API Key field, enter the corresponding key from your account settings. Next, go to the 'Parameters' tab and specify other parameters from your account settings: API Secret, Signature Key, Signature Key ID.



Payment Wallet: The Kingdom Bank Card

Common Currencies **Parameters** Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up Down

Parameter	Value
↕ Sandbox	☐
ab API Secret	89nga7jafxpqas95bz4982locn
ab Signature Key	7nb98yubanq825a7kdfsh1gf24
ab Signature Key ID	y87yhklop
ab Callback URL	https://broker.com/api/callback/payments/thekingd...

Add Edit Delete Default

OK Cancel Help

System features and limitations

The system supports transfers in the following cryptocurrencies: ADA, BTC, DOGE, ETH, SOL, XRP and USD. For USD, the blockchain USDT.TRC20 is used by default. In addition, the system supports the use of USDC.ERC20, USDC.TRC20 and USDT.ERC20. The currency is selected during the payment through the client terminal.

Refund operations through the platform are only supported for Direct Banking, Kingdom Wallet, and PIX Brasil. For all other methods, if you cancel a successful payment on the MetaTrader 5 side, you will need to manually create a refund on the Kingdom Bank side.

The payment system supports withdrawal operations only for PIX Brasil and Direct Banking methods.

Setting Up the Environment

The Kingdom Bank supports operations in a sandbox (test) environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox environment, contact The Kingdom for a special wallet. You will receive a separate test account with the required connection details. Specify them in the wallet settings and enable the 'Sandbox' option.

MetaTrader 5 trading platform

Payment Wallet: The Kingdom Bank Card

CommonCurrenciesParametersCountriesGroupsCommissionsInformation



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add

Edit

Delete

Default

Parameter	Value
 Sandbox	
 API Secret	89nga7jafxpqas95bz4982locn
 Signature Key	7nb98yubanq825a7klfsh1gf24
 Signature Key ID	y87yhklop
 Callback URL	https://broker.com/api/callback/payments/thekingd...

OK

Cancel

Help

Currency settings




The Kingdom Bank supports payments in a variety of currencies. Specify the required options in the gateway settings. In addition, you will need to set a limit on transaction amounts in accordance with The Kingdom Bank requirements.




Payment Wallet: The Kingdom Bank Card

Common Currencies Parameters Countries Groups Commissions Information

 Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
 USD	10.00	unlimited	10.00	1 000.00
+ click to add...				

MetaTrader 5 trading platform

The platform only supports conversion for currencies with a three-character code, while the provider additionally supports the four-digit USDT and USDC currencies. If you specify them as is, then traders will only be able to top up accounts with the same deposit currency. For other deposit currencies, conversion of the payment amount will not be possible, even if you add the corresponding currency pair to the platform (for example, USDTUSD or USDCUSD).

To avoid this limitation, the gateway uses USD as the USDT and USDC currency. Accordingly, you need to specify USD in the gateway settings. During a deposit or withdrawal operation, the transaction amount will be converted from the user's account currency to USD and then sent to the payment system as a USDT or USDC transaction.

When using USD instead of USDT/USDC, please consider possible currency risks associated with the USDTUSD/USDCUSD exchange rate.

Setting up callback requests

Callback requests are used to promptly receive payment statuses. The Kingdom Bank sends requests to a URL that you set in your wallet settings. Accordingly, to enable the receipt of these notifications at the specified address in the platform, you should configure the platform accordingly.

The use of callback requests is mandatory. Without callbacks, users will not be able to save previously used payment methods. Since withdrawals are only possible through previously used methods, this type of operation will not be available. Also, without Callback requests, updating payment statuses may take longer. This could negatively impact the quality of your customer service.

On the platform side, the callbacks are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). The Kingdom Bank will access the platform at this address. Also, the endpoint address for callbacks will be formed relative to this address.
2. Associate the domain with the public IP address of one or more access servers. For further information, please see Integration\Web Services.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules:

<https://broker.com/api/callback/payments/kingdombank>

MetaTrader 5 trading platform

- The first part is an example of a domain name.
- The second part is a predefined part of the address that is used for all callback requests related to payment systems. For example, callbacks to `https://broker.com/api/callback/my/callback` will not reach wallets.
- The third part is defined by you. You can specify any address, but we strongly recommend using a logical and clear naming system.

5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. Please contact The Kingdom Bank for this list of addresses.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on `/api/callback/`. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
 <code>/api/callback/payments/kingdombank</code>	3.126.21.221, 35.156.108.181	The Kingdom Bank payments callback

6. Specify the callback address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

MetaTrader 5 trading platform

Payment Wallet: The Kingdom Bank Card

CommonCurrenciesParametersCountriesGroupsCommissionsInformation



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add

Edit

Delete

Default

Parameter	Value
 Sandbox	
 API Secret	89nga7jafxpqas95bz4982locn
 Signature Key	7nb98yubanq825a7klfsh1gf24
 Signature Key ID	y87yhklop
 Callback URL	https://broker.com/api/callback/payments/thekingd...

OK

Cancel

Help

Other Settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / OpenPayd

OpenPayd

OpenPayd provides a comprehensive banking and payment infrastructure, including accounts, currency exchange, international and local payments, acquiring services, and Open Banking solutions. With an expanding portfolio of licenses covering the UK, Europe, and North America, OpenPayd equips numerous digital businesses worldwide with essential payment solutions. The platform currently supports 102 countries.

By enabling OpenPayd payments in MetaTrader 5, you can accept client deposits via manual and automated bank transfers through the Direct Banking system. The service supports 14 currencies, including EUR, USD, and GBP, as well as popular cryptocurrencies.

To enable payments through OpenPayd, click 'Connect Provider' in the [showcase](#) and complete a short application form. You can also use the registration form on the [provider's website](#). After registration, a company representative will contact you to guide you through the next steps.

Once registered, you will gain access to your personal account, where you can find the necessary connection details. Open your account settings and go to 'Developers \ API Keys'. If you do not have an API key yet, create one:

OpenPayd Sandbox (TEST environment)

API KEYS
Manage your API Keys
Account Holder ID: 95d3f8e1-39df-4x6b-9ty4-0174c20ui7e9

CREATE API KEY

025-02-28 01:37 PM
Disabled
Enabled

024-12-05 11:19 AM
Disabled
Enabled

Home
Accounts
Payments
Exchange
Transactions
Beneficiaries
Linked Clients
Pending Transactions
Developers
API Keys
Webhooks
Settings

CREATE API KEY

Please create a username for the API key

API Username *

broker

CREATE API KEY

MetaTrader 5 trading platform

Enter any recognizable name as 'API Username' and click 'Create API key'. A password will be displayed once save it securely, as you will not be able to view it again after closing the window.

The screenshot shows the OpenPayd Sandbox (TEST environment) interface. The left sidebar contains navigation links: Home, Accounts, Payments, Exchange, Transactions, Beneficiaries, Linked Clients, Pending Transactions, Developers, API Keys, Webhooks, and Settings. The main content area is titled 'API KEYS' and 'Manage your API Keys'. It displays the 'Account Holder ID: 95d3f8e1-39df-4x6b-9ty4-0174c20ui7e9' and a 'CREATE API KEY' button. A modal window titled 'API KEY PASSWORD' is open, showing the password 'yU85*xqE+4' and a 'Copy' button. The modal also includes a confirmation button and a warning that the password will no longer be available after closing the window.

OpenPayd Sandbox (TEST environment)

API KEYS
Manage your API Keys
Account Holder ID: 95d3f8e1-39df-4x6b-9ty4-0174c20ui7e9

API KEY PASSWORD
broker

Please copy the Password below for the API key.
It will only be shown ONCE

yU85*xqE+4 Copy

I HAVE COPIED THE PASSWORD. CLOSE THE WINDOW

Once closed the password will no longer be available to be copied.

MetaTrader 5 trading platform

You will also need the Account Holder ID, which is displayed at the top of the section.

Create a new payment gateway configuration and select 'OpenPayd' as the gateway:

Payment Wallet: OpenPayd Bank Payment

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: OpenPayd Bank Payment

Gateway: OpenPayd Main Trade Server, 1

Type: Direct Banking

☒ Deposit ☒ Push notification
☐ Withdrawal ☒ Email notification
☐ Account creation ☐ SMS notification

Login: broker

Password: ●●●●●●●●

Automatic refunds are not supported. If a successful transaction is rejected, refunds must be created manually on the OpenPayd side.

OK Cancel Help

MetaTrader 5 trading platform

In the 'Type' field, select a payment method:

- Wire Transfer (manual)
- Direct Banking fast interbank transfers

If you want to use multiple payment methods, create separate wallet configurations.

In the Login field, enter the API Username from your API key. In the Password field, enter the API key password. Navigate to the 'Parameters' tab and enter the 'Account Holder ID' obtained from the 'Developers \ API Keys' section.

Payment Wallet: OpenPayd Bank Payment

Common Currencies Parameters Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Parameter	Value
Sandbox	☒
Environment	UK
Account Holder ID	95d38e1-39df-4x6b-9ty4-0174c20ui7e9
Signature Key Path	C:\MetaTrader5\TradeMain\Payments\OpenPayd.P...
Account ID	USD19668612880470,EUR17006084283470,GBP07...
Callback URL	https://broker.com/api/callback/payments/openpay...
Redirect URL	https://broker.com/api/callback/payments/openpay...

Up Down

Add Edit Delete Default

OK Cancel Help

Environment Configuration

OpenPayd offers a sandbox environment for testing transactions. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To access the test environment, contact OpenPayd for a special wallet. A separate account with necessary credentials will be provided. Enter these credentials in your wallet settings and enable the 'Sandbox' parameter.

Payment Wallet: OpenPayd Bank Payment

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up
Down

Parameter	Value
 Sandbox	☒
 Environment	UK
 Account Holder ID	95d38e1-39df-4x6b-9ty4-0174c20ui7e9
 Signature Key Path	C:\MetaTrader5\TradeMain\Payments\OpenPayd.P...
 Account ID	USD19668612880470,EUR17006084283470,GBP07...
 Callback URL	https://broker.com/api/callback/payments/openpay...
 Redirect URL	https://broker.com/api/callback/payments/openpay...

Add ▼

Edit

Delete

Default

OK Cancel Help

MetaTrader 5 trading platform

If the wallet is used in real environment, you should configure its 'Environment' parameter accordingly. OpenPayd provides different environments depending on the jurisdiction in which the broker operates:

- UK for companies in the UK and those outside the European Economic Area (EEA).
- EU for companies within the EEA.

Confirm the appropriate setting with your OpenPayd manager.

Currency Configuration

Each currency in OpenPayd operates through a separate internal account. To use it for payments in MetaTrader 5, specify its ID in the gateway settings. Open the Accounts section in your OpenPayd profile and create an account in the desired currency.

The screenshot displays the OpenPayd user interface in a 'Sandbox (TEST environment)'. The left sidebar contains navigation links: Home, Accounts (selected), Payments, Exchange, Transactions, Beneficiaries, Linked Clients, Pending Transactions, Developers, and Settings. The main content area is titled 'ACCOUNTS' and shows 'All your Accounts on OpenPayd'. It includes a search bar, a 'Hide Closed Accounts' toggle, and a list of three accounts:

Account Name	Status	Balance
Test USD	Primary	146.82 USD
Test XPF	Primary	0.00 XPF
Test ZMW	Primary	0.00 ZMW

MetaTrader 5 trading platform

Select the created account to open its details and copy the ID field.

 **OpenPayd**

Sandbox (TEST environment)



 Home

 **Accounts**

 Payments >

 Exchange

 Transactions >

 Beneficiaries >

 Linked Clients >

 Pending Transactions >

 Developers >

 Settings >

[< Back to Accounts](#)



Test USD

Primary



ID **USD19668612880470**

Bank Account Holder Name **BROKER**

IBAN **BR69CFTE879600000000900100785514**

SWIFT BIC **CFTEMTM1**

Account Number **0000000900100785514**

146.82 USD

ACTIONS ▾

Transaction ID	Status ▾	Type ▾
From Date 	To Date 	Sender
Beneficiary	Minimum amount	Maximum amount

MetaTrader 5 trading platform

Paste this ID into the Account ID parameter in your payment gateway settings. To use multiple currencies, specify their account IDs separated by commas.

Payment Wallet: OpenPayd Bank Payment

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up
Down

Parameter	Value
 Sandbox	
ab Environment	UK
ab Account Holder ID	95d38e1-39df-4x6b-9ty4-0174c20ui7e9
ab Signature Key Path	C:\MetaTrader5\TradeMain\Payments\OpenPayd.P...
ab Account ID	USD 196686 12880470, EUR 17006084283470, GBP07...
ab Callback URL	https://broker.com/api/callback/payments/openpay...
ab Redirect URL	https://broker.com/api/callback/payments/openpay...

Add ▼
Edit
Delete
Default

OK Cancel Help

MetaTrader 5 trading platform



Next, specify the corresponding currencies in the 'Currencies' and transaction limits according to OpenPayd requirements.



Payment Wallet: OpenPayd Bank Payment

Common Currencies Parameters Countries Groups Commissions Information

 Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
 EUR	0.00	unlimited	0.00	unlimited
 GBP	0.00	unlimited	0.00	unlimited
+ click to add...				

Direct Banking supports only GBP and EUR.

Setting up callback requests

Callback requests are used to promptly receive payment statuses. OpenPayd sends requests to a URL specified by you in your wallet settings. Accordingly, to enable the receipt of these notifications at the specified address in the platform, you should configure the platform accordingly.

The use of callback requests is mandatory for the "Bank Transfer" method. Without them, you will not be able to receive transaction processing statuses.

On the platform side, the callbacks are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). OpenPayd will use this address to communicate with the platform, and the endpoint address for callback requests will be formed relative to it.
2. Associate the domain with the public IP address of one or more access servers. For further information, please see Integration\Web Services.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules:

https://broker.com/api/callback/payments/openpayd_direct

- The first part is an example of a domain name.
 - The second part is a predefined part of the address that is used for all callback requests related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
 - The third part is defined by you. You can specify any address, but we strongly recommend using a logical and clear naming system.
5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. Please contact OpenPayd for this list of addresses.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on /api/callback/. The list is used for all access servers.

Callback domain:

- Up
- Down
- Add
- Edit
- Delete

URL	Allowed IPv4/IPv6	Comment
✓ /api/callback/payments/openpayd_dir...	104.155.2.105, 35.205.152.163	OpenPayd payments callback callback

6. Specify the callback address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

Payment Wallet: OpenPayd Bank Payment

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
↕ Sandbox	☐
ab Environment	UK
ab Account Holder ID	95d38e1-39df-4x6b-9ty4-0174c20ui7e9
ab Signature Key Path	C:\MetaTrader5\TradeMain\Payments\OpenPayd.P...
ab Account ID	USD19668612880470,EUR17006084283470,GBP07...
ab Callback URL	https://broker.com/api/callback/payments/openpay...
ab Redirect URL	https://broker.com/api/callback/payments/openpay...

Add ▼

Edit

Delete

Default

OK Cancel Help

MetaTrader 5 trading platform

7. Add the final address for callback requests to your OpenPayd personal account in the Developers\Webhooks section. Click Add Webhook, enter the address, and select the following as the events to receive:

- Open Banking - Payment Status Updated for the Direct Banking method
- Pay In - Completed for the Bank Transfer method

 **OpenPayd** Sandbox (TEST environment)

Home

Accounts

Payments

Exchange

Transactions

Beneficiaries

Linked Clients

Pending Transactions

Developers

API Keys

Webhooks

Settings

WEBHOOKS

Manage webhooks for your API integration

[Learn more about webhooks](#)

ADD ENDPOINT

DESCRIPTION	EVENTS	STATUS
-------------	--------	--------

ADD A WEBHOOK POINT

Endpoint URL *

https://broker.com/api/callback/payments/openpayd_direct

Description

Events to send

PAY IN

☐ Completed

☐ Review

☐ Processing

☐ Failed

TRANSFER

☐ Completed

☐ Failed

☐ Cancelled

RETURN

☐ Return In Completed

☐ Return Out Completed

PAYOUT

☐ Completed

☐ Processing

☐ Failed

☐ Cancelled

EXCHANGE

☐ Completed

☐ Failed

OTHER

☐ Account Status Updated

☐ Fee

☐ Linked Client Status Updated

☒ Open Banking - Payment Status Updated

☒ Enable retry

☐ Manual Adjustment

Cancel

ADD ENDPOINT

1386

Request Signing

To protect the information transmitted, OpenPayd signs each request sent with a special private key. To enable the platform to verify the authenticity of requests, download the public key from your account. Open the Developers\Webhooks section and click 'Download OpenPayd Public Key':

The screenshot shows the OpenPayd Sandbox (TEST environment) dashboard. The left sidebar contains a navigation menu with the following items: Home, Accounts, Payments, Exchange, Transactions, Beneficiaries, Linked Clients, Pending Transactions, Developers (highlighted), API Keys, and Webhooks. The main content area is titled 'WEBHOOKS' and includes the subtitle 'Manage webhooks for your API integration'. Below this is a link to 'Learn more about webhooks' and an 'ADD ENDPOINT' button. A table lists two webhooks with their URLs and event counts. Below the table is a section for 'OpenPayd Webhook signatures' with a link to 'Learn more about webhook signatures' and a 'Download OpenPayd Public Key' button.

URL	EVENTS
https://bk.webredirect.org/api/callback/payments/openpayd_direct	1
https://bk.webredirect.org/api/callback/payments/open_payd	2

MetaTrader 5 trading platform

Save the resulting PUBLIC_KEY.pem file in any directory on the server where your MetaTrader 5 platform is installed. Next, specify the absolute path to this file in the 'Security Key Path' parameter in the payment gateway settings:

Payment Wallet: OpenPayd Bank Payment

Common Currencies Parameters Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Parameter	Value
Sandbox	☒
Environment	UK
Account Holder ID	95d38e1-39df-4x6b-9ty4-0174c20ui7e9
Signature Key Path	C:\MetaTrader5\TradeMain\Payments\OpenPayd.P...
Account ID	USD19668612880470,EUR17006084283470,GBP07...
Callback URL	https://broker.com/api/callback/payments/openpay...
Redirect URL	https://broker.com/api/callback/payments/openpay...

Up Down

Add Edit Delete Default

OK Cancel Help

When configuring the web callback address in the Callback URL parameter, be sure to specify the signature verification key.

Redirect URL

This setting is only required for the Direct Banking method.

Typically, upon completing a payment on its page, the provider redirects the user back to the merchant's website. The provider allows specifying a predetermined redirection page.

In the case of payments in MetaTrader 5, this redirection page is the client terminal itself. Since the terminal does not have a public internet address, a special callback address must be configured within the platform. The provider will send requests to this address upon payment completion, and the platform will intercept these requests to automatically redirect the user to the appropriate page within the terminal.

Create a redirect address in the same way as you do for callback requests. The address must be a subpath to the address for callback requests. For example, the callback address is

`https://broker.com/api/callback/payments/openpayd_direct`

Then the redirect address can be

`https://broker.com/api/callback/payments/openpayd_direct/payment-result`

The highlighted part can be anything.

Enter this address in the Redirect URL parameter in the payment gateway settings and inform your OpenPayd manager.

MetaTrader 5 trading platform

Payment Wallet: OpenPayd Bank Payment

CommonCurrenciesParametersCountriesGroupsCommissionsInformation



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add

Edit

Delete

Default

Parameter	Value
↕ Sandbox	☐
ab Environment	UK
ab Account Holder ID	95d38e1-39df-4x6b-9ty4-0174c20ui7e9
ab Signature Key Path	C:\MetaTrader5\TradeMain\Payments\OpenPayd.P...
ab Account ID	USD19668612880470,EUR17006084283470,GBP07...
ab Callback URL	https://broker.com/api/callback/payments/openpay...
ab Redirect URL	https://broker.com/api/callback/payments/openpay...

OK

Cancel

Help

The Redirect URL must be a subpath of the Callback URL.

Other Settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

Manual Bank Transfers with OpenPayd

When initiating a manual bank transfer in the client terminal, the trader will see the broker's OpenPayd account details based on their selected currency and Account ID settings. The payment reference will be displayed in the format "MT5 <Login> <PaymentID>".

Deposit to account 4817698 via OpenPayd Manual Bank...

[Back to Payments](#)

Broker

<https://broker.net>

Invoice #21

Date 2025.03.05

Description	Amount
Invoice 21, deposit account 4817698	1000.00

Amount to be paid: **1000.00 USD**

Enter this exact details on the bank wire transfer form:

Sender Name John Smith

IBAN MT95CFTE19870000000090010016956

BIC CFTEMTM1

Account Number 000000090010016956

Reference MT5 4817698 21

Amount 1000.00 USD

Please make sure to specify the correct reference and payment details in your transfer, as indicated above, in order to avoid any delays and possible returns of funds due to wrong or lack of details.

MetaTrader 5 trading platform

The user must complete the transfer with this Reference. Upon receiving the transaction, OpenPayd will notify the payment plugin via a web callback, and the plugin will finalize the payment using the transaction Reference.

If the user does not complete the transfer within 14 days, the transaction will be moved to the payment history. However, if OpenPayd later sends a corresponding web callback, the payment can still be successfully processed.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / STICPAY

STICPAY

STICPAY is a global payment provider based in London, offering secure, innovative, and user-friendly financial services. STICPAY provides a wide range of deposit and withdrawal methods, covering Asia, Europe, Africa, the Americas, and Oceania. The system is used in over 200 countries worldwide.

STICPAY supports payments via cards, local payment methods (e.g., PIX, PicPay, CODI, PromptPay), instant bank transfers, and transactions through its own e-wallet.

To enable payments through STICPAY, click 'Connect Provider' in the [showcase](#) and complete a short application form. You can also use the registration form on the [provider's website](#). After registration, a company representative will contact you to guide you through the next steps.

Once registered, you will gain access to your personal account, where you can find the necessary connection details, including the login and the API key. Login is your username in the STICPAY system, which is created during registration in the form of an email. To find your API key, click STICPAY API in the top menu:

The screenshot displays the STICPAY merchant account interface. At the top, there is a navigation bar with links: [About STICPAY](#), [Affiliates](#), [Forex Cashback](#), [iGaming Cashback](#), [User Guide](#), and [STICPAY API](#). A red arrow points to the [STICPAY API](#) link. Below the navigation bar, the main content area is titled **ACCOUNT** and **Account overview**. It contains a table with the following data:

Email	broker-merchant@sticpay.com	account	Verified
Account type	Merchant	Last Login	2025-03-26 18:29:30

Below the table, there is a section titled **Recent transactions** with a message: "There is no result for your search". On the left side, there is a sidebar menu with the following options: **ACCOUNT**, **MONEY TRANSFER**, **ALL HISTORY**, and **MONEY IN**.

Copy the key from the API Key (Live) field for a live environment or API Key (Sandbox) for a sandbox environment.

API

API Integration
WooCommerce


**STICPAY LOGO
DOWNLOAD**


**STICPAY API DOCUMENT
DOWNLOAD**


**USER MANUAL
DOWNLOAD**

API Merchant Integration

STICPAY API allows online merchants to use our payment services via Plug-in. It is designed to help online merchants start using STICPAY services as soon as the API is implemented.

To integrate STICPAY API, merchants need to fill out the form below and download "STICPAY API Document" for more instructions.

For futher inquiries on API, please email us at dev@sticpay.com

Enable	☒
Unique order_no	☐ If enabled, rejects payment/withdrawal requests with same order_no.
API Only	☐ If checked, only allow payments coming from the PAY API. Users won't be able to send you payments using Mypage. You can still allow some of them to do so using the field below.
API Key (Live)	The API key was already shown. If you lost it, please proceed with recover button: RECOVER
API Key (Sandbox)	API Key (Sandbox) : 159eac87ba8790a85y53a23307e538d3395904ct2f3d81d07d1661f27io4c2ll
Display Name	

MetaTrader 5 trading platform

Create a payment gateway configuration, select STICPAY for the gateway and enter the previously received credentials in the "Login" and "API Key" fields:

Payment Wallet: STICPAY Credit Card

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: STICPAY Credit Card

Gateway: STICPAY Main Trade Server, 1

Type: Card

☒ Deposit ☒ Push notification

☐ Withdrawal ☒ Email notification

☐ Account creation ☐ SMS notification

Login: broker-merchant@sticpay.com

API key: 159eac87ba8790a85y53a23307e538d3395904ct2f3d81d07d1661f27o4c21l

Automatic refunds are not supported. If a successful transaction is rejected, refunds must be created manually on the STICPAY side.

OK Cancel Help

MetaTrader 5 trading platform

In the 'Type' field, select a payment method:

- Map charts
- PIX for Brazil
- PicPay for Brazil
- CODI for Mexico
- PromptPay for Thailand
- Direct Banking fast interbank transfers
- STICPAY transfers via STICPAY e-wallet
- Maya for Philippines

If you want to use multiple payment methods, create separate wallet configurations.

System features and limitations

Refund operations through the platform are not supported. If you cancel a successful payment on the MetaTrader 5 side, you will need to manually create a refund on the STICPAY side.

Environment Configuration

STICPAY offers a sandbox environment, allowing you to test transactions. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox environment, use the appropriate API key from your personal account. Enter these credentials in your wallet settings, under the Common tab, and enable the 'Sandbox' option in the Parameters tab.

MetaTrader 5 trading platform

Payment Wallet: STICPAY Credit Card

CommonCurrenciesParametersCountriesGroupsCommissionsInformation



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Add

Edit

Delete

Default

Parameter	Value
 Sandbox	☒
 Callback URL	https://broker.com/api/callback/payments/sticpay

OKCancelHelp

Currency Configuration

The currency of transactions depends on the payment method:

- Card any currencies
- PIX BRL
- PicPay BRL
- CODI MXN
- PromptPay THB
- Direct Banking any currencies
- STICPAY any currencies
- Maya PHP

Depending on the method, specify the appropriate currency to prevent customers from selecting other currencies when making payments via the terminal. Also, set a limit on transaction amounts in accordance with STICPAY requirements.

Payment Wallet: STICPAY Credit Card

Common Currencies Parameters Countries Groups Commissions Information

 Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
 USD	0.00	unlimited	0.00	unlimited
+ click to add...				

Add

Edit

Delete

OK Cancel Help

Setting up callback requests

Callback requests are used to promptly receive payment statuses. In each transaction, the platform transmits a special URL, to which STICPAY should send the processing result. To ensure proper generation of the addresses, you need to configure the platform accordingly.

The use of callback requests is mandatory. Without them, you will not be able to receive transaction processing statuses. The exception is the payment method with the STICPAY wallet, which can work without Callback requests.

On the platform side, the callbacks are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). STICPAY will use this address to communicate with the platform, and the endpoint address for callback requests will be formed relative to it.
2. Associate the domain with the public IP address of one or more access servers. For further information, please see Integration\Web Services.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules:

<https://broker.com/api/callback/payments/sticpay>

- The first part is an example of a domain name.
 - The second part is a predefined part of the address that is used for all callback requests related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
 - The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.
5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. Please contact STICPAY for this list of addresses.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on `/api/callback/`. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
 <code>/api/callback/payments/sticpay</code>	3.113.93.177	STICPAY callback

6. Specify the callback address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

Payment Wallet: STICPAY Credit Card

Common

Currencies

Parameters

Countries

Groups

Commissions

Information



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
 Sandbox	☒
 Callback URL	<code>https://broker.com/api/callback/payments/sticpay</code>

Add

Edit

Delete

Default

OK

Cancel

Help

MetaTrader 5 trading platform

7. For enhanced security, STICPAY uses a whitelist of addresses from which the merchant is allowed to make requests to the API. Click STICPAY API in any section of your personal account, go to the 'Whitelist IPs' field, and specify a comma-separated list of public addresses of your trading servers on which the payment module operates:

Callback URL	https://broker.com/api/callback/payments/sticpay
Plain JSON callback	☒ If enabled, callback response will be formatted to plain JSON. *You will have to update callback parsing. Please test before applying to live account.
API Withdraw Base Wallet	☐ If enabled, API withdraw will automatically deduct from your base wallet when fund is not enough on ordered currency wallet
Retry count	3
Whitelist IPs	13.10.215.72,13.10.215.73 Comma separated values: xxx.xxxx.xxx.xxx, yyyy.yyyy.yyyy
Encryption Type	MD5

SUBMIT

Other Settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / ChipPay

ChipPay

ChipPay specializes in helping partners manage their clients' fiat and cryptocurrency payment and exchange needs, especially in regions across Asia where traditional PSPs may face limitations. The company offers a stable, high-performance payment gateway that operates 24/7 and supports T+0 fund settlements. With ChipPay, you can handle your funds securely while avoiding freezing risks.

To connect ChipPay payments, click 'Connect Provider' in the [showcase](#) and fill out a short online form. You can also use the registration form on the [provider's website](#). The company representative will contact you and will provide further instructions.

Generating a Key and Obtaining a MID

To ensure data security, the platform digitally signs each transaction. Uniques signatures are generated using asymmetric encryption:


- The private key is securely stored on the platform's side. It is used exclusively to sign transactions. This key is never shared externally.
- You provide ChipPay with the corresponding public key, which is used solely to verify the authenticity of signatures. It cannot be used to generate signatures.

This guarantees that only you can sign transaction data, ensuring that no one else can initiate payments on your behalf.

The system uses the standard SSL protocol for secure communication. You may generate your public and private key pair using any preferred method. Below is an example using the OpenSSL open-source library:

Go to the OpenSSL GitHub page and open the Binaries section:
<https://github.com/openssl/openssl/wiki/Binaries>. Download and install the appropriate OpenSSL distribution for Windows:

MetaTrader 5 trading platform



After installation, open the Command Prompt as an administrator. From the command line, navigate to the OpenSSL installation directory, for example:

```
CD C:\Program Files\OpenSSL-Win64\bin
```

Execute the following two commands in sequence:

```
openssl genpkey -out key.pem -algorithm RSA -pkeyopt rsa_keygen_bits:1024  
openssl rsa -in key.pem -outform PEM -pubout -out pub.pem
```

These commands will generate two files in the same directory:

- **pub.pem** your public key. Provide it to your ChipPay representative.
- **key.pem** your private key. Securely store it on the server where the MetaTrader 5 platform is installed. You will need to specify the path to this file when configuring the payment gateway.

Once the public key is received, ChipPay will issue your MID (Merchant Identifier), which serves as your unique ID within their system.

Provider Configuration

Create a payment gateway configuration, select ChipPay for the gateway, and specify the previously received MID in the "Login" field:

MetaTrader 5 trading platform

Payment Wallet: Chip Pay Crypto Payment

Common Currencies Parameters Countries Groups Commissions Information

 Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name:

Gateway:  ChipPay   Main Trade Server, 1 

Type:  Crypto 
 Crypto
 ChipPay - Express Payments China
 ChipPay - Pay P2P Payments
☐ Account creation

☐ Push notification
☐ Email notification
☐ SMS notification

Login:

Automatic refunds are not supported. If a successful transaction is rejected, refunds must be created manually on the ChipPay side.

OK Cancel Help

MetaTrader 5 trading platform

In the 'Type' field, select the payment method:

- **Crypto** deposit via cryptocurrency using a temporary intermediary wallet.
- **Chip Pay Express Payments China** deposit and withdrawal in CNY.
- **Chip Pay P2P Payments** deposit through ChipPay's P2P system, where the user purchases cryptocurrency for crediting to the broker's account.

To use multiple payment methods in parallel, create separate wallet configurations. Detailed descriptions of each payment method follow [below](#).

Next, navigate to the Parameters tab and specify the path to the private key file you generated earlier:

The screenshot shows the 'Payment Wallet: Chip Pay Crypto Payment' dialog box with the 'Parameters' tab selected. The dialog has a title bar with standard window controls. Below the title bar are tabs: 'Common', 'Currencies', 'Parameters' (active), 'Countries', 'Groups', 'Commissions', and 'Information'. A yellow folder icon is on the left, and a text instruction reads: 'Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.' Below this are 'Up' and 'Down' buttons. A table with two columns, 'Parameter' and 'Value', contains three rows: 'Sandbox' with a checkbox, 'Private Key Path' with the value 'E:\work\chippay\key.pem', and 'Callback URL' with a truncated URL. To the left of the table are buttons: 'Add' (with a dropdown arrow), 'Edit', 'Delete', and 'Default'. At the bottom right are 'OK', 'Cancel', and 'Help' buttons.

Parameter	Value
Sandbox	☐
Private Key Path	E:\work\chippay\key.pem
Callback URL	https://broker.com/api/callback/payments/chippay...

System Features and Limitations

Crypto deposits are implemented as follows:

- When a user initiates a deposit through the Crypto method and specifies an amount in MetaTrader 5, ChipPay generates a unique cryptocurrency wallet and displays it on the payment page. The user must transfer the exact requested amount in the specified cryptocurrency to the provided wallet address.
- During the payment lifetime (12 hours in the production environment and 24 hours in the test environment), the user can transfer funds to the specified wallet in any amount and in any supported cryptocurrency. If the amount transferred is less than requested or if the currency differs, the transaction will be marked as unsuccessful. If the amount exceeds the requested sum, the payment will be successful, but the excess funds will not be accounted for or refunded.
- All funds transferred by the user are credited to the broker's ChipPay account.
- For each top-up, ChipPay sends transaction data to MetaTrader 5 for accurate reconciliation in the broker's payment records.



Order Details

Order No: 4656
Amount: 0.02 BTC
Valid Period: 23:26:52

Deposit Records




No Records Yet.

Reminder

- Please take note that if there is any charges on the original platform which the withdrawal request initiated, it might affect the actual amount you received.
- Please ensure the computer and website browsers are safe to prevent messages

BTC



BTC



① Please note :

The order is only valid for **24 hours** , if you deposit after this period, the amount will not be received and no refund will be provided.

The P2P Payments method uses ChipPay's internal exchange. The user selects a counterparty from a list and purchases USDC using CNY. Other currencies are not supported in this method. Supported payment methods include: bank card, AliPay, WeChat, etc. After successful payment, the equivalent USD amount is credited to the broker's ChipPay account. ChipPay's internal exchange rate is used for conversion.



Buy USDC

Orders

KYC

USDC 1000.00

Payment

Search

Refresh in 8 sec

T1

Trader 1

Price 7.20 CNY

Single limit 100.00-1,000.00 USDC

720.00-7,200.00 CNY

Accept payments from ethnic minority

Bank statement required



Buy

T2

Trader 2

Price 7.30 CNY

Single limit 10.00-20,000.00 USDC

MetaTrader 5 trading platform

The Express Payments China method also uses the internal ChipPay exchange. The user selects a counterparty, transfers CNY via P2P, and the counterparty transfers the equivalent amount in cryptocurrency to the broker's wallet. Before proceeding with the transfer, the user must provide their name and phone number. By default, these fields are auto-filled using information from the user's account.

This Express Payments China method also supports withdrawals to a bank card.

Setting Up the Environment

ChipPay supports operations in a sandbox environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To connect to the sandbox, ChipPay will assign you a separate test MID. Enter it in your wallet settings, under the Common tab, and enable the 'Sandbox' option in the Parameters tab.

The screenshot shows the 'Payment Wallet: Chip Pay Crypto Payment' dialog box with the 'Parameters' tab selected. The dialog has a title bar with standard window controls. Below the title bar is a tabbed interface with 'Common', 'Currencies', 'Parameters', 'Countries', 'Groups', 'Commissions', and 'Information'. The 'Parameters' tab is active, displaying a folder icon and a message: 'Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.' On the left side of the Parameters tab, there are buttons for 'Up', 'Down', 'Add', 'Edit', 'Delete', and 'Default'. The main area contains a table with two columns: 'Parameter' and 'Value'.

Parameter	Value
↕ Sandbox	☐
ab Private Key Path	E:\work\chippay\key.pem
ab Callback URL	https://broker.com/api/callback/payments/chippay...

At the bottom of the dialog are 'OK', 'Cancel', and 'Help' buttons.

Currency Settings

Depending on the method, specify the appropriate currency to prevent customers from selecting other currencies when making payments via the terminal.

- **Crypto** a full list of supported cryptocurrencies is available in the documentation:
<https://open.chippay.com/api/EnaddExchangeOrder.html#10202>. Currencies with names longer than three characters are not currently supported.
- **Chip Pay Express Payments China** only CNY.
- **Chip Pay P2P Payments** Chip Pay P2P Payments only USD and CNY. USD deposits are converted 1:1 to USDT when credited to the user's account. For CNY payments, the user is credited in CNY, while the broker receives an equivalent amount in USDT, converted at ChipPay's internal exchange rate.

You must also set transaction limits in accordance with ChipPay's guidelines.

Payment Wallet: Chip Pay Crypto Payment

Common Currencies Parameters Countries Groups Commissions Information

Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdrawal	Max. Withdrawal
\$ BTC	0.00	unlimited	0.00	unlimited
\$ ETH	0.00	unlimited	0.00	unlimited
\$ DAI	0.00	unlimited	0.00	unlimited
\$ ADA	0.00	unlimited	0.00	unlimited
\$ BCH	0.00	unlimited	0.00	unlimited
\$ LTC	0.00	unlimited	0.00	unlimited
\$ XRP	0.00	unlimited	0.00	unlimited
\$ SOL	0.00	unlimited	0.00	unlimited
\$ BNB	0.00	unlimited	0.00	unlimited
\$ ETC	0.00	unlimited	0.00	unlimited
\$ POL	0.00	unlimited	0.00	unlimited
+ click to add...				

Add Edit Delete

OK Cancel Help

Setting up callback requests

Callback requests are used to promptly receive payment statuses. In each transaction, the platform transmits a special URL, to which ChipPay should send the processing result. To ensure proper generation of the addresses, you need to configure the platform accordingly.

The use of callback requests is mandatory. Without them, you will not be able to receive transaction processing statuses.

On the platform side, the callbacks are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). ChipPay will use this address to communicate with the platform, and the endpoint address for callback requests will be formed relative to it.
2. Associate the domain with the public IP address of one or more access servers. For further information, please see Integration\Web Services.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules:

<https://broker.com/api/callback/payments/chippay>

- The first part is an example of a domain name.
- The second part is a predefined part of the address that is used for all callback requests related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
- The third part is defined by you. You can specify any address, but we strongly recommend using a logical and clear naming system. Depending on the type of payment method selected, the following addresses are substituted into the Callback URL parameter in the default gateway settings:
 - ◆ Crypto .../api/callback/payments/[chippay_crypto](#)
 - ◆ Chip Pay Express Payments China .../api/callback/payments/[chippay_exp](#)
 - ◆ Chip Pay P2P Payments .../api/callback/payments/[chippay_p2p](#)

5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. Please contact ChipPay for this list of addresses.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on `/api/callback/`. The list is used for all access servers.

Callback domain:

- Up
- Down
- Add
- Edit
- Delete

URL	Allowed IPv4/IPv6	Comment
✓ <code>/api/callback/payments/chippay_crypto</code>	52.221.89.244, 13.229.201.117	ChipPay callback

6. Specify the callback address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. Please make sure to specify a full address. The URL must include a domain name. Specifying an IP address is not allowed.

Payment Wallet: Chip Pay Crypto Payment

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
↕ Sandbox	☐
ab Private Key Path	E:\work\chippay\key.pem
ab Callback URL	https://broker.com/api/callback/payments/chippay...

Add ▼

Edit

Delete

Default

OK Cancel Help

Other Settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / [Payment Gateways](#) / Uniwire

Uniwire

Uniwire is a crypto payments system you can shape to your changing environment. You can accept, convert, pay out, and store a wide range of cryptocurrencies. The company specializes in enterprise-level solutions tailored to the unique needs of brokers and exchanges. Its multi-chain platform, Uniwire, supports BTC, ETH, LTC, SOL, MATIC, TRX, XRP, TON, Bitcoin Lightning, stablecoins such as USDT and USDC, and much more.

To connect Uniwire payments, click 'Connect Provider' in the [showcase](#) and fill out a short online form. You can also use the registration form on the [provider's website](#). The company representative will contact you and will provide further instructions.

Creating a Key

After registration, you will be given access to your [personal account](#), where you can find details for connecting the provider. Open 'Settings \ API Keys' and select 'New API Key'.

The screenshot displays the MetaTrader 5 web interface for managing API keys. The top navigation bar includes links for 'Broker', 'Hi, broker', 'Support', 'Website', and 'Logout'. The main content area is titled 'API Keys > New API Key'. On the left, a sidebar menu shows 'Settings' selected, with 'API Keys' highlighted. The 'New API Key' form contains the following fields:

- Name ***: A text input field containing 'MetTrader'. Below it, a note says 'Give name for your own recognition.'
- Max Payout**: A text input field containing '5000' and a dropdown menu set to 'USD'. Below it, a note explains: 'If payouts are allowed - limit maximum amount in USD per payout. Any amount over limit will require approval in the app. Such payouts can be also approved using API keys with special "Approve" permissions.'
- Whitelist IP's**: A text input field. Below it, a note says: 'Restrict access to trusted IPs only (Recommended). Write each address in new line.'
- Permissions ***: A table with three columns: 'Select all', 'Select all', and 'Select all'. The rows are 'Invoices', 'Transactions', and 'Payouts'. Each row has three radio button options: 'None' (selected), 'Read only', and 'Full access'. The 'Payouts' row also has an 'Approve' option.

	Select all	Select all	Select all
Invoices	☒ None	☐ Read only	☐ Full access
Transactions	☒ None	☐ Read only	☐ Full access
Payouts	☒ None	☐ Read only	☐ Full access
			☐ Approve

MetaTrader 5 trading platform

Specify any name to distinguish the key used for MetaTrader 5 from others. For added security, you can enter a list of public IP addresses of your trading servers in the "Whitelist IPs" field. This ensures that the system will only interact with your platform. Next, enable all permissions and click 'Save Key'.

API Keys » MetaTrader

API Key was saved successfully.

Name *	MetaTrader	
	Give name for your own recognition.	
Max Payout		USD
	If payouts are allowed - limit maximum amount in USD per payout. Any amount over limit will require approval in the app. Such payouts can be also approved using API keys with special "Approve" permissions.	
Whitelist IP's		
	Restrict access to trusted IPs only (Recommended). Write each address in new line.	
API Key	fcd9d104d34d498e9f6996d295281b63	
	API public key.	
API Secret	36Kvy6GiiFbDGIFA8cXN81Ny0Bt69s2sWg9ajwBsximH	Hide
	API secret for signing requests. Keep it safe!	

MetaTrader 5 trading platform

Copy the generated API Key and API Secret.

Provider Configuration

Create a payment gateway configuration, select Uniwire as your gateway, and specify

- API Key in the "Login" field
- API Secret in the "Password" field

Payment Wallet: Uniwire Invoice

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: Uniwire Invoice

Gateway: Uniwire Main Trade Server, 1

Type: Crypto - Uniwire Invoice

☒ Deposit ☒ Push notification

☐ Withdrawal ☒ Email notification

☐ Account creation ☒ SMS notification

Login: fcd9d104d34d498e9f6996d295281b63

Password:

Automatic refunds are not supported. If a successful transaction is rejected, refunds must be created manually on the Uniwire side.

OK Cancel Help

MetaTrader 5 trading platform

In the 'Type' field, select the payment method:

- Invoice cryptocurrency deposit.
- Payout withdrawal of funds to a crypto wallet.

If you want to use multiple payment methods, create separate wallet configurations.

Open the Profiles section in your personal account and select 'New Profile':

Broker ▾ Hi, broker Support Website Logout

Profiles >> New Profile

Dashboard Invoices Transactions Payouts Conversions Profiles Wallets Settings

Edit Profile

Profile Name * MetaTrader
For internal use. Name profile for your own recognition.

Callback URL https://broker.com/api/callback/payments/cryptochill
Optional. URL for payment notifications.

Notification Email finance@broker.com
Optional. Email address(es) for payment notifications. Separate by comma for multiple addresses.

Email Notifications:

Invoices	☐ Pending	☐ Confirmed	☐ Complete	☐ Incomplete
Transactions	☐ Pending	☐ Confirmed	☐ Complete	☐ Quarantined
Payouts	☐ Pending	☐ Confirmed	☐ Complete	

Invoice Expiration * 15 minutes
Period after which invoices will expire. Used for fiat to cryptocurrency price lock. Can be overridden per invoice and expiration can be renewed in the Invoice public link view. All payments to address still can be made after invoice expiration and most recent exchange rates will be used for fiat calculation.

MetaTrader 5 trading platform

Specify any name to distinguish the profile used for MetaTrader 5 from others. At the bottom of the page, select the currencies you plan to work with:

Enabled Currencies				
Currency	Is Enabled	Wallet *	Min Confirmations *	Custom Fee
Bitcoin (BTC)	☒	Bitcoin ⇅	1 ⇅	
Bitcoin 0-Conf **	☐			
Ethereum (ETH)	☒	Ethereum ⇅	1 ⇅	

For each selected currency, choose the wallet that will be used to track all related transactions. Uniwire will create the necessary wallets for you.

Save the profile and copy its ID from the list:

Broker ▾

Hi, broker

Support

Website

Logout

Profiles

+ New Profile

Dashboard

Invoices

Transactions

Payouts

Conversions

Profiles

Wallets

Settings

Profile name	Currencies	Properties	ID
MetaTrader	BTC, ETH	Callback URL	8ppff3ty-738b-795f-456...

MetaTrader 5 trading platform

Then, open the wallet configuration on the MetaTrader 5 side, go to the "Parameters" tab, and enter the profile ID in the 'Profile ID' field.

Payment Wallet: Uniwire Invoice

Common Currencies **Parameters** Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up
Down


Parameter	Value
ab Callback Token	T5vU8fiv2J8kji5tO01Y3pGw3jvbu3Y
ab Profile ID	8ppff3ty-738b-795f-4566-9db32e392921
ab Callback URL	/api/callback/payments/uniwire_invoice

Add ▼
Edit
Delete
Default

OK Cancel Help

Setting Up the Environment

Uniwire supports operations in a sandbox environment. In this environment, the provider simulates transaction processing so that you can check how payments work, without performing real money transactions. To switch between environments, use your personal account dashboard:



The screenshot shows the top navigation bar of the MetaTrader 5 personal account dashboard. It includes a 'Broker (Testnet)' dropdown menu, a 'Hi, broke' user greeting, and a 'Total \$4,057' balance display. Below the navigation bar, there are buttons for '+ Invoice' and '+ Payout'. A table lists the wallets, with columns for 'Wallet', 'Pending', 'Reserved', 'Balance', and 'In US'. The table shows two entries: 'Ethereum Testnet' with a balance of 1.60690019 ETH and 'Bitcoin Testnet' with a balance of 0.0003364 BTC.

Wallet	Pending	Reserved	Balance	In US
Ethereum Testnet	-	-	1.60690019 ETH	\$4,02
Bitcoin Testnet	-	-	0.0003364 BTC	\$3

The payment module automatically determines the type of transaction based on the system's responses and, if necessary, marks it as a test transaction.

Currency Settings

When making a deposit or withdrawal, the user specifies two currencies:

- The currency in which they want to deposit or withdraw funds. This is set in the wallet settings.
- The currency they will actually use for the transaction – the one the merchant or broker will receive or send. Available options are configured in the [Profiles](#) section of your personal account.

Deposit to account 15802: John Smith

[Back to Payments](#)

Deposit amount:

USD

USD



The payment amount will be converted to your trade account currency (USD) automatically

Choose a payment method:

PayPal



Wire Transfer

VISA



**Crypto
Payment**

Payment service provider:

Uniwire



Cryptocurrency Chain:*

BTC



Continue

Payment details are entered on the relevant payment system side. Your broker has no access to this data. If you have any problems with the money transfer, please contact the broker with whom you opened this trading account.

MetaTrader 5 trading platform

Currencies are converted using Uniwire's internal exchange rate.

To specify the currencies users will use for deposits or withdrawals, open the "Currencies" tab in the wallet settings. Only currencies with three-letter codes are supported. You can also set transaction amount limits in this section.

Payment Wallet: Uniwire Invoice

Common Currencies Parameters Countries Groups Commissions Information

Please specify the currencies that will be processed by this wallet. Empty list means that payments are accepted in any currencies.

Currency	Min. Deposit	Max. Deposit	Min. Withdra...	Max. Withdra...
USD	0.00	unlimited	0.00	unlimited
BTC	0.00	unlimited	0.00	unlimited
LTC	0.00	unlimited	0.00	unlimited
ETH	0.00	unlimited	0.00	unlimited
TRX	0.00	unlimited	0.00	unlimited
POL	0.00	unlimited	0.00	unlimited
XRP	0.00	unlimited	0.00	unlimited
PAX	0.00	unlimited	0.00	unlimited
DAI	0.00	unlimited	0.00	unlimited
EUR	0.00	unlimited	0.00	unlimited
GBP	0.00	unlimited	0.00	unlimited
AUD	0.00	unlimited	0.00	unlimited
CAD	0.00	unlimited	0.00	unlimited
CHF	0.00	unlimited	0.00	unlimited

Add Edit Delete

OK Cancel Help

Setting up callback requests

Callback requests are used to promptly receive payment statuses. In each transaction, the platform transmits a special URL, to which Uniwire should send the processing result. To ensure proper generation of the addresses, you need to configure the platform accordingly.

The use of callback requests is optional. However, if you do not configure them, updating payment statuses may take longer. This could negatively impact the quality of your customer service. In addition, callback requests are used to process delayed deposits:

- When initiating a deposit, the user is provided with an address in the selected blockchain to transfer the funds.
- If the user does not complete the transfer within 15 minutes, Uniwire will mark the transaction as expired and mark it as failed.
- However, the payment address issued to the user will remain valid without any restrictions. If the user later transfers funds to this address, Uniwire will send a callback request to the platform with an updated payment status.
- If your system is configured to handle callback requests, the funds will be successfully credited to the user's account in MetaTrader 5.

On the platform side, the callbacks are received and processed by access servers. To configure notifications:

1. Register a domain (or subdomain for your existing domain). Uniwire will use this address to communicate with the platform, and the endpoint address for callback requests will be formed relative to it.
2. Associate the domain with the public IP address of one or more access servers. For further information, please see Integration\Web Services.
3. Add an SSL certificate for the specified domain in the Integration\Web Services section. The operation requires a certificate issued by a trusted certification authority, while self-signed certificates are not allowed even in a sandbox environment. Operation is only possible via the HTTPS protocol. HTTP is not supported.
4. Choose an endpoint address for receiving callback requests. The address is specified relative to the previously selected domain, taking into account the following rules:

<https://broker.com/api/callback/payments/uniwire>

- The first part is an example of a domain name.
- The second part is a predefined part of the address that is used for all callback requests related to payment systems. For example, callbacks to <https://broker.com/api/callback/my/callback> will not reach wallets.
- The third part is defined by you. You can enter any address, however we strongly recommend using a logical and clear naming system.

MetaTrader 5 trading platform

5. Add the selected URL to the allowed list in the Web Services section and specify the list of IP addresses, from which the payment provider will send transaction status notifications. Please contact Uniwire for this list of addresses.

Web Services

Please specify a list of addresses, from which the platform will accept and process callbacks on /api/callback/. The list is used for all access servers.

Callback domain:

Up

Down

Add

Edit

Delete

URL	Allowed IPv4/IPv6	Comment
 /api/callback/payments/uniwire	3.218.251.136,54.157.91.227	Uniwire Callback

6. Specify the callback address in the Callback URL parameter in the payment gateway settings. The system will use it to attribute the received request to the relevant wallets. The address must be specified without the domain name.

MetaTrader 5 trading platform

Payment Wallet: Uniwire Invoice

Common

Currencies

Parameters

Countries

Groups

Commissions

Information



Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
ab Callback Token	T5vU8fiv2J8kji5tO01Y3pGw3jvbu3Y
ab Profile ID	8ppff3ty-738b-795f-4566-9db32e392921
ab Callback URL	/api/callback/payments/uniwire_invoice

Add

Edit

Delete

Default

OK

Cancel

Help

7. Open the previously created profile in your Uniwire personal account and click 'Edit Profile'. Specify the full address for callback requests, including the domain, in the Callback URL field.

Broker ▾
 Hi, broke

Profiles » MetaTrader

Profile Details

Name	Development
Callback URL	
Notification Email	-
Invoice Expiration	15 minutes
Monitor Addresses	1 hour

Edit Profile

Broker ▾
 Hi, broke

Profiles » MetaTrader » Edit Profile

Edit Profile

Profile Name *	Development For internal use. Name profile for your own recognition.
Callback URL	https://broker.com/api/callback/payments/cryptochill Optional. URL for payment notifications.

8. Open the 'Settings \ API Keys' section in your Uniwire account and copy the 'Callback Token' value

API Keys

+ New API Key

Name	API Key	Permissions	Created
MetaTrader	fcd9d1...	Full access: Account, Auto-Conversions, Auto-Funding, Auto-Payouts, Conversions, Exchange-Rates, Invoices, Payouts, Profiles, Transactions, Wallets Read only: Api-Keys	43 minutes ago Show requests

API Callbacks

Callback Token

T5vU8fiv2J8kiji5tO01Y3pGw3jvbu3Y

Use this token to verify incoming callbacks. [Documentation](#)

Hide

MetaTrader 5 trading platform

Add the value to the corresponding wallet parameter on the MetaTrader 5 side:

Payment Wallet: Uniwire Invoice

Common Currencies Parameters Countries Groups Commissions Information

 Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Up

Down

Parameter	Value
ab Callback Token	T5vU8fiv2J8kji5tO01Y3pGw3jvbu3Y
ab Profile ID	8ppff3ty-738b-795f-4566-9db32e392921
ab Callback URL	/api/callback/payments/uniwire_invoice

Add ▼

Edit

Delete

Default

OK Cancel Help

Other Settings

All other settings are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details, please visit the [Payment Gateways](#) section.

MetaTrader 5 Trading Platform / Platform Setup / Payments / Payment Gateways / Bank Transfer

Bank Transfer

This payment processing option does not require integration with third-party online systems. It significantly facilitates and automates operations with bank transfers. By setting up bank transfers in the platform, you will receive a convenient payment processing tool. An option for depositing and withdrawing funds through bank transfers will appear in client terminals.

Create a payment gateway configuration and select "Bank transfer" as the gateway:

Payment Wallet: Bank Transfer

Common Currencies Parameters Countries Groups Commissions Information

Integrate your platform with a payment system using a server plugin. Request the parameters from the chosen service provider.

☒ Enable

Name: Bank Transfer

Gateway: Wire Transfer Trade Main, 1

Type: Wire Transfer

☒ Deposit ☒ Push notification

☒ Withdrawal ☒ Email notification

☐ Account creation

OK Cancel Help

All other settings, except the Parameters section, are standard and do not differ from other gateways. You can set up currencies, commissions, gateway access by country, group, etc. For further details please visit the [Payment Gateways](#) section.

The Parameters section provides settings for account deposits via bank transfer. They will be discussed below.

Deposits

To make a deposit, the user selects the appropriate option in the terminal's payments section:

Deposit to account 3805827: John Smith

[Back to Payments](#)

Choose a payment method:

☒  HSBC Hong Kong, USD

Choose the payment system currency:

USD ▼

The payment amount will be converted to your trade account currency (USD) automatically

Specify the desired deposit amount:

1000

USD

At least 10 USD

Continue

Next, the user is forwarded to the page with the invoice, which should be paid. This page is customizable. When an invoice page is opened, an active payment with the "Processing" status is created in the system. A unique internal number is automatically assigned to it.

Bank Transfer Instruction to depositing...

[Back to Payments](#)

[Download](#)
[Confirm](#)
[Reject](#)



Broker

accounts@broker.com

https://www.broker.com

Invoice #358

Date 2023.07.18
 Client John Smith
 Address Cyprus
 Email john.smith@mail.com

Description	Amount
Invoice 358, deposit account 3805827	1 000.00

Amount to be paid: **1 000.00 USD**

Enter this exact details on the bank wire transfer form:

Bank HSBC Hong Kong
 Bank address 1 Queen's Road Central, Hong Kong
 Bank SWIFT / BIC HSBCHKH HKH
 Beneficiary Broker
 Beneficiary address Cyprus
 Beneficiary account 1324567890
 Payment details Deposit Agreement 3805827
 Amount 1 000.00 USD

After checking the invoice, the client must confirm or decline it. Confirmation means that all data is correct, and the user will pay the invoice. After that, the payment's status in the system changes to "Pending". If the client declines the invoice for some reason, the payment record is deleted from the platform in order not to overload the database.

Next, you should check the receipt of money in your bank account. Once you receive the money, confirm the payment through the Manager terminal. Immediately after that, the amount will be credited to the client's trading account as a separate balance operation.

Configuring invoices for bank transfers

An invoice is generated in the terminal based on the template, which is located in the file [main server directory]\templates\bank_transfer\default.htm. You can modify the template, but be careful with the macros, which substitute company, payment, and bank details in the template text. You can also create different template versions for different languages.

Macro values for the company and bank details are taken from the payment gateway settings:

- <!--COMPANY_LOGO--> company logo, the 'Company Logo Url' parameter. In the gateway settings, the value can be filled in with a link to the corresponding image hosted on a publicly accessible site.
- <!--COMPANY_NAME--> company name, the 'Company Name' parameter. If the parameter is not filled in the gateway settings, the name will be taken from the client group settings.
- <!--COMPANY_ADDRESS--> company address, the 'Company Address' parameter.
- <!--COMPANY_PHONE--> company phone number, the 'Company Phone' parameter.
- <!--COMPANY_EMAIL--> company email, the 'Company Email' parameter. If the parameter is not filled in the gateway settings, the name will be taken from the client group settings.
- <!--COMPANY_WEBSITE--> company website, the 'Company Website' parameter. If the parameter is not filled in the gateway settings, the name will be taken from the client group settings.
- <!--COMPANY_RESPONSIBLE_OFFICER--> the name of the company employee, the 'Company Responsible Officer' parameter.
- <!--COMPANY_SIGNATURE--> the signature of the company employee, the 'Company Signature Url' parameter. In the gateway settings, the value can be filled in with a link to the corresponding image hosted on a publicly accessible site. If you cannot place the company's seal and the responsible officer's signature on publicly available resources for security reasons, you can add images to the template in binary form. For example: .
- <!--COMPANY_SEAL--> company's seal, the 'Company Seal Url' parameter. In the gateway settings, the value can be filled in with a link to the corresponding image hosted on a publicly accessible site.
- <!--WALLET_BANK--> bank name, the 'Bank' parameter.

MetaTrader 5 trading platform

- <!--WALLET_BANK_ADDRESS--> bank address, the 'Bank Address' parameter.
- <!--WALLET_BANK_SWIFT--> bank's SWIFT/BIC, the 'Bank SWIFT/BIC' parameter.
- <!--WALLET_BENEFICIARY--> account holder name, the 'Beneficiary' parameter.
- <!--WALLET_BENEFICIARY_ADDRESS--> account holder's address, the 'Beneficiary Address' parameter.
- <!--WALLET_BENEFICIARY_ACCOUNT--> account number or IBAN, the 'Beneficiary Account / IBAN' parameter.

Payment Wallet: Bank Transfer

Common Currencies Parameters Countries Groups Commissions Information

Configure the payment wallet to allow deposits and withdrawals straight in the platform. Please request the relevant parameters from the selected service provider.

Parameter	Value
ab Bank	HSBC Hong Kong
ab Bank Address	1 Queen's Road Central, Hong Kong
ab Bank SWIFT / BIC	HSBCHKHCHKH
ab Beneficiary	Broker
ab Beneficiary Address	Cyprus
ab Beneficiary Account / IBAN	1234567890
ab Company Name	Broker
ab Company Address	+3572222222
ab Company Phone	accounts@broker.com
ab Company Email	https://www.broker.com
ab Company Website	John Smith, CEO
ab Company Responsible Officer	https://www.broker.com/i/logo.png

Add Edit Delete

OK Cancel Help

MetaTrader 5 trading platform

Payment data is also filled in using macros, but their values are determined directly by the operation. Their description is available under the payment gateways section.

Client data is filled in using the following macros:

- <!--CLIENT_NAME--> client's name.
- <!--CLIENT_ADDRESS--> client's address.
- <!--CLIENT_PHONE--> client's phone number.
- <!--CLIENT_EMAIL--> client's email.

Values for the macros are taken from account data on the server.

Withdrawals

To withdraw funds, the user selects the appropriate option in the terminal's payments section: This will open a form for specifying bank details to which funds from the trading account will be transferred.

Withdraw from account 3805827: John Smith

[Back to Payments](#)

Available funds: 35 811 USD

Choose a payment method:

☒  Wire Transfer

Bank Name:

Bank Code / SWIFT:

Bank Account / IBAN:

Full Name:

TIN:

Billing address:

Country:

Postal Code:

Payment details:

Choose the payment system currency:

The withdrawal amount will be converted to the payment system currency (USD) automatically

Specify the desired withdrawal amount:

Continue

MetaTrader 5 trading platform

Once the form is filled out, an active payment with the "Waiting" status is created in the platform. A unique internal number is automatically assigned to it. This payment stores the details specified by the user. When the transaction is created, a balance operation to debit funds is immediately performed on the user's trading account. In fact, funds are blocked to prevent users from withdrawing more than they actually have.

Withdrawal #360: 1 000.00 USD c 3805827, John Smith, real\payments ? X

General

Details

Details

Customer Full Name
John Smith

Customer TIN
777777777

Bank Name
HSBC Hong Kong

Bank Code
HSBCHKHHHKH

Bank Account
123456789

Billing Address 1
1, Ledra

Billing Country
CY

Billing Postcode
1000

Cancel Update

MetaTrader 5 trading platform

Next, your accountant should make a bank transfer to the specified details. After that the payment must be confirmed through the Manager terminal.

If the transfer cannot be completed for some reason, the payment should be rejected. In this case, the amount of the failed operation will be automatically credited back to the trading account as a separate balance operation. The comment of the operation will contain "rollback #[withdrawal operation ticket]".

MetaTrader 5 Trading Platform / Platform Setup / Payments / Payment Processing Rules

Payment Processing Rules

You can flexibly customize payment processing depending on various parameters. For example, you can automatically confirm card transactions within a certain amount limit, always manually process bank transfers, or track withdrawals for customers registered less than a month ago. Almost any parameters of a trading account, as well as parameters of wallets and operations, can be used as conditions.

Rules are configured separately for withdrawal and deposit operations. The parameters are the same, except for the availability of some conditions.

By default, no payments are allowed. You must create at least one allow rule with the required set of conditions.

Checking the Rules


The rules are checked from top to bottom. If the operation matches the conditions of the upper rule, it is processed in accordance with it; if not, the next rule is checked, and so on. The rules are checked until the transaction is confirmed, rejected, or sent to the manager for processing.

To change the position of the rules, use the "↑ Move Up" and "↓ Move Down" commands in the context menu or toolbar. Whenever you change the list of rules, all operations currently in processing are checked again.

Creating a Rule

Open the rules section for withdrawals or deposits and create a new entry.

MetaTrader 5 trading platform



In Common settings, specify the following:

- **Name** the name of the rule. Set descriptive names which reflect the idea of the action. This will ensure efficient control when you add multiple rules to the system.
- **Description** a more detailed description of the rule.
- **Action** the action to be applied to the operation that matches the rule conditions:
 - ◆ **Accept automatically** the operations will be confirmed manually without requiring manual confirmation.
 - ◆ **Accept manually** the operations will be forwarded to the manager for confirmation. For bank transfers, the processing is always manual, even if the rule sets automatic confirmation.
 - ◆ **Reject** operations will be rejected immediately.


Rule Specifics

The rules apply in different ways, depending on the transaction type:

- For deposits, the rules are checked twice. The first check is implemented after the user performs a transaction in the client terminal. If the rules do not require the rejection of the operation, the request is sent to the payment provider. After the transaction is successfully completion in the payment system, the rules are checked again. With manual confirmation, the manager will receive a request for processing; with automatic confirmation, the funds will be immediately credited to the trader's trading account as a balance operation.
- For withdrawal operations, the rules are checked once, before sending the request to the payment provider.

Rule Conditions

Having configured common rule parameters, describe rule trigger conditions.



Comparison Types

Standard comparison types are available for all conditions:

- Equal (=)
- Not equal (!=)
- Greater than (>)
- Greater than or equal (>=)
- Less than (<)
- Less than or equal (<=)

For string conditions, such as the group name or a comment, the Match Mask condition is also available. Here you can specify strings with the "*" mask.

- Condition "Ggroup", value "real*" = all real groups.
- Condition "Comment", value "*vip*" = all accounts, comments of which contain the string "vip".

The following conditions are available:

Schedule

These parameters set date and time conditions. The rule is triggered if the user performs an operation on the specified date or time.

Accounts

These settings specify conditions based on account parameters:

MetaTrader 5 trading platform

- **Login** the rule is triggered for the specified account. You can specify a comma-separated list of values and value ranges. For example 100,102,107,120-130.
- **Group, Country, City, Color, Comment** the rule is triggered for the account from the specified group, country, city, etc. For example, if the group is set to "real*", then the rule will be triggered only for real accounts. If you specify "Argentina" as the country, then the rule will be applied to accounts from Argentina. The condition works similarly for other account parameters.
- **Registration** the condition is set relative to the account creation date in the platform. Specify the date and the comparison type: equal to, less than, or greater than. Accordingly, the condition will be triggered for accounts registered on the specified date, earlier or later than this date. For example, if you specify "Registration > 2020.09.01", The rule will only be triggered for accounts created after the specified date.
- **Last visit** the condition is set relative to the last connection of the account to the platform. Specify the date and the comparison type: equal to, less than or greater than. Accordingly, the condition will trigger for accounts connected on the specified date, earlier or later than this date. For example, if you specify "Last visit > 2023.01.01", then the rule will be triggered for accounts that last connected to the platform after the specified date.
- **Balance** the condition is set relative to the current account balance; the amount is specified in the deposit currency. Using this condition, you can set up rules for large customers.
- **Credit** is similar to the "Balance" condition. In this case, the amount of credit funds on the account is checked.
- **Floating profit, Equity, Margin, Free margin, Margin level** these conditions are similar to the "Balance" condition. Appropriate trading account states are checked here.
- **Deposit currency** condition regarding account deposit currency. For example, if you specify "EUR*", the rule will only apply to EUR-based accounts.

You can create an unlimited number of rules to cover any situation.

Payment

These settings specify conditions based on the payment transaction parameters:

- **Amount** the transaction amount. Using this option, you can automatically approve payments up to a certain amount, while transferring larger payments to managers for manual confirmation.
- **Currency** transaction currency.
- **Wallet** the wallet via which the transaction is performed.
- **Gateway** the gateway via which the transaction is performed.

Check

This is an additional group of conditions for checking operations:

- **Verify unbalanced withdrawal** this is a true/false condition. It checks if the user withdraws more funds than they deposited through the same wallet or more than they have earned. The condition allows additional measures to be

taken to combat potential money laundering. For example, if you allow transferring funds between accounts, you can enable additional control over withdrawal operations by the manager who will check how much money the user withdraws.

- Verify cardholder name – a true/false condition. It checks whether the name specified on the card in the completed payment matches the client's name indicated in the trading account. The condition enables additional protection against fraud using stolen cards. With this verification, you can create rules that will automatically reject suspicious payments or send them for additional manual verification to managers.


Verification features:

- - ◆ When making transactions, users enter data (including name) not in the platform but on the payment provider's page. Therefore, the platform can check the card name only after the transaction has been completed and only if the payment provider sends this information to the platform. At the moment, the transfer of the necessary data is supported by Unlimit, ECOMMPAY, emerchantpay and Exactly.
 - ◆ A name can be verified before performing a transaction only if the provider supports card linking and allows further transactions only using previously authorized cards.
 - ◆ If you enable name checking, but the provider does not support the transfer of the necessary data, all checks will fail: in all cases, the system will consider that the name does not match.
 - ◆ In the trading account, the client's name is indicated in three separate fields: First Name, Last Name, Middle Name. The system compares any combination of these fields (Last Name+Middle Name, Middle Name+Last Name, First Name+Last Name, First Name+Last Name+Middle Name, etc.) with the cardholder field. The check is case insensitive.

MetaTrader 5 Trading Platform / Platform Setup / Payments / Controlling Payments

Controlling Payments

Service usage can be monitored using the Active and History sections. The sections feature the transactions that are currently being processed by managers, as well as the history of completed/rejected transactions.



MetaQuotes - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Import Export Apply + Settings X Navigation Sort

Payments

- Active
- History
- Accounts
- Wallets
 - Trade Main
- Deposit Rules
- Withdrawal Rules
- Gateways
- Data Feeds
- Plugins
- Reports
- ECN
- Routing

ID	Login	Action	State	Created	User Amount	User Curre...
333	3825992	deposit	done	2023.07.07 10:33:38	1 000.00	USD
334	3825992	deposit	done	2023.07.07 10:33:57	1 000.00	USD
335	3825992	deposit	done	2023.07.07 10:37:37	1 000.00	USD
336	3825992	deposit	done	2023.07.07 10:37:52	1 000.00	USD
339	3935451	deposit	done	2023.07.07 10:43:20	1 000.00	USD
340	3935451	deposit	canceled	2023.07.07 10:43:47	666.00	USD
341	3935451	deposit	done	2023.07.07 10:44:00	666.00	USD
342	3935451	withdrawal	done	2023.07.07 10:49:25	1 000.00	USD
343	3935451	withdrawal	done	2023.07.07 10:50:10	1 000.00	USD
344	3935451	withdrawal	done	2023.07.07 10:58:30	541.00	USD
346	3935449	withdrawal	done	2023.07.13 09:58:56	1 000.00	USD

Search * All Payment 2023.07.07 00:00 2023.07.07 23:59 Request

For Help, press F1 8488 / 7 KB

To view transactions, request them from the server. Specify the filter to the right of the icon :

- By accounts specify one or several account numbers separated by commas.
- By trader group select a group from the list or specify the group name manually.
- By login specify one or several accounts separated by commas.
- By wallet filter records by wallet.

For the payment history additional options are available:

- By date select a predefined period using the  button or specify the dates manually.

Specify the desired filters and press "Request". Select an operation in the list to view its details.

- Access to viewing and managing payments is subject to separate manager account permissions.
- For additional payment control, use special automation triggers. You can use them to set up notifications about any transactions and export data to external systems.

General Payment Details

Deposit #341: 766 USD to 3935451, John Smith, real\payments

General

Details

History

Deposit

Status

Done

Created

2023.07.07 10:44:00

Done

2023.07.13 12:30:42

Trade Account

John Smith, 3935451, real\payments, 1 : 100

Amount, USD	Commission, USD	Deal
766.00	10.00	5028569376

Wallet

Unlimit - Card

Amount, USD	Commission, USD	Conversion Rate
776.00	0.00	0.00000

Transaction

14941515

Transaction Status

COMPLETED

Manager

None

Description

400000...0051

Cancel

Update

The following information is shown for each payment:

- Status payments can have one of the following statuses:
 - ◆ Initial payment created on the server. Only used for internal purposes.
 - ◆ Processing the operation is being processed by the payment provider.
 - ◆ Waiting the operation is pending to be processed by the manager.
 - ◆ Locked the operation is captured by the manager for further processing.
 - ◆ Done the payment was successfully completed.
 - ◆ Rejected the operation was rejected by the manager.
- ◆ Rejected without refund used when rejecting payments made through wallets that do not support automatic refunds. For further details please read "Refunds".
- ◆ Canceled the transaction was rejected by the payment provider.
- ◆ Failed an error occurred while processing the payment.
- Created the date of the transaction in the client terminal.
- Trading account login of the account on which the operation is performed.
- Amount the operation amount requested by the client. Specified in the deposit currency.
- Commission commission charged by the broker in accordance with the settings.
- Deal ticket of the balance operation via which funds are credited to or debited from the trading account.
- Wallet the name of the wallet via which the operation is performed.
- Amount the amount of the transaction on the side of the payment provider. It is specified in the currency selected by the user on the client terminal side when making the operation.
- Commission the payment provider's commission for the operation.
- Conversion Rate the rate of conversion from the client's currency to the payment system currency (or vice versa).
- Transaction transaction ID assigned by the payment system.
- Transaction Status transaction status transmitted by the payment system.
- Manager the login and name of the manager who processed the operation. It is filled only for manually processed transactions.
- Description additional information about the operation. Can be filled in by payment systems or manually by managers.

Changing the payment status manually does not trigger any processing events. If "Canceled" is set for a successful top-up, the amount is not debited from the account. This should be done manually. If "Rejected" is set for a withdrawal operation being processed, the previously blocked amount is not released. To do this, the payment should be rejected via the manager terminal.

Details

Information in this section depends on the payment method: card, e-wallet, or bank transfer. The details depend on the payment system.

MetaTrader 5 trading platform

- For cards, these include card number, expiration date and owner's name
- For wallets, wallet number or ID is shown
- Bank transfers provide account details: bank name, division and code, account number, client name, etc.

Deposit #341: 766 USD to 3935451, John Smith, real\payments

General

Details

History

Details

Customer Email

johnsmith@mail.com

Card Number

400000...0051

Card Expiration

04/2024

Cardholder Name

John Smith

Cancel

Update

History

For efficient employee performance monitoring and secure storage of information, all changes in payment transactions are tracked and displayed in the Versions section. Version support allows you to see all changes made to the transaction. You can revert changes if necessary, since all earlier specified data are stored in the platform.

MetaTrader 5 trading platform

Deposit #317: 1 000 USD to 3935450, John Smith, real\payments

General

Details

History

22023.07.10 17:161863, John Smith

Description: Sent on 2023.07.10

12023.07.10 17:11created automatically

ID: 317

Login: 3935450

State: done

Created: 2023.07.04 15:02:47

Done: 2023.07.10 17:11:55

Gateway: wire transfer

Type: wire transfer

Wallet Name: hsbc hong kong, usd

User Amount: 1 000.00

User Currency: USD

Wallet Amount: 1 000.00

Wallet Currency: USD

Manager: 1863, John Smith

Deal: 5028565084

IP: 192.168.0.1

Language: English

Polling Time: 2023.07.04 15:02:57

Polling Counter: 5

Cancel

Update

MetaTrader 5 trading platform

Information on each change contains the number and date of the change as well as the relevant manager's login. To view more detailed information about the changes, click on the row. The details show each changed parameter: its name, previous value and new value.

Payment Accounts

At the moment, payment accounts are used only for transactions with bank cards. They store card details. Payment accounts are created when a user adds a new card or makes a deposit from a new card (the card is also added in this case).

To view the payment account details, go to the Payments \ Accounts section and query the records. Select a record to view its details:

The screenshot shows the MetaTrader 5 Administrator window. The left sidebar has a tree view with 'Accounts' selected under 'Payments'. The main area displays a table of payment accounts. A dialog box titled 'Payment Account #10 of 3935451, John Smith, real\payments' is open, showing the details for account ID 10.

ID	Login	Gateway	Type	Wallet Login	Card Number
29	3825992	unlimit	card	37189	400000...00
28	3825992	ecommpay	card	113591	400000*****00
24	3935448	unlimit	card	37189	400000...00

ID:	10
Trade Account:	John Smith, 3935451, real\payments, 1 : 100
Gateway:	Unlimit
Type:	Card
External ID:	DBD78221DABE161637FB35E7ED184074
Currency:	
Card Token:	c44aedef155e740285ea6b39f5383c52352780dbeabfed4746c92aa6701f1ef
Card Number:	400000*****0006
Card Expiration:	12/2025
Cardholder Name:	CARD HOLDER

Buttons: Update, Cancel

MetaTrader 5 trading platform

The following details are provided for payment accounts:

- **ID** unique account ID within the MetaTrader 5 platform.
- **Trading Account** details of the trading account for which the account is saved: holder's name, account number, group, leverage.
- **Gateway** payment provider.
- **Type** type of payment method: card, PayPal, WebMoney, etc.
- **External ID** unique ID used by the payment system to identify the account.
- **Currency** currency with which the payment method operates. This field is required for some providers who link cards to a specific currency. If no currency is specified, the payment instrument can use any currency for transactions.
- **Card token** unique ID used by the payment system to identify the card. Unlike the external ID, the token for the same card can change.
- **Card Number** masked card number. The system does not store full card numbers.
- **Card Expiration** card expiration date.
- **Cardholder Name** the name of the card holder.

The payment system does not store full card details (number and CVV) due to legal restrictions. This would require an organization to hold a special license. Instead, the system stores a unique token, by which the external system can identify the card.

Adding Cards

Due to specific requirements of some payment providers, the system needs to know in advance which card will be used to withdraw funds. If the user has not previously added cards and has not deposited funds (cards are added automatically during deposits), then when withdrawing funds in the client terminal, the user must first add the card:

Withdraw from account 3805827: John Smith

[Back to Payments](#)

Available funds: 36 811 USD

Choose a payment method:

☒  Unlimit - Card

☐  Unlimit - WebMoney

☐  Unlimit - PayPal

Bank card:*

[Add new card](#)

Add new card

[Back to withdrawal](#)

Email:*

johnsmith@mail.net

[Add](#)

MetaTrader 5 trading platform

Upon pressing Add, the user is forwarded to the payment system page and specifies card details. The system performs a special operation of 1 USD to authorize the card. This amount is locked on the card and then immediately unlocked, so nothing is debited from the user. After that, a payment account is created in the platform, which stores a special token – a unique identifier by which the payment system can identify the card.

After that, the user returns to the payment page, selects a card and performs the transaction.

Withdraw from account 3805827: John Smith

[Back to Payments](#)

Available funds: 36 811 USD

Choose a payment method:

☒  Unlimit - Card

☐  Unlimit - WebMoney

☐  Unlimit - PayPal

Bank card:*

400000...0051 05/27 ▾

×

Add new card

400000...0051 05/27

Choose the payment system currency:

USD ▾

The withdrawal amount will be converted to the payment system currency (USD) automatically

Specify the desired withdrawal amount:

1000

USD

Fee: 10 USD

The approximate amount to be received: 990 USD

Continue

MetaTrader 5 trading platform

- During deposit operations, the used cards are added to the system automatically. It is not necessary to add cards separately. The user can enter the amount and click Continue.
- If creation of accounts is disabled in the payment gateway settings, the option for adding new cards will disappear from the terminal. It will only be possible to add a new card by making a deposit.

Payments in Accounts

Account properties store all related transactions and payment accounts. Select a transaction in the list to view the details.

 Account: 3805827, John Smith, USD, 1:100, Netting

Overview Personal Account Limits Profile Subscriptions Payments Security

ID	Action	State	Created	Done	Wallet Name	User Amount	User Currency
 357	deposit	waiting	2023.07.14 14:19:19		unlimit - card	1 000.00	USD
 358	deposit	done	2023.07.18 10:05:36		hsbc hong kong, usd	1 000.00	USD
• 2 active payments							
 275	deposit	canceled	2023.05.16 16:25:15	2023.05.16 16:25:28	unlimit - card	10.00	USD
 307	deposit	canceled	2023.06.28 15:52:29	2023.06.28 16:00:29	unlimit - card	1 000.00	USD
 314	deposit	canceled	2023.07.03 13:54:36	2023.07.03 13:55:07	unlimit - card	1 000.00	USD
 322	deposit	canceled	2023.07.06 11:06:58	2023.07.06 11:07:03	unlimit - card	1 000.00	USD
 323	deposit	canceled	2023.07.06 11:09:14	2023.07.06 11:09:27	unlimit - webmoney	1 000.00	USD
 324	deposit	done	2023.07.06 11:10:23	2023.07.06 11:10:57	unlimit - paypal	1 000.00	USD
 355	deposit	done	2023.07.14 13:37:05	2023.07.21 12:33:10	unlimit - card	1 000.00	USD
 360	withdrawal	rejected	2023.07.18 14:16:13	2023.07.18 14:32:52	wire transfer	1 000.00	USD
 361	deposit	canceled	2023.07.18 17:00:31	2023.07.18 17:00:37	unlimit - card	1 000.00	USD

Last 3 months

2023.05.01 - 2023.07.21

Request

ID	Gateway	Type	Wallet Login	Card Number	Card Expiration	Cardholder Name
 33	unlimit	card	37189	400000...0051	05/2027	JOHN SMITH

New Client...

Update

Cancel

Help

MetaTrader 5 Trading Platform / Platform Setup / Payments / Processing Payments

Processing Payments

Using payment processing rules, you can flexibly configure the system and process some transactions in a fully automatic mode, while requiring manual confirmation by the manager for others. This provides additional operation security. For example, you can require manual control for suspiciously large withdrawal operations. All bank transfers are always processed manually.

Manual payment processing is implemented through the Manager terminal. Open the Payments \ Processing section. The bottom part displays a list of all payments pending processing.

1863 - MetaQuotes - John Smith

File Edit View Tools Window Help

Automation

Filter

3805827, Joe Black, real\payments

Deposit #357 1 000.00 with commission 10.00 USD (1 010.00 USD) via Unlimint - Card

Lock

ID	Login	Action	State	Created	User A...	User...	Transaction
No locked payments							
327	3935450	deposit	waiting	2023.07.06 13:01:42			hsbc
337	3825992	deposit	waiting	2023.07.07 10:38:16			e
345	3935451	deposit	waiting	2023.07.10 13:59:54			hsbc
357	3805827	deposit	waiting	2023.07.14 14:19:19			

Processing: 5 Active: 14 History

For Help, press F1

Navigator

- MetaTrader 5 Manager
 - Servers
 - Analytics
 - Server Reports
 - Clients & Orders
 - Payments
 - Processing (5)
 - Active (14)
 - History
 - Subscriptions
 - Dealing
 - Groups (162)
 - Plugins (5)
 - Mailbox (21 993)
 - Support Center
 - App Store

To process payments, the manager should have the "Access payments" and "Process payments" permissions. The manager can receive for processing only payments made by account from groups available to the manager.

Select the desired payment, and then click "Lock" at the top. The captured payment is removed from the queue, and no other manager can process it at the same time. After checking the payment details, you can approve or reject it. If you do not want to process the payment, press "Unlock", and it will be returned to the queue.

The screenshot shows the MetaTrader 5 trading platform interface. The window title is "1863 - MetaQuotes - John Smith". The menu bar includes File, Edit, View, Tools, Window, and Help. The toolbar contains various icons for file operations, automation, and connection. The main area displays the payment details for ID 3805827, Joe Black, real\payments. The payment is a deposit of 1 000.00 USD with a commission of 10.00 USD (1 010.00 USD) via Unlimint - Card. There are buttons for "Unlock", "Confirm", and "Reject". Below these buttons is a "Comment" input field. At the bottom, there are two tables showing transaction history. The first table has columns: ID, Login, Action, State, Created, User A..., User..., Transaction ID, Description, and Manager. The second table has columns: ID, Login, Action, State, Created, Wallet Name, User Amou..., and User Cu... The status bar at the bottom shows "Processing: 5", "Active: 14", "History", and "For Help, press F1".

3805827, Joe Black, real\payments

Deposit #357 1 000.00 with commission 10.00 USD (1 010.00 USD) via Unlimint - Card

Unlock

Confirm Reject

Comment

ID	Login	Action	State	Created	User A...	User...	Transaction ID	Description	Manager
357	3805827	deposit	locked	2023.07.14 14:19:19	1 000.00	USD	14967953	400000...0077	1863, John

ID	Login	Action	State	Created	Wallet Name	User Amou...	User Cu...
325	3935450	deposit	waiting	2023.07.06 11:15:25	hsbc hong kong, usd	1 000.00	USD
327	3935450	deposit	waiting	2023.07.06 13:01:42	hsbc hong kong, usd	1 000.00	USD
337	3825992	deposit	waiting	2023.07.07 10:38:16	emirates nbd, usd	1 000.00	USD
345	3935451	deposit	waiting	2023.07.10 13:59:54	hsbc hong kong, usd	333.00	USD

Processing: 5 Active: 14 History

For Help, press F1

8323 / 17 KB

Further actions depend on the payment type and the system through which it is performed.

Payments by Cards and e-Wallets

Depending on the type, such transactions are sent to manual verification at different stages:

- Deposits are forwarded for manual confirmation after they have been successfully completed in the payment system. If the manager confirms the transaction, the amount will immediately be credited to the user's trading account as a separate balance transaction. If the manager rejects the transaction, the amount will not be credited to the account. Further actions related to returning the funds to the client depend on the payment provider. For further details please read "[Refunds](#)".
- Withdrawals require manual confirmation before being sent to the payment system. The amount is immediately debited from the user's account using a balance operation. If the manager confirms the operation, a request to transfer funds will be sent to the payment system. If the manager rejects the transaction, the user will receive a refusal and the money will be credited back to the trading account as a separate balance operation.

Bank Transfer

This type is always processed manually, without external payment systems. When you receive a request for a deposit or withdrawal via bank transfer, you should pass the relevant information to the company's accountant. Click on the row of a locked operation to open its details:

MetaTrader 5 trading platform

ID	Login	Action	State	Created	User A...	User...	Transaction ID	Description	Manag
337	3825992	deposit	locked	2023.07.14 14:19:19	1 000.00	USD			1863, John S

Deposit #337 1 000 USD to 3825992, John Smith, real\payments

General

Details

Details

Customer Full Name
Joe Black

Bank Name
HSBC Hong Kong

Bank Branch
1 Queen's Road Central, Hong Ko

Bank Code
HSBCHKHHHKH

Bank Account
123456789

Payment Details
Top-up 3825992

Return

Confirm

Reject

Cancel

Update

MetaTrader 5 trading platform

In the case of a deposit, the accountant must check your bank account and verify that the transfer has been completed. After that, the manager can confirm the operation. Next, the system will credit the funds to the trading account as a separate balance operation.

In case of withdrawal, funds are first debited from the trading account by a balance transaction. Next, the accountant must perform the transfer using the specified details. The manager can then confirm the operation.

Additional information is available in the [Bank Transfer](#) section.

Refunds


Funds deposited by clients into their accounts can be returned according to two main scenarios.

Rejection during initial processing by manager

The initial processing occurs when the client replenishes the account, and the transaction is forwarded to the manager for manual confirmation. The manager may reject this transaction for some reason, for example, in accordance with the company's AML policy.


Deposits are forwarded for manual confirmation after they have been successfully completed in the payment system. Therefore, after rejection on the MetaTrader 5 side, the funds must be returned to the client back to the used payment method: card, wallet, etc. If the provider company through which the deposit transaction was made supports automatic refunds, then after the transaction is rejected, the platform will automatically send a corresponding request to the provider. In this case, no additional actions are required from the manager.

If the provider does not support automatic refunds, the funds will need to be returned manually. If you try to reject such a transaction, the system will display the following warning:



MetaTrader 5 trading platform

When you reject the payment, it will be set to the "Rejected without refund" state. After that, go to your account/dashboard on the payment provider's portal and cancel the corresponding deposit transaction. After this, on the MetaTrader 5 side, you should manually change the payment status to "Rejected".



Canceling a completed payment

If the payment has already been accepted and credited to the client's trading account, the refund procedure is slightly different:

- Write off the corresponding amount from the trading account balance using the Manager terminal
- Go to your account/dashboard at the payment provider through which the top-up was made and create a refund for the corresponding transaction. In this case, no automatic returns are possible; the procedure must be performed manually.
- Open the corresponding payment on the MetaTrader 5 side and change its status to "Rejected" or "Canceled". The reason for cancellation can be additionally specified in the "Description" field.

MetaTrader 5 trading platform

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Payments](#) / Payments in Client Terminals

Payments in Client Terminals

After you configure payments on the trading server side, a special section will appear in the client terminals, from where your traders will be able to make deposits and withdrawals.

The screenshot displays the MetaTrader 5 client terminal interface, specifically the 'Payments' section. The top bar shows the account number 3805827, available funds of 36 811, and the currency USD. The main area is divided into two panels: 'Deposit to account' and 'Withdraw from account'. Both panels list payment systems: Bank Transfer, VISA, MasterCard, and PayPal. The 'Transaction history' table at the bottom shows two transactions: a completed deposit of 1 000 USD on 2023.07.18 and a pending deposit of 1 000 USD on 2023.07.14.

Date	Ticket	Operation	Payment system	Status	Amount, USD	PDF
2023.07.18 10:05	358	Deposit	Bank Transfer	Completed	1 000	
2023.07.14 14:19	357	Deposit	400000...0077	Pending	1 000	

In addition to deposit and withdrawal options, the section displays the history of all transactions completed through the payment system. Pending invoices for depositing via a bank transfer can be downloaded as a PDF file.

Transaction specifics:

- Transactions are always associated with the currently connected account. To deposit or withdraw funds from another account, the user must first connect to it.
- The payments section is only available for real accounts and is not shown for other account types.
- The list of available payment methods is determined by the gateway settings. You can configure access based on groups and countries.
- Payment settings take precedence over settings of links to deposit and withdrawal pages. If payments are configured in the platform, all deposit and withdrawal commands will open the payments section rather than external pages.


Find detailed info on using the payment system on the client terminal side in the appropriate manuals:

- MetaTrader 5 for desktops
- MetaTrader 5 for iPhone/iPad
- MetaTrader 5 for Android

MetaTrader 5 Trading Platform / Platform Setup / Managers

Managers

User logins created in the Managers section possess special rights to manage the system (edit accounts, quotes for clients, generate reports, etc.)



The screenshot shows the MetaQuotes - MetaTrader 5 Administrator interface. The left sidebar displays a tree view with the following structure:

- Administrator
 - Servers
 - MetaTrader Server**
 - Network Cluster
 - Integrations
 - Automations
 - Security
 - Time
 - Holidays
 - Groups (519)
 - Clients & Accounts
 - Allocations
 - Clients
 - Managers** (highlighted)
 - Trading Accounts
 - Orders & Deals
 - Gateways

The main panel displays a table of user logins:

Login	Name	Mailbox	Groups
1000	Young Gavin	Administrator	*
1001	Evans Gabriel		*
1003	Lewis Brian		*
1006	Martin Jose	Administrator 6	*
1007	Martin Bryan	Administrator 7	*
1008	Moore Luis		*
1011	Spencer Robert	Clients	*
1014	Jackson Brandon	Administrator 2	*
1015	Wright Alexander		*
1022	Turner Lucas		*
1026	Smith Aiden	Manager	demo*,real*,preliminary
1027	Lee Diego		*
1029	Lee Patrick		*
1033	Wilson Kevin		*
1034	Phillips Jackson		*
1037	Cooper Seth		*

At the bottom of the window, there is a status bar with the text "For Help, press F1" and a network status indicator showing "841 / 0 Kb".

MetaTrader 5 trading platform

Manager accounts are all shown in a table with the following fields:

- **Login** manager's account.
- **Name** manager's name.
- **Mailbox** name of the manager's mailbox.
- **Groups** groups serviced by this manager.

Managers who have permissions to connect via the administrator terminal are marked by icon 🗑, all other managers - by 🛠.

- Manager accounts are created only based on accounts added in the corresponding section.
- A manager can service only those accounts that belong to the server, to which the group the manager is included to refers.

In order to create or edit a manager account, press "+ Add" and "⚙ Edit", respectively. In order to delete a manager, press "✗ Delete". These commands are available in the Edit menu, on the Standard toolbar and in the context menu. Upon the execution of these commands, a window of manager settings will appear.

Additional general information about working with configuration records is given in the "Working with Instructions" section.

Supervision of managers

For the additional control of access to the server data, managers' search queries, data exports, copying to clipboard and table filters used are logged in the platform. The actions are logged on the Manager and Administrator terminal side and on the trading server side.

For example, if the employee exports a report or data on online accounts, clients and quotes, the following entries will be added to the server log:

2020.02.06 08:24:01.114	10.25.217.106	'1024': export report 'Accounts\Accounts Groups'
2020.02.06 08:24:30.865	10.25.217.106	'1024': export online trading accounts, 4 records
2020.02.06 08:24:44.756	10.25.217.106	'1024': export clients, 85 records to 'Clients.csv'
2020.02.06 08:25:17.225	10.25.217.106	'1024': export ticks of 'Gold' for 2017.06.26, 578

When copying configurations to clipboard, the following entry is added to the logs:

2020.02.06 08:24:30.865	192.168.0.1	'1033': copy MetaTrader 5 Main Server Journal to
-------------------------	-------------	--

Common

MetaTrader 5 trading platform

Manager: First Admin

Common Permissions Reports IP Access List

Managers control platform settings, accounts and trading operations. To add a manager, create a trading account in the 'managers' or 'administrators' group and specify its login in this tab. Then configure access to client groups.

Login: 1000 Mailbox name: Administrator

Groups:

- * (person icon)

Add Edit Delete

OK Cancel Help

The following parameters are specified on this tab:

- **Login** manager login, added in the "Accounts" section. The specified account must be included to the managers' group.
- **Mailbox name** name of the manager's mailbox. If the mailbox name is not specified, the manager will not be able to send emails via the internal mailing system.


In the "Groups" filed, groups of accounts that will be serviced by the manager should be specified:

- **Add** add a service group. After you press this button, a new line will appear in the window. Specify one of the groups from the list here. You can use mask "*" and negation sign "!" to set up groups. For example, if you specify "demo*" it will indicate all groups, whose name (including path) starts with "demo" (for example, demo\forex, demoforex, demoforex\usd). If you specify "!managers*,*", it will indicate all groups except those, whose name starts with "managers".
- **Delete** delete a selected group.
- **Edit** edit a selected group. The same action can be performed by double-clicking on the group.

- A manager account can be created only based on the account included to the managers' group.

- In the manager terminal only the accounts that belong to the groups permitted for the manager are available.
- Rules for the groups are checked from top to bottom. If you allow all groups in the first row, you will not be able to prohibit some of them in the next rules.
- A rule cannot consist of prohibition only. For example, the rule "!demo*" is not valid. A prohibition can be used together with a permission to see some other groups. For example, "!demo*,real*".

Permissions



Managers' permissions and access to different data are set up on this tab:

- **Available logs** selecting period, logs within which will be available to the manager.
- **Available reports** selecting period, within which a manager is able to view various reports and request account trading history in the Manager terminal. In addition to this parameter, individual data depth limits from the [Reports](#) section are also checked when requesting reports. The strictest limit always applies. For example, if the 'Available reports' parameter is set to '6 months' and a specific report has a limit of 90 days, the manager will only be able to request data for the past 90 days.
- **Role** here you can select one of predefined sets of permissions. Using buttons "Save As" and "Delete" you can save and delete your own sets of permissions. These sets are saved in /roles folder of the [directory](#), where the terminal information in the user's profile is stored on the PC.

Below the list of permissions is located. In order to enable a permission, tick off them. The following permissions are available here:

- **Connection type**
 - ◆ Connect using MetaTrader 5 Administrator connection to the server using the administrator terminal.
 - ◆ Connect using MetaTrader 5 Manager connection to the server using the manager terminal.
- **Configuration setup**
 - ◆ Configure network possibility to configure the [platform components](#).
 - ◆ Configure VPS configuring [Sponsored VPS](#) for traders.
 - ◆ Configure mail servers setting up [integration with email services](#).
 - ◆ Configure messengers setting up [integration with SMS providers and messengers](#).
 - ◆ Configure KYC setting up [integration with KYC services](#).
 - ◆ Configure payments configuring integration with payment systems (in development).
 - ◆ Configure web services access to the [Integration \ Web services](#) section.
 - ◆ Configure IP access list setup of [access](#) to the platform by IP addresses.
 - ◆ Configure automations setting up [automatic actions](#) for specified scenarios.
 - ◆ Configure server operation time setup of the server [working hours](#).
 - ◆ Configure holidays setting up [holidays](#).
 - ◆ Configure groups setting up [groups of accounts](#).
 - ◆ Configure allocations setting up groups, in which traders are able to open [demo and preliminary real accounts](#) directly from client terminals.
 - ◆ Configure corporate links setting up [links](#) to be displayed in client terminals.
 - ◆ Configure managers' permissions setting up these permissions.
 - ◆ Configure request routing configuring [rules of routing](#) of requests.
 - ◆ Configure gateways configuring parameters of [gateways](#).
 - ◆ Configure plugins managing [plugins](#).
 - ◆ Configure datafeeds setting up [datafeeds](#).
 - ◆ Configure reports setting up [reports](#).
 - ◆ Configure symbols setting up [financial symbols](#).

MetaTrader 5 trading platform

- ◆ Configure history charts synchronization setting up synchronization of history data with other servers.
- ◆ Configure ECN setting up ECN.
- ◆ Configure funds and ETF setting up investment funds.
- **Administration**
 - ◆ Access server logs permission to request server operation logs.
 - ◆ Receive automatic server reports permission to receive automatically generated reports on the server operation.
 - ◆ Edit charts permission to edit history data on the server. To access the data, the manager also needs the "Configure symbols" permission.
 - ◆ Send emails permission to send emails via the internal mailing system.
 - ◆ Send news permission to send news. A manager/administrator is able to send news only if their account belongs to a group created at the main trade server.
 - ◆ Export data permission to export data (accounts, orders, etc.) in external files from the manager and administrator terminals. The permission does not affect the ability to export server configurations from the administrator terminal.
 - ◆ Manage server machines access to a menu for managing the computer on which the platform server is running.
- **Accounts**
 - ◆ Accountant (deposit/withdraw) permission to work with assets on accounts.
 - ◆ Access accounts possibility to view the list of accounts.
 - ◆ View technical accounts when combined with "Show to regular managers", provides greater convenience in working with various testing and technical accounts. Disable the "Show to regular managers" permission for all technical accounts, and then disable access to technical accounts for the managers who do not configure the platform. Otherwise, such technical accounts can be confusing for managers working with clients.
 - ◆ Manage technical accounts with this permission, the manager can enable and disable options "Show to regular managers" and "Include in server reports" for a trading account. Without this permission, the manager can only see the states of the relevant options, without the ability to change them (read-only).
 - ◆ Access the account personal details permission to view personal details on accounts. You can separately provide access to the name, location (country, city, region, zip code), address, document number, email, phone number, and general data (other less important data: language, status, comment, MetaQuotes ID, etc.).
 - ◆ Edit accounts modifying account details.
 - ◆ Delete accounts permission to delete client accounts in the administrator and the manager terminals and via Manager API. In order to delete accounts, a manager account must also have the "Edit accounts" permission.
 - ◆ View currently connected clients permission to view accounts currently connected to the server.
 - ◆ Confirm dangerous actions confirmation dialog is displayed in the manager terminal by default when performing balance operations on a client account and during bulk order closing. In order to perform one of

these actions, a randomly generated character sequence should be entered. If disabled, the actions are performed immediately with no confirmation.

- ◆ Push notifications a right to send push notifications to clients' mobile devices using the manager terminal. Messages are sent based on MetaQuotes ID, which is a unique user identifier. To obtain the ID, a user needs to install MetaTrader 5 Mobile for [iPhone](#) and [Android](#). Detailed information is provided in the manager terminal user guide.

- **Dealing**

- ◆ Access orders and positions permission to view trade [orders](#), [deals](#) and [positions](#). To be able to access this data, the manager must also have the "Access accounts" permission. The "Access orders and positions" permission affects the possibility of enabling the "Modifying of orders" and "Dealer" permissions.
- ◆ Edit orders, positions, and deals permission to edit any fields of [orders](#), [deals](#) and [positions](#) in the administrator and the manager terminals and via Manager API. Also provides access to the Exposure tab in the Manager terminal.
- ◆ Delete orders, positions, and deals permission to delete any [orders](#), [deals](#) and [positions](#) in the administrator and the manager terminals and via Manager API. In order to delete trade operations, a manager account must also have the "Edit orders, positions and deals" permission.
- ◆ Dealer permission to perform trading and dealing operations in the manager terminal. Also provides access to the Exposure tab in the Manager terminal. In addition, it controls access to the availability of group position closing and splitting feature in the Manager terminal.
- ◆ Supervisor permission to see the entire queue of requests coming from client groups available to the manager, and to see how the requests are processed by other dealers in the manager terminal. A manager works as a Supervisor being not connected as a dealer in the manager terminal. Once the manager has connected as a dealer, they will see only their own requests coming for processing according to the [routing rules](#).
- ◆ Show raw quotes without spread difference if this permission is given, an additional command "Show raw quotes" appears in the context menu of the "Market Watch" window in the manager terminal. By enabling it, the manager will be able to see the quotes without [applying the spread settings](#) of the manager group.
- ◆ Throw in quotes permission to throw in quotes from the manager terminal.
- ◆ Modify spread and execution mode permission to modify spread and execution mode from the manager terminal.
- ◆ Risk manager permission to receive information on the total clients' positions and company's coverage positions. The parameter affects the availability of section "Summary Positions" and "Exposure" as well as of the account "Exposure" tab in the Manager terminal.
- ◆ Edit groups (margin settings) permission to modify the [margin settings of groups](#) via the manager terminal.
- ◆ Edit groups (commission settings) permission to modify the [commission settings of groups](#) via the manager terminal.
- ◆ Receive reports permission to request and receive various reports on clients' operations.

- **Payments**

- ♦ Access payments view current and processed payments and payment accounts.
- ♦ Process payments confirm and decline manually processed payments via the Manager terminal.
- ♦ Edit payments edit current and processed payments and payment accounts.
- ♦ Delete payments delete current and processed payments and payment accounts.

- **Back office** permission to access the Clients section. Permissions in this section apply to both Manager and Administrator terminals.

- ♦ Access clients general access to the Clients section.

- ♦ Access personal details access to clients' personal data. You can separately provide access to the name, location (country, city, region, zip code), address, document number, email, phone number, and general data (other less important data: language, status, Lead Source, Lead Campaign, etc.).

- ♦ Create clients permission to create new client records manually.
- ♦ Edit clients permission to edit any client data, except documents.
- ♦ Delete clients permission to delete client records.
- ♦ KYC check ability to launch auto verification of client data using integration with KYC services.
- ♦ Access documents permission to view clients' documents.
- ♦ Create documents permission to add general information about documents to client records.
- ♦ Edit documents permission to edit general information about documents in client records.
- ♦ Delete documents permission to delete general information about documents from client records.
- ♦ Add files to documents permission to add document files to client records.
- ♦ Delete files from documents permission to delete document files from client records.
- ♦ Access comments permission to read comments to client records and documents.
- ♦ Add comments permission to add comments to clients and their documents.
- ♦ Delete comments permission to delete comments to clients and documents.

- **Finteza**

- ♦ Access to Finteza access to the Finteza Analytics section.
- ♦ View websites view website related information from Finteza in the Analytics section of the Manager terminal.
- ♦ View campaigns permission to view information on marketing campaigns from Finteza in the Analytics section of the Manager terminal.
- ♦ View reports the permission is currently not used.

- **Subscriptions** access to the Subscriptions section.

- ♦ View subscriptions view and edit subscription settings in the Administrator terminal, as well as view active subscriptions and the

MetaTrader 5 trading platform


history of subscriptions in the Administrator and Manager terminal.

- ◆ Edit subscriptions ability to create and delete subscriptions for traders in the Administrator and Manager terminal.

Once the access rights are changed the manager is automatically reconnected for changes to take effect.

Reports

Configure manager access to server reports. Click "Add" and specify the path to the report or group of reports. Next, set the permissions to view and export report data to a file and specify the depth of information that will be available to the manager.




MetaTrader 5 trading platform

For efficient permission categorization, create a hierarchy of reports and arrange them into directories according to their purpose. For example, you can create a separate directory with dealer transaction reports, a separate directory for marketers who are responsible database analysis and customer acquisition, etc. Such categorization will assist in configuring access rights: you will only need to specify one line with the directory path rather than specify each individual report.

When reports are requested, the system checks both the individual data depth limits from the 'Reports' section and the 'Available reports' parameter from the 'Permissions' section. The strictest limit always applies. For example, if the 'Available reports' parameter is set to '6 months' and a specific report has a limit of 90 days, the manager will only be able to request data for the past 90 days.

IP Access List



On this tab, you can set up the range of IP addresses, from which this manager can connect. Thus you can limit managers' access, for example, to the dealing room only.

- **Add** add a range of IP addresses. As soon as you press this button, a new line will appear in the window. In fields "From" and "To" specify the first and last IP of the range, respectively.
- **Delete** delete a selected IP range.
- **Edit** modify a selected IP range. The same action can be performed by a click on the necessary line.

To complete the creation or modification of a manager, press OK. If you press "Cancel", the window will be closed, while changes will not be saved.

Context Menu

The context menu of the "Manager" section contains the following commands:

- **Servers** using this command, one can filter the managers displayed in the list by the trade server they belong to. A list containing all trade servers of the platform will be opened as soon as it is executed.
-  **Add** add a new manager.
-  **Edit** edit a selected manager.
-  **Delete** delete a selected manager.
-  **Move Up** move a selected manager up relative to others.
-  **Move Down** move a selected manager down relative to others.
-  **Sort by Login** sort managers by their logins. Sorting is performed on the server, not on the local MetaTrader 5 Administrator.
-  **Export to File** export the settings of managers to a file.
-  **Import from File** import the settings of managers to a file.
-  **Find** open the search window.
- **Auto Arrange** if this option is enabled the size of columns is selected automatically.
- **Grid** this option shows/hides field separators in the table with managers.

MetaTrader 5 Trading Platform / Platform Setup / Orders

Orders

Using the "Orders" section, you can manage the history of orders placed by clients, pending orders and the orders that are not executed at the moment.

MetaQuotes - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Import Export Apply + Settings X Back Forward Sort

- Integrations
- Automations
- Security
- Time
- Holidays
- Groups (519)
- Clients & Accounts
- Orders & Deals
 - Positions
 - Orders**
 - Deals
- Gateways
- Data Feeds
- Plugins
- Reports
- ECN
- Routing

Time	Login	Order	Symbol	Type	Volume
2020.03.06 15:46:18.145	1814550	102397819	GBPCHF	sell	0.10 / 0.
2020.03.06 15:46:18.147	1814550	102397820	GBPCHF	sell	0.10 / 0.
2020.03.06 15:46:18.225	1814550	102397821	GBPCHF	sell	0.10 / 0.
2020.03.06 15:46:22.330	1814550	102397822	GBPCHF	sell	0.10 / 0.
2020.03.06 15:46:22.332	1814550	102397823	GBPCHF	sell	0.10 / 0.
2020.03.06 15:46:22.334	1814550	102397824	GBPCHF	sell	0.10 / 0.
2020.03.06 15:49:31.172	1814550	102397825	GBPCHF	sell	0.10 / 0.
2020.03.06 15:49:31.174	1814550	102397826	GBPCHF	sell	0.10 / 0.
2020.03.06 15:49:31.337	1814550	102397827	GBPCHF	sell	0.10 / 0.
2020.03.06 15:50:02.775	1814550	102397828	GBPCHF	sell	0.10 / 0.
2020.03.06 15:50:03.632	1814550	102397829	GBPCHF	sell	0.10 / 0.
2020.03.06 15:50:03.836	1814550	102397830	GBPCHF	sell	0.10 / 0.
2020.03.06 15:50:12.236	1814550	102397831	GBPCHF	sell	0.10 / 0.
2020.03.06 15:50:27.178	1814550	102397832	GBPCHF	sell	0.10 / 0.

Q * ☐ Open only 2020.03.02 00:00 2020.03.05 23:59

For Help, press F1 3609 / 1 KB

Depending on the items chosen in the context menu, different information about orders is displayed here. Orders can be sorted out by any field. To do it, click with the left mouse button on its name.

Requesting Orders

To view orders, compose a request. A request can be performed:

- **By Groups**
To do it, select a group from the dropdown list.
- **By Logins**
To do it, should specify one or several logins separated with commas.
- **By Tickets**
To request orders by their numbers specify one or several numbers separated with commas. Before the numbers it is necessary to specify the "#" symbols.

Then you can specify the following parameters of the request:

- Trading instruments for which orders will be requested. One symbol or a group of symbols can be selected from the list. Optionally, you can specify a comma separated list of trading instruments or groups of symbols. For example, Forex*, CFD*, Metals\GOLD. Please note that filtering is performed on the server side, and not on the administrator terminal side. To obtain data on other instruments, send another request. The request is performed for all financial instruments by default.
- If you check the "Open only" option then only the pending orders that haven't triggered yet will be displayed.
- Then you can specify one of the predefined periods of request using the  button: "Today", "Last 3 days", "Last week", "Last 3 months", "Last 6 months" and "All history". To specify a custom request period, use the fields to the right. Orders are requested based on the execution time. Open orders do not have this parameter, so they will be included in all queries.
- Then you can specify a database the orders will be requested from: current database or one of the backups.

To execute the request, press the "Request" button or execute the " Request" command in the context menu.

Viewing an Order

To start viewing or editing an order, double-click on it in the list. The trading operation dialog is a fully-featured tool with a plethora of advanced features, such as the display of the structure of operations, visualization, tick history and logs.

MetaTrader 5 trading platform

Position #5072917935 buy 0.01 AUDCAD 0.89953

Mitchell Steven, 3767921, demo\demo forex, 1 : 100

Ticket	Time	Type	Volume	Price	Profit
5072917935	2022.07.27 23:02:10.493	buy	0.01	0.89953	6.6
5072917935	2022.07.14 13:36:41.864	buy stop	0.01 / 0.01	0.89953	order
5028164712	2022.07.27 23:02:10.493	buy	0.01	0.89953	0.0

Details Visualization Ticks Journal

Order: 5072917935 Position: 5072917935

BUY STOP

0.01

AUDCAD, Australian Dollar vs Canadian Dollar

Remained volume:

0.00

Reason: Client

Setup time: 2022.07.14 13:36:41.864

Order price: 0.89953

State: FILLED

Done time: 2022.07.27 23:02:10.493

Current price: 0.89990

Expiration: GTC

Expiration time: 1970.01.01 00:00:00

Trigger price: 0.00000

Filling: RETURN

Stop loss: 0.00000

Dealer ID:

Take profit: 0.00000

Expert ID:

Margin rate: 0.67161000

External ID:

Comment: order

Disabled activations:

Modifications:

Report...

Update

Account details

The upper part of the dialog features brief information about the account, on which the operation was performed: name, login, group and leverage. Click on this line to view [account details](#).

Overview and related operations

All related trading operations are shown in this block: deals executed as a result of order execution and the resulting position. Thus you can easily access the entire chain of related actions. Select an operation from the tree and all relevant parameters will be instantly displayed in the bottom part.

Trading operation details

The following parameters are indicated for orders:

- **Login** [account](#) number the order was placed on;
- **Order** order number (ticket);
- **Setup time** time when the order was placed by the client. If the order is processed in an external trading system, this field displays the time of order placing in the external system (not in the MetaTrader 5 platform). When Stop Limit orders are triggered, a new value is written to this field, instead of the time the order was placed by the client: the time when the corresponding limit order was placed.
- **Position** ticket of the position opened, modified or closed due to this order. For "close by" orders, two tickets are displayed: closed position ticket and opposite position ticket.
- **Type** order type: "Buy", "Sell", "Buy Limit", "Sell Limit", "Buy Stop", "Sell Stop", "Buy Stop Limit", "Sell Stop Limit" or "Close By";
- **Initial volume** volume requested in the order;
- **Symbol** [symbol](#) the order was placed for;
- **Filling** additional parameters of [order execution](#): "All or none", "Cancel remainder", "Book or Cancel" or "Return remainder".
- **Order price** price specified by trader for execution of the order;
- **Trigger price** this field is intended for the "Buy Stop Limit" and "Sell Stop Limit" orders. It contains the price level when they trigger and the corresponding limit orders are placed.
- **Stop loss** the Stop Loss level;
- **Take profit** the Take Profit level;
- **Comment** text comment to the order. This field can contain trader's comments if they were specified.
- **Margin rate** rate of converting the symbol margin currency to the deposit currency.
- **Expiration** [expiration type](#) of the order: "GTC" (Good Till Canceled), "Day" or "Specified".
- **Expiration time** if lifetime of the order has expired then this field contains the date and time of expiration;
- **Disable activation** additional conditions (flags), with which order activation is prohibited. The flags can be set by Gateway API when orders are sent to an external system. For example, if activation of stop loss and take profit must be

controlled by an external system, a flag disabling activation on the MetaTrader 5 side can be set for the order. Order flags are inherited by positions created upon order execution. Available flags:

- ♦ **Limit** no processing of limit level hitting.
- ♦ **Stop** no processing of stop level hitting.
- ♦ **Stop Limit** no processing of stop limit level hitting.
- ♦ **SL** no processing of Stop Loss activation.
- ♦ **TP** no processing of Take Profit activation.
- ♦ **Stop Out** no processing of Stop Out activation.
- ♦ **Expiration** no processing of expired order cancellation.
- **Modifications** if the order is changed manually, this field displays who implemented the changes:
 - ♦ **Administrator** order changed by an administrator.
 - ♦ **Manager** open price changed by a manager.
 - ♦ **Restore** order restored.
 - ♦ **Admin API** order changed via Manager API administrator interface.
 - ♦ **Manager API** order changed via Manager API manager interface.
 - ♦ **Server API** order changed via Server API.
 - ♦ **Gateway API** order changed via Gateway API.

- The orders changed by an administrator or manager, as well as restored orders are highlighted in the list in red.
- Use Trade Modification Report to obtain information about all modified trade operations.

- **Reason** a reason of placing the order:
 - ♦ **Client** the order is placed manually by a client via the client terminal;
 - ♦ **Expert** the order is placed by a client using an Expert Advisor;
 - ♦ **Dealer** the order is placed by a dealer via the manager terminal;
 - ♦ **SL** the order is placed as a result of Stop Loss triggering;
 - ♦ **TP** the order is placed as a result of Take Profit triggering;
 - ♦ **SO** the order is placed because a client reached the Stop-Out level;
 - ♦ **Rollover** the order is placed when reopening position for charging swaps;
 - ♦ **External Client** the order is placed by a client from an external trading system.
 - ♦ **Variation margin** the order is placed for accruing variation margin.
 - ♦ **Gateway** the order is placed by a MetaTrader 5 gateway that had connected to the trading platform.
 - ♦ **Signal** the order is placed as a result of copying a trade signal according to a subscription in the client terminal.
 - ♦ **Settlement** the order is placed as a result of performing operations connected with the settlement of a futures contract/option. Not used at the moment.
 - ♦ **Transfer** the order is placed due to transferring a position at the settlement price to a new symbol with the same underlying asset. Not used at the moment.

MetaTrader 5 trading platform

- ◆ **Synchronization** the order is placed as a result of synchronization of an account's trade state with an external system.
- ◆ **External Service** the order is placed from an external trading system for technical reasons (for example, to correct the trade state of a client).
- ◆ **Mobile** the order was created via the MetaTrader 5 mobile terminal for Android or iPhone.
- ◆ **Web** the order was created via the web terminal.
- ◆ **Split** the order was created as a result of a symbol split.
- ◆ **Corporate action** the order was created as a result of a corporate action, such as consolidating or renaming securities, transferring a client to a different account, etc. API applications set this flag for service operations so that the platform does not account for such corporate actions in commission calculations.
- ◆ **Migration** order was created while importing clients' trading operations from the MetaTrader 4 server.
- **Expert** the identifier (magic number) of an Expert Advisor that has sent this order from the client terminal.
- **Done time** time when the order was executed. If the order is processed in an external trading system, this field displays the time of order execution in the external system (not in the MetaTrader 5 platform);
- **State** current state of the order (filled, rejected, partially filled, expired, etc.). Editing allowed for emergency situations only. It is strongly not recommended to change this setting manually without a special need;
- **Current price** current price of the symbol the pending order was placed for. For market orders, a value from the "Order price" field is displayed here;
- **Remained volume** if the order is not filled in the volume requested by trader this field will display the remainder volume;
- **ID** unique identifier of the order in the external systems.
- **Dealer** number of account of the dealer that processed this order. If "0" is specified in this field, it means that the order was processed without a dealer.

If a manager has access rights for modifying orders then any field in this window can be modified. As soon as all the changes are made, the "Update" button should be pressed. If you press the "Delete" button the order will be deleted from the currently selected database.

Visualization

In this section, execution of a trading operation is visualized on the tick chart of the appropriate symbol.

MetaTrader 5 trading platform



Nearest ticks before and after the operation

When examining disputable situations with traders, it is often necessary to analyze quotes which were broadcasted at the trading operation execution time. The relevant quote data can be obtained in a couple of clicks. Open operation details and navigate to the "Ticks" section. The terminal will automatically request the quote history from the server for the entire day on which the operation was performed. The nearest quote to operation execution time will be automatically selected in the list of received quotes.

MetaTrader 5 trading platform

Details Visualization Ticks Journal					
Date	Bid	Ask	Last	Volume	
✓ 2019.02.06 09:58:18	0.93906	0.94006	0.00000	0.00	
✓ 2019.02.06 09:58:18	0.93905	0.94005	0.00000	0.00	
✓ 2019.02.06 09:58:18	0.93906	0.94006	0.00000	0.00	
✓ 2019.02.06 09:58:18	0.93907	0.94007	0.00000	0.00	
✓ 2019.02.06 09:58:19	0.93908	0.94008	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93907	0.94007	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93904	0.94004	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93901	0.94001	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93898	0.93998	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93900	0.94000	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93899	0.93999	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93900	0.94000	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93901	0.94001	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93900	0.94000	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93901	0.94001	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93899	0.93999	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93898	0.93998	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93897	0.93997	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93898	0.93998	0.00000	0.00	

Operation journal

This is another tool to assist during the follow-up operation examination. There is no need to manually request logs from the server and to filter its records. Open operation details, navigate to the "Journal" section and the terminal will automatically request the necessary logs from the server, using ticket and time interval filters (from the operation date to the current day).

MetaTrader 5 trading platform

Details
Visualization
Ticks
Journal

Time	IP	Message
2019.05.13	(20490 kb)	-----
* 2019.05.13 15:25:54.684	11.14.194.2	'1815606': order placed [#100329729 buy limit 1.00 AUDCAD at 0.93559], time 0.79 ms
* 2019.05.13 15:28:51.242	11.14.194.2	'1815606': modify order #100329729 buy limit 1.00 AUDCAD at 0.93559 sl: 0.00000 tp: 0.0...
* 2019.05.13 15:28:51.242	11.14.194.2	'1815606': request confirmed, rule 'Auto Execution' (modify #100329729 buy limit 1.00 AUDC...
* 2019.05.13 15:28:51.242	11.14.194.2	'1815606': order modified [#100329729 buy limit 1.00 AUDCAD at 0.93531], time 0.48 ms
* 2019.05.13 15:28:57.667	11.14.194.2	'1815606': modify order #100329729 buy limit 1.00 AUDCAD at 0.93531 sl: 0.00000 tp: 0.00...
* 2019.05.13 15:28:57.667	11.14.194.2	'1815606': request confirmed, rule 'Auto Execution' (modify #100329729 buy limit 1.00 AUDC...
* 2019.05.13 15:28:57.667	11.14.194.2	'1815606': order modified [#100329729 buy limit 1.00 AUDCAD at 0.93531], time 0.58 ms
* 2019.05.13 17:04:08.806		'1815606': order [#100329729 buy limit 1.00 AUDCAD at 0.93531] triggered, activation price...
* 2019.05.13 17:04:08.806		'1815606': activate order #100329729 buy limit 1.00 AUDCAD at 0.93531 (0.93430 / 0.9353...
* 2019.05.13 17:04:08.806		'1815606': request confirmed at client price 0.93531, rule 'Auto Execution' (activate #10032...
* 2019.05.13 17:04:08.807		'1815606': order performed buy 1.00 at 0.93531 [#100329729 buy limit 1.00 AUDCAD at 0...
2019.05.14	(20480 kb)	-----
* 2019.05.14 15:30:53.643	11.14.194.2	'1026605': server journal (#100329729, 2019.05.13 - 2019.05.14)

#100329729

▼

Full

▼

All

▼

2019.05.13

▼

2019.05.14

▼

Request

Update

Cancel

Help

Trading operation report

The trading operation details available in the editing dialogs can be saved as a report. The report contains the entire chain of operations from an order to a position, visualization on a tick chart, extract from the server log and the trading account overall status.

To generate a file, click "Report" in the context menu in the "Overview and related operations" section. Next, select data to be saved: account state, trading totals, logs, tick chart, etc.

MetaTrader 5 trading platform

Position #100059643 buy 1.00 USDCAD 1.34415

John Smith, 1816500, demo\demo forex-5-hedged, 1 : 100

Ticket	Time	Type	Volume	Price	Profit
100059643	2016.11.30 17:20:03.380	buy	1.00 / 1.00	market	
	17:20:03.380	buy	1.00	1.34415	0.0
	17:20:03.380	buy	1.00	1.34415	1.206.0

☒ Show Milliseconds
 ☒ Auto Arrange
 ☒ Grid

Expiration: GTC
 Filling: RETURN
 Dealer ID:
 Expert ID:
 External ID:
 Comment:
 Disabled activations:
 Modifications:

Save As

Save in: This PC

☒ This PC
☐ Network

☒ Trade Account
☒ Trade Summary
☒ Journal

☒ Object Table
☒ Trade Results

☒ Tick Table
☒ Tick Chart

File name: Position-100059643.html

Save as type: HTML Files (*.html)

Select the path on the disk and click "Save".

Moving Orders to History

Any open order can be move canceled and moved to history. At that, its state will be changed to "Canceled". Click "To history":

Dealer ID:

Expert ID: 173339640206990851

External ID:

Comment:

Disabled activations:

Modifications:

Take profit:

Margin rate:

Report... To History Update Cancel Help

Orders moved to history cannot trigger or be executed; also margin is not charged for them.


Reopening Orders

Pending orders can be reopened from the orders' trading history. Before reopening the order, client's trading positions and account should be properly corrected:

- Delete the trade opened according to the order.
- Correct the client's positions using the special command. To do this, open the account's dialog window and execute "Fix Positions" context menu command in the Overview tab.
- Correct the client's balance. Select the appropriate account in the list and execute "Balance->Fix Balance" context menu command.

After that, the triggered order can be reopened. To do this, move to Orders section, find the necessary order, open it for editing and click "Reopen":

MetaTrader 5 trading platform



Expert ID: 173339640206990851

Margin rate: 1.27681000

External ID:

Comment:


Disabled activations:

Modifications:

Report... Reopen Update Cancel Help

Backup Databases of Orders

Backup copies are copies of the order database at certain points in time. They are created daily on the backup server. To get the list of available backup copies, select "More backups..." and specify a time period:



Backups period

Server: Backup Trade, 8

Period: Today

From: 2020-03-09 to: 2020-03-10

OK Cancel

After specifying a period the additional items will appear in the field of choosing database all the backups made for the specified period of time. Then you should request orders from the selected database. Any order can be restored to the current database using the "📂 Restore" command of the context menu.

Restored orders are not deleted from the backup databases.

Context Menu

The context menu of the "Orders" section contains the following commands:

-  **Edit** modify a selected order;
-  **Delete** delete a selected order;
-  **Request** execute a request;
-  **Restore** restore a selected order from a backup database to the current one. This command is active only if a backup database is currently requested;
- **Copy As** copy orders selected in the list:
-  **Lines** copy entire selected information.
- **List of Logins** copy the list of logins only.
- **List of Tickets** copy the list of tickets only.


MetaTrader 5 trading platform

-  **Export** export requested orders as a *.HTM, *.HTML file or as a *.CSV file;
-  **Journal** request the journal entries by a selected order;
-  **Find** open the search window;
- **Show Milliseconds** show the time of trade operations with a millisecond precision;
- **Auto Arrange** if this option is enabled the size of columns is selected automatically;
- **Grid** this option shows/hides field separators in the table with orders;
- **Columns** using this sub-menu, one can choose which details of orders will be displayed in the list.

MetaTrader 5 Trading Platform / Platform Setup / Deals

Deals

This section allows working with the entire history of deals executed by traders' orders, and balance operations.



MetaQuotes - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Import Export Apply + Settings X Left Arrow Right Arrow Sort

Automations Security Time Holidays Groups (519) Clients & Accounts Orders & Deals Positions Orders Deals Gateways Data Feeds Plugins Reports ECN Routing Funds & ETF

Time	Login	Deal	Symbol	Volume	Price	Reason
2020.03.09 08:34:40.535	18154...	100386085	AUDCAD	0.01	0.89467	W
2020.03.09 08:34:43.823	18154...	100386086	AUDCAD	0.01	0.89428	W
2020.03.09 08:35:00.716	18154...	100386087	EURUSD	0.01	1.14678	W
2020.03.09 08:35:03.583	18154...	100386088	AUDCAD	0.01	0.89541	W
2020.03.09 08:35:19.277	18154...	100386089	AUDCAD	0.01	0.89462	W
2020.03.09 08:35:22.408	18154...	100386090	AUDCAD	0.01	0.89455	W
2020.03.09 08:35:38.339	18154...	100386091	AUDCAD	0.01	0.89555	W
2020.03.09 08:35:50.265	18154...	100386092	AUDCAD	0.01	0.89569	W
2020.03.09 08:36:05.570	18154...	100386093	AUDCAD	0.01	0.89547	W
2020.03.09 08:36:17.452	18154...	100386094	AUDCAD	0.01	0.89443	W
2020.03.09 08:36:33.306	18154...	100386095	AUDCAD	0.01	0.89438	W
2020.03.09 08:36:36.571	18154...	100386096	AUDUSD	0.01	0.65563	W
2020.03.09 08:36:52.130	18154...	100386097	AUDUSD	0.01	0.65537	W
2020.03.09 08:36:55.564	18154...	100386098	AUDUSD	0.01	0.65530	W

Q * 2020.03.09 00:00 2020.03.09 23:59 Current database

For Help, press F1 1862 / 8 Kb

Depending on points selected in the context menu, various information about deals is shown here. Deals can be sorted out by any field by a left button click on the field name.

Requesting Deals

In order to view deals, a request should be constructed. A request can be performed:

- **By groups**
To do it, select a group from the dropdown list.
- **By logins**
Specify one or several account numbers separated by commas.
- **By tickets**
To request deals by their number, specify one or several tickets separated by commas. Before deal tickets the # symbol should be specified.

Further the following request parameters can be specified:

- Trading instruments for which deals will be requested. One symbol or a group of symbols can be selected from the list. Optionally, you can specify a comma separated list of trading instruments or groups of symbols. For example, Forex*, CFD*, Metals\GOLD. Please note that filtering is performed on the server side, and not on the administrator terminal side. To obtain data on other instruments, send another request. The request is performed for all financial instruments by default.
- You can specify one of predefined request periods using the  button: "Today", "Last 3 days", "Last week", "Last 3 months", "Last 6 months" and "All history".
- You can set precise time limits of the request. Indicate them manually or using the calendar that is opened at a click on button .
- Further you can specify from which database deals should be requested: current database or one of backups.

To perform the request, press the "Request" button or execute the " Request" command of the context menu.

Viewing a Deal

To start viewing or editing a deal, double click on the selected deal in the list. The trading operation dialog is a fully-featured tool with a plethora of advanced features, such as the display of the structure of operations, visualization, tick history and logs.

MetaTrader 5 trading platform

Deal #100386229 buy 0.02 EURUSD at 1.14201

John Smith, 1816500, demo\demo\forex-5-hedged, 1 : 100

Ticket	Time	ID	Type	Volume	Price	Profit
102548225	2020.03.09 09:15:47.895		sell	0.05 / 0.05	1.14195	
100386228	2020.03.09 09:15:47.896		sell	0.05	1.14195	0.00
102548392	2020.03.09 09:16:02.208		close by	0.02 / 0.02	1.14201	#102548225 by #102548075
100386229	2020.03.09 09:16:02.208		buy	0.02	1.14201	0.00 -0.12
100386230	2020.03.09 09:16:02.208		sell	0.02	1.14195	0.00 0.00
102548998	2020.03.09 09:17:05.808		buy	0.03 / 0.03	1.14213	

Details Visualization Ticks Journal

Deal: 100386229

Position: 102548225

Order: 102548392

BUY

OUT BY

0.02

EURUSD, Euro vs US Dollar

Closed volume:

0.02

Create time: 2020.03.09 09:16:02.208

Reason: Web

Dealer ID:

Expert ID:

External ID:

Comment: #102548225 by #102548075

Price: 1.14201000

Position price: 1.14195000

Stop loss: 0.00000

Take profit: 0.00000

Commission: 0.00

Fee: 0.00

Swap: 0.00

Profit: -0.12

Raw profit: -0.12

Profit rate: 1.00000000

Margin rate: 1.14201000

Gateway price: 0.00000000

Market Bid: 1.14201

Market Ask: 1.14209

Market Last: 1.14200

Modifications:

Report...

Update

Cancel

Help

Account details

The upper part of the dialog features brief information about the account, on which the operation was performed: name, login, groups and leverage. Click on this line to view [account details](#).

Overview and related operations

This block displays all the related trading operations: the order as a result of which the deal was executed, the position affected by the deal, as well as which initiated the operation, the deals performed as a result of order execution and the final position. Thus you can easily access the entire chain of related actions. Select an operation from the tree and all relevant parameters will be instantly displayed in the bottom part.

Trading operation details

The following parameters are indicated for deals:

- **Login** [account](#) number the deal has been performed on.
- **Creation time** time of deal execution.
- **Deal** a unique deal number.
- **Order** ticket (number) of the [order](#) the deal was executed on.
- **Position** ticket of the position that was opened or closed by this deal.
- **Action** deal type, and the direction of the deal relative to the current [position](#) of the account: in (entry), out (exit), in/out (position reverse) or out by (closing position with an opposite one). There are the following types of deals:
 - ◆ **Sell** selling a financial instrument.
 - ◆ **Buy** buying a financial instrument.
 - ◆ **Balance** top-up of balance via a manager terminal.
 - ◆ **Credit** crediting via a manager terminal.
 - ◆ **Charge** other financial operations on the account that do not belong to any of categories.
 - ◆ **Correction** manual correction of a client's balance.
 - ◆ **Bonus** accrual of bonuses. Operations of this type affect the credit assets of a client ("[Credit](#)" field).
 - ◆ **Commission** accrual of commission.
 - ◆ **Daily commission** deal of charging [commission](#) at the end of a trading day.
 - ◆ **Monthly commission** deal of charging commission at the end of a month.
 - ◆ **Agent commission** deal of charging agent commission (used during an [instant charge](#)).
 - ◆ **Daily agent commission** deal of accruing agent commission at the end of a trading day.
 - ◆ **Monthly agent commission** deal of accruing agent commission at the end of a month.
 - ◆ **Interest rate** deal of [accruing annual interest](#) at the end of a month.
 - ◆ **Canceled buy and Canceled sell** canceled deal. Such deal types are possible, for example, when working with an external trading system via a [gateway](#). A deal can be canceled in an external trading system. In this

case, the type of a previously performed deal in the platform (Buy or Sell) is changed to Canceled buy or Canceled sell respectively. At the same time, profit/loss of such a deal is reset. A client's position is then recalculated and an appropriate profit/loss is deposited/withdrawn in a separate balance deal. Deal cancellation does not entail changes in client orders history. Canceled buy and Canceled sell type deals do not participate in an account financial status calculation and are not considered in positions recalculation.

- ◆ **Dividend** paying taxable dividends.
- ◆ **Franked dividend** paying non-taxable dividends (tax is paid by a company, not a client).
- ◆ **Tax** charging a tax.
- ◆ **SO Compensation** negative balance compensation after a Stop Out.
- ◆ **SO Credit Compensation** resetting credit funds to zero after the negative balance compensation.
- **Volume** deal volume.
- **Closed volume** position volume closed by this deal. This field enables convenient working with reversal deals. In addition to the total volume of the executed deal, which is opposite to the current position, you can view the closed volume. This ability is especially useful if the initial reversed position is composed of several deals, and its total volume is not explicitly visible.
- **Symbol** financial instrument of the deal.
- **Price** deal price.
- **Value** deal value in client deposit currency. The rate of conversion to deposit currency is shown in the "Margin rate" field. The field is used only for Exchange* calculation type symbols and groups with the "for Stock Exchange, based on margin discount rates" risk management type.
In case of exchange risk accounting, each deal affects the account balance: the deal value is charged or deducted from the balance. In other words, the system uses the Value field here (not the Profit one, as is the case with OTC accounting). The same applies to verifying the balance using the trading history: the values of deals (rather than their results) are verified. Thus, if you change the deal price for some reason, make sure to update the Value field as well, since it is not recalculated automatically. Otherwise, the value change result is not displayed on the account balance after its verification and correction using the trading history.
- **Stop loss** the Stop Loss level. Stop Loss values for entry and reversal deals are set in accordance with the Stop Loss of orders, which initiated these deals. The Stop Loss values ☐ of appropriate positions as of the time of position closing are used for exit deals.
- **Take profit** the Take Profit level. Take Profit values for entry and reversal deals are set in accordance with the Take Profit of orders, which initiated these deals. The Take Profit values ☐ of appropriate positions as of the time of position closing are used for exit deals.
- **Reason** reasons for deal execution:
 - ◆ **Client** deal performed by a client manually through the client terminal.
 - ◆ **Expert** deal performed by a client with using an Expert Advisor.
 - ◆ **Dealer** deal performed by a dealer through the manager terminal.
 - ◆ **Stop loss** deal performed as a result of Stop Loss activation.
 - ◆ **Take profit** deal performed as a result of Take Profit activation.
 - ◆ **Stop out** deal performed when the client reached the Stop out level.

- ◆ **Rollover** deal performed when reopening a position for charging swaps.
- ◆ **External Client** deal performed by a client from an external trading system.
- ◆ **Variation margin** deal performed for accruing variation margin. Such deals are executed in pairs: one deal closes an existing position in order to register the result (accrue the variation margin), the second deal re-opens the position with the same ticket, but at the new Close price. The position ticket is written to the "Position" field of both deals.
- ◆ **Gateway** deal performed by a MetaTrader 5 gateway that had connected to the trading platform.
- ◆ **Signal** deal performed as a result of copying a trade signal according to a subscription in the client terminal.
- ◆ **Settlement** deal performed as a result of performing operations connected with the settlement of a futures contract/option. Not used at the moment.
- ◆ **Transfer** deal performed due to transferring a position at the settlement price to a new symbol with the same underlying asset. Not used at the moment.
- ◆ **Synchronization** deal performed as a result of synchronization of an account's trade state with an external system.
- ◆ **External Service** deal performed from an external trading system for technical reasons (for example, to correct the trade state of a client).
- ◆ **Mobile** the deal is conducted via the MetaTrader 5 mobile terminal for Android or iPhone.
- ◆ **Web** the deal is conducted via the web terminal.
- ◆ **Split** the deal is conducted as a result of a symbol split.
- ◆ **Corporate action** deal created as a result of a corporate action, such as consolidating or renaming securities, transferring a client to a different account, etc. API applications set this flag for service operations so that the platform does not account for such corporate actions in commission calculations.
- ◆ **Migration** deal is created while importing clients' trading operations from the MetaTrader 4 server.
- **Expert ID** the identifier (magic number) of an Expert Advisor that has executed this deal in the client terminal.
- **Commission** commission charged for deal execution. The field is only used for the standard commission charged immediately. Commission settings are specified for each group separately.
- **Fee** fee charged for deal execution. The field is used for the Fee commission type.
- **Agent commission** agent commission fees for the deal. Parameters of agent commissions are specified for each group separately.
- **Swap** charged swap.
- **Profit** profit gained from the deal.
- **Position price** open price of a position, which has been closed by this deal. This field is filled for deals that have the "out" or "in/out" type.
- **Gateway price** the field is only used for operations which are forwarded to external trading systems via gateways. It shows the actual deal price on the external system side, not taking into account gateway price transformation settings.

- **Raw profit** profit/loss of the committed deal. The profit/loss is represented in the profit currency of the symbol the deal is performed by.
- **Comment** a comment to the deal. Additional information can be written in the comment field. For example, a comment indicating an account for whose trades an agent receives the commission is automatically added to the agent commission deals;
- **External ID** a unique identifier of the deal in external systems.
- **Dealer ID** the number of the dealer's account who processed this deal. "0" specified in this field means that the deal was processed without a dealer.
- **Modifications** if the deal is changed manually, this field displays who implemented the changes:
 - ♦ **Administrator** deal changed by an administrator.
 - ♦ **Manager** open price changed by a manager.
 - ♦ **Position** deal modification data was inherited from the position closed by that deal.
 - ♦ **Restore** deal restored.
 - ♦ **Admin API** deal changed via Manager API administrator interface.
 - ♦ **Manager API** deal changed via Manager API manager interface.
 - ♦ **Server API** deal changed via Server API.
 - ♦ **Gateway API** deal changed via Gateway API.

- Deals that close positions fully or partially inherit their modification flags. After closing, no separate entry about the position remains in the database. In order not to lose data on modifications, the flags are copied to the deal closing the position. In this case, the additional Position modification flag is added to the deal meaning that the flags were inherited from the position. When inheriting, the deal modification flags are not lost. Instead, they are added to the position flags.
- The deals changed by an administrator or manager, as well as restored deals are highlighted in the list in red.
- Use Trade Modification Report to obtain information about all modified trade operations.

- **Profit rate** exchange rate of the deal profit currency to the trader's group deposit currency;
- **Margin rate** exchange rate of the margin currency to the trader's deposit currency. The value depends on the deal direction. For buy deals, it is the rate of margin currency selling for the deposit currency; for Buy deals it is the rate of currency margin buying for the deposit currency.
- **Market Bid** the market Bid price as at the time of deal execution by the server. The field is only filled for the deals which were created after the platform was updated to build 2890 or higher. For earlier deals, the value will be zero.
- **Market Ask** the market Ask price as at the time of deal execution by the server. The field is only filled for the deals which were created after the platform was updated to build 2890 or higher. For earlier deals, the value will be zero.
- **Market Last** the market Last price as at the time of deal execution by the server. The field is only filled for the deals which were created after the

MetaTrader 5 trading platform

platform was updated to build 2890 or higher. For earlier deals, the value will be zero.

If a manager's account has permissions to "Change orders", any field in this window can be edited. After all changes have been made, press "Save".

Visualization

In this section, execution of a trading operation is visualized on the tick chart of the appropriate symbol.



MetaTrader 5 trading platform

Nearest ticks before and after the operation

When examining disputable situations with traders, it is often necessary to analyze quotes which were broadcasted at the trading operation execution time. The relevant quote data can be obtained in a couple of clicks. Open operation details and navigate to the "Ticks" section. The terminal will automatically request the quote history from the server for the entire day on which the operation was performed. The nearest quote to operation execution time will be automatically selected in the list of received quotes.

Details Visualization Ticks Journal					
Date	Bid	Ask	Last	Volume	
✓ 2019.02.06 09:58:18	0.93906	0.94006	0.00000	0.00	
✓ 2019.02.06 09:58:18	0.93905	0.94005	0.00000	0.00	
✓ 2019.02.06 09:58:18	0.93906	0.94006	0.00000	0.00	
✓ 2019.02.06 09:58:18	0.93907	0.94007	0.00000	0.00	
✓ 2019.02.06 09:58:19	0.93908	0.94008	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93907	0.94007	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93904	0.94004	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93901	0.94001	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93898	0.93998	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93900	0.94000	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93899	0.93999	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93900	0.94000	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93901	0.94001	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93900	0.94000	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93901	0.94001	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93899	0.93999	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93898	0.93998	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93897	0.93997	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93898	0.93998	0.00000	0.00	

Update

Cancel

Help

Operation journal

This is another tool to assist during the follow-up operation examination. There is no need to manually request logs from the server and to filter its records. Open operation details, navigate to the "Journal" section and the terminal will automatically request the necessary logs from the server, using ticket and time interval filters (from the operation date to the current day).

Time	IP	Message
2019.05.13	(20490 kb)	-----
* 2019.05.13 15:25:54.684	11.14.194.2	'1815606': order placed [#100329729 buy limit 1.00 AUDCAD at 0.93559], time 0.79 ms
* 2019.05.13 15:28:51.242	11.14.194.2	'1815606': modify order #100329729 buy limit 1.00 AUDCAD at 0.93559 sl: 0.00000 tp: 0.00...
* 2019.05.13 15:28:51.242	11.14.194.2	'1815606': request confirmed, rule 'Auto Execution' (modify #100329729 buy limit 1.00 AUDC...
* 2019.05.13 15:28:51.242	11.14.194.2	'1815606': order modified [#100329729 buy limit 1.00 AUDCAD at 0.93531], time 0.48 ms
* 2019.05.13 15:28:57.667	11.14.194.2	'1815606': modify order #100329729 buy limit 1.00 AUDCAD at 0.93531 sl: 0.00000 tp: 0.00...
* 2019.05.13 15:28:57.667	11.14.194.2	'1815606': request confirmed, rule 'Auto Execution' (modify #100329729 buy limit 1.00 AUDC...
* 2019.05.13 15:28:57.667	11.14.194.2	'1815606': order modified [#100329729 buy limit 1.00 AUDCAD at 0.93531], time 0.58 ms
* 2019.05.13 17:04:08.806		'1815606': order [#100329729 buy limit 1.00 AUDCAD at 0.93531] triggered, activation price...
* 2019.05.13 17:04:08.806		'1815606': activate order #100329729 buy limit 1.00 AUDCAD at 0.93531 (0.93430 / 0.9353...
* 2019.05.13 17:04:08.806		'1815606': request confirmed at client price 0.93531, rule 'Auto Execution' (activate #10032...
* 2019.05.13 17:04:08.807		'1815606': order performed buy 1.00 at 0.93531 [#100329729 buy limit 1.00 AUDCAD at 0...
2019.05.14	(20480 kb)	-----
* 2019.05.14 15:30:53.643	11.14.194.2	'1026605': server journal (#100329729, 2019.05.13 - 2019.05.14)


#100329729
Full
All
2019.05.13
2019.05.14
Request

Update
Cancel
Help

Trading operation report

The trading operation details available in the editing dialogs can be saved as a report. The report contains the entire chain of operations from an order to a position, visualization on a tick chart, extract from the server log and the trading account overall status.


To generate a file, click "Report" in the context menu in the "Overview and related operations" section. Next, select data to be saved: account state, trading totals, logs, tick chart, etc.



Select the path on the disk and click "Save".

Backup Databases of Deals

Backup copies are copies of the deal database at certain points in time. They are created daily on the backup server. To get the list of available backup copies, select "More backups..." and specify a time period:



After specifying a period the additional items will appear in the field of choosing database all the backups made for the specified period of time. Then you should request deals from the selected database. Any deal can be restored to the current database using the "🔄 Restore" command of the context menu.

Restored deals are not deleted from the backup databases.

Context Menu


The context menu of the "Deals" section contains the following commands:

- **Edit** modify a selected order;
- **Delete** delete a selected order;
- **Request** execute a request;
- **Restore** restore a selected deal from a backup database to the current one.
This command is active only if a backup database is currently requested;
- **Copy As** copy deals selected in the list:
- **Lines** copy entire selected information.
- **List of Logins** copy the list of logins only.
- **List of Tickets** copy the list of tickets only.
- **Export** export requested orders as a *.HTM, *.HTML file or as a *.CSV file;
- **Journal** request the journal entries by a selected deal;
- **Find** open the search window;
- **Show Milliseconds** show the time of trade operations with a millisecond precision;
- **Auto Arrange** if this option is enabled the size of columns is selected automatically;
- **Grid** this option shows/hides field separators in the table with deals;
- **Columns** using this sub-menu, one can choose which details of deals will be displayed in the list.

MetaTrader 5 Trading Platform / Platform Setup / Positions

Positions

This section allows working with all current positions of your traders.



MetaQuotes - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Import Export Apply + Settings X Back Forward Sort

Security

Time

Holidays

Groups (520)

Clients & Accounts

Orders & Deals

Positions

Orders

Deals

Gateways

Data Feeds

Plugins

Reports

ECN

Routing

Funds & ETF

Symbols (87418)

Time	Login	Position	Symbol
2017.02.14 09:24:33.609	1813133	100092449	CADCHF
2017.02.14 09:24:43.168	1813133	100092450	EURUSD
2017.03.09 11:31:52.777	1813220	100096335	AUDCAD
2017.03.09 11:31:15.580	1813220	100096325	AUDJPY
2017.03.09 11:31:56.165	1813220	100096336	EURCAD
2017.03.09 11:31:18.664	1813220	100096326	EURCHF
2017.03.09 11:31:21.461	1813220	100096327	EURGBP
2017.03.09 11:31:02.853	1813220	100096323	EURUSD
2017.03.09 11:31:33.742	1813220	100096330	GBPUSD
2017.03.09 11:31:44.576	1813220	100096333	USDCAD
2017.03.09 11:31:37.403	1813220	100096331	USDCHE
2017.03.09 11:31:41.002	1813220	100096332	USDJPY
2017.07.21 18:55:21.626	1813252	100253264	AUDUSD
2017.07.24 03:08:28.498	1813252	100253265	AUDUSD
2017.08.22 14:04:21.779	1813252	100256665	AUDUSD

Q * More backups... Request

For Help, press F1

4915 / 25 KB

MetaTrader 5 trading platform

Depending on the items chosen in the context menu, different information about positions is displayed here. Positions can be sorted out by any field. To do it, click on its name.

The trading platform supports two position accounting systems: netting and hedging.

Requesting Positions

To view current positions, compose a request in the line located in the lower part of the section. The request can be performed:

- **By Groups**

To do it, select a group from the dropdown list.

- **By Logins**

To do it, should specify one or several logins separated with commas.

To request all positions, specify the asterisk (*).

Further the following request parameters can be specified:

- Trading instruments for which positions will be requested. One symbol or a group of symbols can be selected from the list. Optionally, you can specify a comma separated list of trading instruments or groups of symbols. For example, Forex*, CFD*, Metals\GOLD. Please note that filtering is performed on the server side, and not on the administrator terminal side. To obtain data on other instruments, send another request. The request is performed for all financial instruments by default.
- Further you can specify from which database positions should be requested: current database or one of backups. To perform the request, press the "Request" button or execute the "🔄 Request" command of the context menu.

Viewing a Position

To view or to edit a position, double-click on it in the list. The trading operation dialog is a fully-featured tool with a plethora of advanced features, such as the display of the structure of operations, visualization, tick history and logs.

MetaTrader 5 trading platform

Position #100096325 sell 1.00 AUDJPY 86.022

John Smith, 1816500, demo\demo forex-5-hedged, 1 : 100

Ticket	Time	ID	Type	Volume	Price	Fee	Profit
100096325	2017.03.09 11:31:15.580	100096325	sell	1.00	86.022		15 815.9
100096325	2017.03.09 11:31:15.579		sell	1.00 / 1.00	86.022		
100094840	2017.03.09 11:31:15.580		sell	1.00	86.022	0.00	0.0

Details

Visualization

Ticks

Journal

Position: 100096325

SELL

1.00

AUDJPY, Australian Dollar vs Japanese Yen

Opened: 2017.03.09 11:31:15.580

Updated: 2017.03.09 11:31:15.580

Reason: Web

Dealer ID:

Expert ID: 173339640206990851

External ID:

Comment: Demo

Disabled activations:

Modifications:

Open price: 86.022000

Current price: 67.534

Stop loss: 125.000

Take profit: 62.000

Swap: 0.00

Profit: 15815.90

Profit rate: 0.00680342

Margin rate: 0.74964000

Report...

Update

Cancel

Help

Account details

The upper part of the dialog features brief information about the account, on which the operation was performed: name, login, groups and leverage. Click on this line to view [account details](#).

Overview and related operations

This block shows the orders and deals related to the selected position, i.e. the entire history of position opening and change. Thus you can easily access the entire chain of related actions. Select an operation from the tree and all relevant parameters will be instantly displayed in the bottom part.

Trading operation details

The following parameters are indicated for positions:

- **Login** [account](#) number the position was opened on.
- **Position** ticket (unique number) of the position. Usually, a position ticket matches the [ticket of the order](#) used to open the position. The exceptions are positions re-opened as a result of service operations or opened without placing an order. The tickets may be different for positions having the following [opening reasons](#):
 - ◆ Rollover charging swaps with position re-opening
 - ◆ Split re-opening a position after a split
 - ◆ Variation margin re-opening a position after charging a variation margin
 - ◆ Synchronization opening a position when synchronizing with an external system (without a previous order)
 - ◆ Transfer relocating a position with a calculated price to a new symbol with the same underlying asset

Tickets of positions having other opening reasons match initial orders.

A position ticket changes when it is reversed in a single [in/out deal](#) (used in the [netting mode](#)).

- **Open Time** time when the position was opened.
- **Update Time** last position modification time (when its volume was changed). This is actually the time of the last deal for the financial instrument which corresponds to this position. This time does not change when Stop Loss or Take Profit is modified or when the position is edited via the Administrator terminal or API.
- **Type** type of the position - buy or sell.
- **Symbol** [symbol](#) the position was opened for.
- **Volume** the current position volume in lots.
- **Reason** reasons for position opening:
 - ◆ **Client** opened by a client manually through the client terminal.
 - ◆ **Expert** opened by a client with using an Expert Advisor.
 - ◆ **Dealer** opened by a dealer through the manager terminal.

MetaTrader 5 trading platform

- ◆ **Stop loss** not used for positions.
- ◆ **Take profit** not used for positions.
- ◆ **Stop out** not used for positions.
- ◆ **Rollover** opened when reopening a position for charging swaps.
- ◆ **External Client** opened by a client from an external trading system.
- ◆ **Variation margin** not used for positions.
- ◆ **Gateway** opened by a MetaTrader 5 gateway that had connected to the trading platform.
- ◆ **Signal** opened as a result of copying a trade signal according to a subscription in the client terminal.
- ◆ **Settlement** opened as a result of performing operations connected with the settlement of a futures contract/option. Not used at the moment.
- ◆ **Transfer** opened due to transferring a position at the settlement price to a new symbol with the same underlying asset. Not used at the moment.
- ◆ **Synchronization** opened as a result of synchronization of an account's trade state with an external system.
- ◆ **External Service** opened from an external trading system for technical reasons (for example, to correct the trade state of a client).
- ◆ **Mobile** position opened via the MetaTrader 5 mobile terminal for Android or iPhone.
- ◆ **Web** position opened via the web terminal.
- ◆ **Split** position opened as a result of a symbol split.
- ◆ **Corporate action** position created as a result of a corporate action, such as consolidating or renaming securities, transferring a client to a different account, etc. API applications set this flag for service operations so that the platform does not account for such corporate actions in commission calculations.
- ◆ **Migration** position opened as a result of import of clients' trading operations from the MetaTrader 4 server.
- **Price** weight-average price of the position opening: $(\text{price of deal 1} * \text{volume of deal 1} + \dots + \text{price of deal N} * \text{volume of deal N}) / (\text{volume of deal 1} + \dots + \text{volume of deal N})$. The accuracy of rounding of the average weighted price is equal to the number of decimal places in the symbol price plus three additional digits.

The weighted average price is calculated sequentially, as the position increases or is partially closed. For example, a client trading in a netting group has executed the following series of trades:

1. Buy 0.01 EURUSD at 1.10050 (In)
2. Buy 0.02 EURUSD at 1.10052 (In)
3. Sell 0.02 EURUSD at 1.10067 (Out)
4. Buy 0.01 EURUSD at 1.10056 (In)

At each step, the following value will be displayed in the position open price:

1. The value of 1.10050 as is, since the position entry was performed in one trade
2. When the position is increased, the weighted average open price is calculated: $(1.10050 * 0.01 + 1.10052 * 0.02) / (0.01 + 0.02) = 1.10051333$
3. After partial closing of the position (0.02 lots out of 0.03 are closed), the

client is left with a 0.01-lot position with the open price of 1.10051333

4. When the position is further increased, the new weighted average price is calculated taking into account the previous calculated one: $(1.10051333 * 0.01 + 1.10056 * 0.01) / (0.01 + 0.01) = 1.10053666$

- **Stop Loss** the Stop Loss level of the position.
- **Take Profit** the Take Profit level of the position.
- **Profit** the current profit on this position. The profit does not include swap and commission.
- **Current Price** the current price of the symbol of the position.
- **Swap** swaps charged.
- **Margin Rate** exchange rate of the margin currency to the trader's deposit currency. It is usually calculated and registered at the moment when a position is opened or its volume is modified. The rate can be recalculated at the end of the trading day if the relevant option is enabled in symbol settings.
- **Profit rate** exchange rate of the position profit currency to the trader's group deposit currency.
- **Comment** a comment to the position. A comment to a position is inherited from the last deal by the symbol of the position.
- **Expert** the identifier (magic number) of an Expert Advisor that has opened this position in the client terminal.
- **ID** a unique identifier of the position in external systems;
- **Dealer** the login of a dealer (gateway) that processed an order, which opened the position. If "0" is specified in this field, it means that the order was processed without a dealer.
- **Disable activation** additional conditions (flags), with which order activation is prohibited. The flags can be set by Gateway API when orders are sent to an external system. For example, if activation of stop loss and take profit must be controlled by an external system, a flag disabling activation on the MetaTrader 5 side can be set for the order. Order flags are inherited by positions created upon order execution. Available flags:
 - ◆ **Limit** no processing of limit level hitting.
 - ◆ **Stop** no processing of stop level hitting.
 - ◆ **Stop Limit** no processing of stop limit level hitting.
 - ◆ **SL** no processing of Stop Loss activation.
 - ◆ **TP** no processing of Take Profit activation.
 - ◆ **Stop Out** no processing of Stop Out activation.
 - ◆ **Expiration** no processing of expired order cancellation.
- **Modifications** if the position is changed manually, this field displays who implemented the changes:
 - ◆ **Administrator** position changed by an administrator.
 - ◆ **Manager** open price changed by a manager.
 - ◆ **Restore** position restored.
 - ◆ **Admin API** position changed via Manager API administrator interface.
 - ◆ **Manager API** position changed via Manager API manager interface.
 - ◆ **Server API** position changed via Server API.
 - ◆ **Gateway API** position changed via Gateway API.

- Deals that close positions fully or partially inherit their modification flags. After closing, no separate entry about the position remains in the database. In order not to lose data on modifications, the flags are copied to the deal closing the position. In this case, the additional Position modification flag is added to the deal meaning that the flags were inherited from the position. When inheriting, the deal modification flags are not lost. Instead, they are added to the position flags.
- The positions changed by an administrator or manager, as well as restored positions are highlighted in the list in red.
- Use Trade Modification Report to obtain information about all modified trade operations.

Visualization

In this section, execution of a trading operation is visualized on the tick chart of the appropriate symbol.



MetaTrader 5 trading platform

Nearest ticks before and after the operation

When examining disputable situations with traders, it is often necessary to analyze quotes which were broadcasted at the trading operation execution time. The relevant quote data can be obtained in a couple of clicks. Open operation details and navigate to the "Ticks" section. The terminal will automatically request the quote history from the server for the entire day on which the operation was performed. The nearest quote to operation execution time will be automatically selected in the list of received quotes.

Details Visualization Ticks Journal					
Date	Bid	Ask	Last	Volume	
✓ 2019.02.06 09:58:18	0.93906	0.94006	0.00000	0.00	
✓ 2019.02.06 09:58:18	0.93905	0.94005	0.00000	0.00	
✓ 2019.02.06 09:58:18	0.93906	0.94006	0.00000	0.00	
✓ 2019.02.06 09:58:18	0.93907	0.94007	0.00000	0.00	
✓ 2019.02.06 09:58:19	0.93908	0.94008	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93907	0.94007	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93904	0.94004	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93901	0.94001	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93898	0.93998	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93900	0.94000	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93899	0.93999	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93900	0.94000	0.00000	0.00	
✓ 2019.02.06 09:58:20	0.93901	0.94001	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93900	0.94000	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93901	0.94001	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93899	0.93999	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93898	0.93998	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93897	0.93997	0.00000	0.00	
✓ 2019.02.06 09:58:21	0.93898	0.93998	0.00000	0.00	

Update

Cancel

Help

Operation journal

This is another tool to assist during the follow-up operation examination. There is no need to manually request logs from the server and to filter its records. Open operation details, navigate to the "Journal" section and the terminal will automatically request the necessary logs from the server, using ticket and time interval filters (from the operation date to the current day).

Time	IP	Message
2019.05.13	(20490 kb)	-----
* 2019.05.13 15:25:54.684	11.14.194.2	'1815606': order placed [#100329729 buy limit 1.00 AUDCAD at 0.93559], time 0.79 ms
* 2019.05.13 15:28:51.242	11.14.194.2	'1815606': modify order #100329729 buy limit 1.00 AUDCAD at 0.93559 sl: 0.00000 tp: 0.00...
* 2019.05.13 15:28:51.242	11.14.194.2	'1815606': request confirmed, rule 'Auto Execution' (modify #100329729 buy limit 1.00 AUDC...
* 2019.05.13 15:28:51.242	11.14.194.2	'1815606': order modified [#100329729 buy limit 1.00 AUDCAD at 0.93531], time 0.48 ms
* 2019.05.13 15:28:57.667	11.14.194.2	'1815606': modify order #100329729 buy limit 1.00 AUDCAD at 0.93531 sl: 0.00000 tp: 0.00...
* 2019.05.13 15:28:57.667	11.14.194.2	'1815606': request confirmed, rule 'Auto Execution' (modify #100329729 buy limit 1.00 AUDC...
* 2019.05.13 15:28:57.667	11.14.194.2	'1815606': order modified [#100329729 buy limit 1.00 AUDCAD at 0.93531], time 0.58 ms
* 2019.05.13 17:04:08.806		'1815606': order [#100329729 buy limit 1.00 AUDCAD at 0.93531] triggered, activation price...
* 2019.05.13 17:04:08.806		'1815606': activate order #100329729 buy limit 1.00 AUDCAD at 0.93531 (0.93430 / 0.9353...
* 2019.05.13 17:04:08.806		'1815606': request confirmed at client price 0.93531, rule 'Auto Execution' (activate #10032...
* 2019.05.13 17:04:08.807		'1815606': order performed buy 1.00 at 0.93531 [#100329729 buy limit 1.00 AUDCAD at 0...
2019.05.14	(20480 kb)	-----
* 2019.05.14 15:30:53.643	11.14.194.2	'1026605': server journal (#100329729, 2019.05.13 - 2019.05.14)


#100329729 Full All 2019.05.13 2019.05.14 Request

Update Cancel Help

Trading operation report

The trading operation details available in the editing dialogs can be saved as a report. The report contains the entire chain of operations from an order to a position, visualization on a tick chart, extract from the server log and the trading account overall status.


To generate a file, click "Report" in the context menu in the "Overview and related operations" section. Next, select data to be saved: account state, trading totals, logs, tick chart, etc.



Select the path on the disk and click "Save".

Backup Databases of Positions

Backup copies are copies of the position database at certain points in time. They are created daily on the backup server. To get the list of available backup copies, select "More backups..." and specify a time period:



After specifying a period the additional items will appear in the field of choosing database all the backups made for the specified period of time. Then you should request positions from the selected database. Any position can be restored to the current database using the "🔄 Restore" command of the context menu.

- Restored positions are not deleted from the backup databases.
- When a position is restored, the deals that formed the position are not restored.

Context Menu

The context menu of this section contains the following commands:

-  **Edit** open a selected position for editing;
-  **Delete** delete a selected position;
-  **Request** request positions;
-  **Restore** restore a selected position from a backup database to the current one. This command is active only if a backup database is currently requested;
- **Copy As** copy positions selected in the list:
-  **Lines** copy entire selected information.
- **List of Logins** copy the list of logins only.
- **List of Tickets** copy the list of tickets only.
-  **Export** export requested positions as a *.HTM, *.HTML file or as a *.CSV file;
-  **Find** open the search window;
- **Show Milliseconds** show the time of trade operations with a millisecond precision;
- **Auto Arrange** if this option is enabled the size of columns is selected automatically;
- **Grid** this option shows/hides field separators in the table with positions;

MetaTrader 5 trading platform

- **Columns** using this sub-menu, one can choose which details of positions will be displayed in the list.


MetaTrader 5 Trading Platform / Platform Setup / Gateways

Gateways

Gateways integrate MetaTrader 5 with external trading systems. With this integration, you can provide the possibility for your traders to execute trading operations on almost any exchange. They will receive quotes and will execute trades in their familiar terminal while all their operations will be forwarded to an external system.

The platform offers a variety of built-in turnkey gateways for integration with exchanges and trading systems. You can test them right away. Additional third-party solutions are featured in the App Store. Using the Gateway API, you can create your own gateways for integration with any trading systems.

In the Gateway section, available solutions can be viewed in two modes: product showcase and configuration list. You can switch between them using buttons  and .



Broker-Demo - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Export Import Apply + Settings X Sort

Gateways

Gateways connect the platform to liquidity provider...

Name	Mode	Server	Groups	Symbols	Last action
MetaTrader 5 WL	T + Q	78.140.180....	*	Forex*;ECN*	Onli
Currenex Gateway	T + Q	dret-fix-ssl...	*	*	Onli
Liquidity provider 1	T + Q	203.4.179.1...	*	*	2022.02.14 11:13:
Liquidity provider 2	T + Q	access.met...	*	*	2022.02.14 11:13:
Broker 1	T + Q	access.met...	*	*	Onli
Broker 2	T + Q	access.met...	*	*	Onli
Broker 3	T + Q	broker.serv...	*	*	2022.02.14 11:13:

Selected Available

For Help, press F1

1292 / 0 KB

MetaTrader 5 trading platform

The product showcase provides basic information: gateway name, connection status and the amount of transmitted Market Depth and tick data. The Selected tab displays all gateways for which you have configurations. The Available tab features all gateway modules available on the History server. You can configure them at any time.

The list mode enables the management of existing gateway configurations. It provides quick access to the main parameters:

- **Name** gateway name.
- **Mode** gateway operation mode: receives quotes (Q), processes operations (T), or both.
- **Server** the address of the external trading system server to which the gateway connects.
- **Groups** groups available to the gateway.
- **Symbols** symbols available to the gateway.
- **Last active** data and time of the last successful connection of the gateway to the external system.
- **ID** gateway identifier used to identify trade requests processed by this gateway.
- **Status** connection status and the number of trading operations processed by the gateway/total transmitted ticks and Market Depth changes.

Using the context menu, you can adjust the set of displayed data.

How Gateways Work

The interaction of gateways and servers is performed through the special library MT5APIGateway.dll.

For receiving quotes and news, the gateway connects to the history server. At that the priority of transmission of quotes for a symbol is determined in the same way as for data feeds by the position of configuration of the gateway in the list. This is described in more details in a separate section.

To perform trade operations, all trade servers of the platform connect to the gateway.

MetaTrader 5 trading platform



Switching between Gateway

The position of a gateway in the list defines its priority in the delivery of data: the higher the position is, the higher the priority of the gateway is. However, a server is permanently receiving information from all gateway at once. Such a solution allows to immediately switch to another gateway in case of problems. For example, several gateways deliver quotes of the same symbol from different financial companies - the priority defines what gateway should be used. If the required data are not received from the selected gateway for a certain period of time, the server automatically switches to the next gateway that provides information on the same symbol. However, as soon as data from the gateway with higher priority are received, the server will switch back to it.

- The idle timeout of a gateway is set up on the history server settings in "Datafeeds timeout".
- For symbols with the depth of market enabled the current data source (a gateway of a data feed) is determined by the first quote that comes after starting the history server.
- Switching of gateways for a symbol can be tracked in the "Ticks" section.
- Flow of quotes for a symbol coming from a gateway has a higher priority than a flow from a data feed. Switching to quotes from a data feed occurs in case the data flow from the gateway has stopped.
- Switching of gateways is performed independently for each symbol.

The process of activation of a quotes flow from a certain gateway is reflected in the history server journal. To find such records, use the keyword "activation".

Possible delay in the delivery of Market Depth prices after switching gateways

To consume less resources, the history servers does not store the best prices and Market Depth values for each symbol and each available data source. For the same purpose, the Market Depth is passed from the data feed to the server in the form of changes relative to the previous state. Additionally, the full Market Depth snapshot is sent to the server no more than once every 30 seconds.

Therefore, if the main price feed is stopped and the server switches to the reserve one, the server has to wait for the first Market Depth snapshot from the data feed. During this time (up to 30 seconds), the Market Depth data is not updated.

Setting Up Gateways

The gateways are configured in two steps:

- **Configuration of a gateway** configuration of the gateway itself;
- **Setting up the routing** setting up the routing of trade requests to be processed by the gateway.

To view the logs of gateways, select it in the tree-like list in the left part of the terminal and go to the "Journal" tab.

Context Menu

The context menu of the "Gateways" section contains the following commands:

- **+ Add** add a new gateway;
- **⚙ Edit** edit the selected gateway;
- **✗ Delete** delete the selected gateway;
- **↑ Move Up** move the selected gateway up relative to others;
- **↓ Move Down** move the selected gateway down relative to others;
- **↕ Sort Alphabetically** sort configurations alphabetically. Please note that sorting is done on the server, not in the local terminal.
- **▶ Enable** enable the selected configuration.
- **◻ Disable** disable the selected configuration.
- **Automation triggers** create an automation task for the selected event or edit an existing one. The menu displays only the triggers and tasks associated with the current section.
- **Automation actions** add an automation action to an existing task or create a new task based on the action. The menu displays only the actions associated with the current section.
- **📁 Export to File** export the settings of gateways to a file.
- **📁 Import from File** import the settings of gateways to a file.
- **📖 Journal** request logs according to the selected configuration. This will open the trade server logs section, with the name of the selected configuration automatically specified in the query field. You will only need to press the request button.
- **🔍 Find** open the Search window;
- **Auto Arrange** if this option is enabled the size of columns is selected automatically;
- **Grid** this option shows/hides field separators in the table with the gateways.


MetaTrader 5 Trading Platform / Platform Setup / Gateways /
Configuration of Gateways

Configuration of Gateways

In order to add or modify a gateway, in the Gateways section click "+ Add" or "⚙ Edit", respectively. In order to delete a gateway, click "✗ Delete". These commands are also available in the Edit menu, on the toolbar and in the context menu.

Additional general information about working with configuration records is given in the "Working with Instructions" section.

Common



The screenshot shows the 'Gateway' configuration window with the 'Common' tab selected. The window title is 'Gateway'. The 'Common' tab is active, showing a description: 'This gateway allows connecting to a remote MetaTrader 5 Platform' with a yellow and blue icon. Below this, there is a checked 'Enable' checkbox. The 'Name' field is 'MetaTrader 5 Gateway' and the 'ID' field is '10'. The 'Module' dropdown is set to 'MetaTrader 5 Gateway' and the 'Trade and Quotes' dropdown is set to 'Trade and Quotes'. The 'Trading server' field is 'access.metatrader5.com:443'. The 'Trading login' field is '1000' and the 'Password' field is masked with dots. A blue link 'Show additional network settings' is present. At the bottom, there are 'OK', 'Cancel', and 'Help' buttons.

Field	Value
Name	MetaTrader 5 Gateway
ID	10
Module	MetaTrader 5 Gateway
Trade and Quotes	Trade and Quotes
Trading server	access.metatrader5.com:443
Trading login	1000
Password	

This tab is used for setting up main parameters of the gateway:

- **Enable** enable/disable the gateway. For the gateways running as a service via the "Remote gateway" module, unchecking "Enable" will lead to disconnection of platform servers from the gateway service, while the service itself will not be stopped.
- **Name** name of the gateway. Use of special characters (?, *, <, > etc.) is not allowed, as this may cause issues while working with the gateway log files.
- **ID** in this field you should specify a unique identifier of the gateway. This exact identifier will be written to the "Dealer" field of deals processed by the gateway. This identifier is also used when creating the rules of routing of trade requests to the gateways.
The ID cannot be changed in an existing gateway configuration. To change it, create a new configuration and delete the old one.
- **Module** name of the executable file of the gateway. In this field you should select one of the available executable files of gateways found in the */gateways* directory of the history server. The unlimited number of configurations with different settings can be created for each module. In the field to the right, you can select one of the modes of operation supported by the gateway:
- **Trade and Quotes** in this mode, the gateway translates quotes and processes trade operations.
- **Trade Only** in this mode, the gateway only processes trade operations. This mode can be used when working with an external trading system through several accounts in it. At that there are several corresponding configurations of the same gateway. In this case, quotes are provided by one configuration, and the others work only with trade operations.
- **Trading server** address of server of an external trade system the gateway will connect to.
- **Trading login** login of an account for connection to the external trade system.
- **Password** password to an account for connection to the external trade system.

- ID of the gateway must not coincide with any of the manager accounts. When adding a new gateway or editing an existing one, the system checks availability of the identifier of the gateway. If the value is not allowed, the settings of the gateways won't be saved or modified respectively.
- When you change any of the parameters, the gateway automatically restarts to apply the changes.

Advanced Network Settings

Additional network settings include history/trade server to gateway connection parameters. These settings are designed to provide the security of operation between the server and the gateway. In most cases, the settings are hidden and do not require configuration (the history server sets the required address and connection parameters).

These parameters need to be specified in two cases: when working in the remote gateway mode, and if the address/port selected for the gateway is busy. In the second case, the following message is written to the log: gateway address 'Gateway name' already used, please setup another address for gateway.

- **Gateway sever** address at which the gateway will receive connections from the history and trade servers. The system automatically determines available addresses of network interfaces of the history server and displays them in this field. The list includes a special address history.server:port. For example, history.server:12345. Peculiarities of using such address:
 - ♦ The gateway will accept connections on the specified port of all the IP addresses the history server works on (they are specified in the list of listen addresses on the "Network" tab of the history sever).
 - ♦ The gateway will accept connections from the trade servers on the public access points of the history server (they are specified in the list of public addresses on the "Network" tab of the history server).
 - ♦ If the list of list addresses of the history server includes 0.0.0.0, then the gateway will use this address for operation. 0.0.0.0 means listening on all addresses.
- ♦ Specifying the address in this way allows automatic switching the history server with set up local gateways to a backup server without need to set up the addresses of the gateways manually.
- ♦ An address in this format cannot be used for remote gateways since they do not know the platform environment.
- **Gateway login** login that will be used for authorization of the history and trade servers on the gateway. Only a positive number can be specified as a login.
- **Password** password that will be used for authorization of the history and trade servers on the gateway. The password must fulfill the security requirements (at least 6 characters long with two of three types of symbols: upper case letters, lower case letters and digits).

You can also specify the address 127.0.0.1 or localhost for the gateway server. This is the so-called Loopback or a virtual network interface, which is not linked to any hardware. Such addresses are used by default when the gateway, the history server and trade servers operate on the same computer. For such addresses, the platform performs additional checks to ensure proper operation:


1. The platform receives lists of addresses listened by the history and trade servers
2. If at least one trade server does not have the same address as the history server, it is considered that at least one platform component is installed on another physical computer.
3. In this case, the gateway will not be run on localhost (127.0.0.1), but on a set of listening addresses of the history server. The port specified in the "Gateway server" parameter is used for the port. For example, if the address 127.0.0.1:16387 is specified for a gateway, and the server operates on 192.168.0.1:442, the gateway will run on 192.168.0.1:16387.

MetaTrader 5 trading platform

4. When connecting to the gateway, the trade server also determines which address to connect to (as in points 1 and 2): Loopback or a set of addresses. The port specified in the "Gateway server" parameter is used for the port. The following addresses are used for the set of addresses (in the order of priority):
- Public addresses of the history server
 - Local addresses listened by the history server, which coincide with its public points (located on the same subnet).

If you install the gateway as a service on the Loopback address and then move any of the platform components to a different computer, the gateway will become unavailable for that component.

Groups



MetaTrader 5 trading platform

At this tab you should specify the groups of clients whose trade operations will be processed by the gateway. Orders, deals and positions of clients from these groups will be translated to external trade systems through the gateway. The following commands are available for managing groups:


- **Add** add a group. After you press this button, a new field will appear. A click on this field will open a list where you should specify a group or a subgroup from those available on the server. For more details please read "[Specifying Symbols and Groups](#)";
- **Delete** delete a selected group;
- **Edit** modify a selected group. The same action can be performed by a double click on an entry.

Allow importing traders balances

Using this option you can allow or restrict the gateway to change and correct the balance of traders. For this option to be active, the corresponding functional must be supported by the gateway.

This functional is required when an external trading system on its own performs the accounting of the financial results for trade accounts (for example, it can calculate and correct the balance at the end of a trade day).

Symbols



In this section, specify the symbols that will be available to the gateway. For these symbols, the gateway will:

- Receive and update (if import is allowed) settings
- Deliver quotes

Unlike group settings, the list of available symbols does not affect the trade requests which the gateway can receive. The way in which the gateway will handle such requests depends on the gateway implementation. To avoid unexpected behavior, it is recommended to correctly configure request routing to the gateway, specifying only the necessary symbols in the rules.

Click "Add" and select the desired symbol or group of symbols. They can also be specified manually: one or multiple symbols separated by commas.

You can additionally use mask "*" and the negation sign "!". For example, Cboe FX*,!Cboe FX\EURUSD all symbols from the Cboe FX group except EURUSD. The exception does not work for a single "*" mask. It always allows all symbols:

- Forex*,!Forex\EURUSD all symbols in the Forex subgroup, except EURUSD.
- *,!Forex\EURUSD all symbols. The EURUSD symbol will not be excluded.

For details, please visit the [Specification of Symbols and Groups](#) section.

If the symbol row in the table is highlighted in red, then this symbol no longer exists. It may have been moved or deleted. Open the entry and edit the symbol path.

The priority of a gateway is always higher than that of a data feed when it is used as a source of quotes.

Allow to import symbol settings

Using this option you can enable/disable import of settings of symbols, which data the gateway translates and for which perform trade operations. For this option to be active, the corresponding functional must be supported by the gateway.

Import of symbol settings via the gateway has a number of features:

- If a symbol does not present in the platform, it will be created in the Preliminary group.
- All newly added symbols are imported with trading disabled. The administrator must manually enable trading after checking the settings.
- If a symbol is already available in the platform, then only its trading settings will be updated.

The automatic import of symbol setting greatly simplifies the work of the platform administrator. Instead of adding and specifying the settings manually, now it is only necessary to move symbols from the Preliminary group to the required one and enable trading.

MetaTrader 5 trading platform

When a gateway changes symbol settings, the "symbol config updated" entry appears in the Main Trade Server journal. The gateway name is specified as the IP address of the entry source (the IP field).

When the "Allow importing symbol settings" option is enabled, the gateway can add and edit any symbols in the Preliminary* group, even if it is not indicated in the list above.

Translations

Gateway

Common Groups Symbols **Translations** Parameters Timeouts Monitoring

If necessary, please specify parameters for converting data transmitted through the gateway: name of the source symbol in the external system and value of correction of incoming prices. If any of the parameters is not set, its source values will be used.

Up

Down

Add

Edit

Delete

Symbol	Source	Bid	Ask
EURUSD		-1	1

OK Cancel Help

Information that is received from the gateway can be converted:

- **Symbol** name of a symbol at the MetaTrader 5 server.
If another source of quotes is set in the specified symbol (in the "Source" field) or the option "Allow realtime quotes from data feeds" is disabled, then the translation setting will only apply to trade requests sent through the gateway. The symbol name and prices will be translated in the requests. The translation setting will not affect the streamed symbol quotes.
- **Source** name of a symbol in the external trade system (initial name of the symbol). This parameter is intended for adjust the names of symbols in the external trade system in accordance with the names of symbols in the platform;
- **Bid** in this field you can specify a number of points to change the Bid prices by.
- **Ask** in this field you can specify a number of points to change the Ask prices by.

If any of the parameters is not set, its source values will be used. For example, if the name of symbol in the external trade system is not specified, it is considered that the symbol name in the external system is the same as the symbol name in the platform.


If more than one translation settings match the same symbol on the platform side, only the one located higher in the list will be applied. For example, the following settings are available:

- EURUSD.GW | EURUSD | Bid -1 | Ask +1
- *.GW | * | Bid -2 | Ask +2

In this case, EURUSD prices will be changed by -1/+1, and the prices of all other symbols will be changed by -2/+2.

- When translating prices, make sure the prices are correct. Usually a negative (or zero) value is indicated for the Bid price, and a positive (or zero) value is indicated for Ask. Otherwise, you may get a negative spread.
- Translations also affect the depth of market. Consider an example, when the Bid value is set to -10 and the Ask value is set to 10. There are sell requests at the price 120 and 110, and buy requests at the price 90 and 80. As a result of conversion, the price of the sell requests will be changed to 130 and 120, and the price of buy requests will be changed to 80 and 70.
- Find out more in the "Symbol and Price Translation" section.

Parameters



This tab allows to specify additional parameters of a gateway that are not implemented at the "Server" tab. Presence of this parameters is stipulated by a necessity of passing additional settings to a gateway for its correct operation. The parameters are described in these fields:

- **Parameter** name of a parameter;
- **Value** value of a specified parameter.

This tab contains the following commands for managing the parameters:

- **Add** add a new parameter. A new line will appear in this window as soon as you press it. In the "Parameter" field enter the name of the parameter, in "Value" - the necessary value to assign to this parameter;
- **Edit** modify a selected parameter. The same action can be performed by double clicking on the selected field;
- **Delete** delete a selected parameter.
- **Default** set default parameters.

Standard Parameters

All gateways have a standard set of supported parameters:

- **NewsCategory** news categories. As its value you can specify the title of the news category that is received from this data feed. Further this category name can be used to specify news to be received by separate groups.
- **Quotes Delay** delay of transmitted quotes in seconds. The maximum duration of quotes delay is 20 minutes (1200 seconds). The flow of delayed quotes is


neither thinned out, nor changed. A quote is passed to MetaTrader 5 History Server only after the expiration of delay period since the quote has arrived to Gateway API. If the temporary delay parameter is not defined, the quote delay is not used. Changes in depth of market and price statistics are delayed together with the quotes flow.

- **Quotes Tickstats Sample** the minimum frequency of sending price statistics in milliseconds. This parameter allows thinning out updates of price statistics reducing the traffic.
- **Quotes Ticks Sample** the minimum frequency of sending quotes in milliseconds. This parameter allows thinning out updates of quotes reducing the traffic. This parameter is recommended for use on demo servers only.
- **Quotes Books Sample** the minimum frequency of depth of market updates in milliseconds. This parameter allows thinning out updates of the depth of market reducing the traffic. This parameter is recommended for use on demo servers only.
- **Trading Calendar Holidays** trade systems/exchange can have their own schedule of working and non-working days that is different from the time and holidays settings of MetaTrader 5. This parameter allows redefining working and non-working for the gateway.
To add a non-working day, specify it in the following form: +DDMMM. Day is specified with two digits, month is specified as the first three letters of the month name. For example, +01JAN.
To add a working day, specify it in the following form: -DDMMM, for example, -07FEB. You can specify several days separated via semicolon, for example, +01JAN;-07FEB. If the working day you are adding does not fall within the platform working time or within trading/ quoting sessions of instruments, you should updated appropriate settings.

The parameters for thinning out of price data can be used together with Quotes Delay. Allowed values are from 100 to 3000 milliseconds.

If a parameter value is incorrect, it won't be used.

Timeouts




This tab describes the behavior of gateways in case data receipt is stopped.

- **Interval between reconnections** time period between the attempts to reconnect to the external server;
- **Number of reconnection attempts** a number of reconnection attempts is specified in this field. If a series of reconnection attempts doesn't result in establishing a connection, attempts will be stopped for a time period specified in the field below;
- **Interval between series of reconnections** if a series of specified number of reconnection attempts doesn't result in establishing a connection, attempts will be stopped for a time period specified in this field. After this time period another series of reconnections will be performed.

An example of working with timeouts is given in a [separate section](#).

Monitoring

MetaTrader 5 trading platform



From this section, you can access gateway monitoring settings. Use them for additional control and debugging.

- **Enable trading operations logging** enable printing of additional information about the gateway operation to the journal.
- **Enable detailed profiling** collect advanced metrics related to request processing. The platform monitors the performance of gateways similarly to cluster server monitoring. It logs various metrics, such as CPU load and memory consumption, among others. You can find them by the "Monitoring" keyword. If you enable detailed profiling, the platform will log additional parameters. Enable this mode only when debugging or testing, since it can slow down request processing. The feature is under development.
- **Collect transactions for [x] days** the feature is under development.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Gateways](#) / Status

Status

This page features general information about the gateway: description, version, settings and statistics. From the same page, you can quickly enable and disable the gateway.

To access this section, select a gateway in the tree or click on it in the product showcase.

ForexBroker-Demo - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Export Import Apply + Settings X Sort

MetaTrader 5 WL Gateway

Version: 5.00 build 3144 (10 Jan 2022)

The gateway is currently enabled [Disable](#)

Gateway to any MetaTrader 5 broker or liquidity provider. All financial instruments provided by the external system can become available to your traders: the gateway will forward the relevant trade requests and deliver quotes.

Preparation

Contact the desired broker and agree on integration terms and conditions. You will need a regular trading account with the required financial symbols to configure connection. All trading operations of your clients, forwarded through the gateway, will be performed on behalf of this account.

Gateway configuration

- **Trading server.** IP address and port of the external MetaTrader 5 server to which trade requests will be sent.
- **Trading login.** Trading account number on the external MetaTrader 5 server. All clients' trading operations forwarded through the gateway will be executed on this account.
- **Password.** Password for connection to the account on the external MetaTrader 5 server.



Module: MetaTrader 5 Gateway

API version: 5.00 build 3091

Signed by: MetaQuotes Ltd.

Certificate by: thawte SHA256 Code Signing CA

Configuration

Mode: Trade and Quotes

Gateway server: 127.0.0.1:16385

Trading server: 78.140.180.42:1950

Databases

Trades: 0

Traffic: 15909 / 0 KB

Copyright 2000-2022, MetaQuotes Ltd.

Status | Positions | Journal

For Help, press F1

1960 / 1 KB

Basic Data

Basic information about the gateway is shown at the top of the window:

- **Module** the name of the gateway executable file.
- **API Version** version and data of the Gateway API, which was used for creating the gateway.
- **Signed by** the company by which the gateway executable is signed.
- **Certificate issued by** the certification authority that issued the certificate to the above company.

Configuration

Basic gateway settings are shown in this block:

- **Mode** gateway operation mode (execution of trading operations and/or transmission of quotes).
- **Gateway server** the address at which the gateway accepts connections from the history and trade servers.
- **Trading server** the address of the external trading system server to which the gateway is connected.

To move to detailed setup, please click  next to the gateway name.

Databases

Gateway statistics is shown in this block:

- **Trades** the number of trading operations processed by the gateway.
- **Traffic** incoming and outgoing gateway traffic.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Gateways](#) / Journal of Gateways

Journal of Gateways

In order to view the journal of operation of gateways, select it in the tree-like list in the left part of the terminal and go to the "Journal" tab.

Time ▲	IP	Message
• 2022.11.18 13:35:20.381	Gateway	Symbols Path=
• 2022.11.18 13:35:20.381	Gateway	Symbols Update=No
• 2022.11.18 13:35:20.381	Gateway	Calculate Hedged Margin=No
• 2022.11.18 13:35:20.381	Gateway	Calculate Hedged Margin Rate=2.0
• 2022.11.18 13:35:20.381	Gateway	News Enable=No
• 2022.11.18 13:35:20.383	Quotes	books cleared
▲ 2022.11.18 13:36:21.000	QuotesBase	quotes stream stopped(no quotes during 61 sec)
• 2022.11.18 13:37:45.449	2a00:1178:1:60::2a	'10': login (Trade Server build 3506, cid: 896f289a1949b25b9d3e1d63a0ec6574)
• 2022.11.18 13:37:45.945	SymbolsBase	5061 symbols imported
• 2022.11.18 13:37:45.945	NetworkConfig	12 servers imported

Status | Positions | Journal

Working with the journal of gateways is the same as with the server journal. To request logs, specify a keyword, time period and click "Request".

Extended Logging

Extended logging mode can be enabled in "Monitoring" tab of the gateway settings. This allows receiving more detailed data on the gateway operation.

Measuring gateway operation speed

Result of measuring the speed of processing trade operations by the gateway is an important data displayed in the gateway journal in extended logging mode. Data on each request processing speed is shown in three journal lines:

```
order #100103556 - process time: 78.855 ms (request process: 12.088 ms, order execute: 66
order #100103556 - gateway API overhead: 0.254 ms (request lock: 0.037 ms, request confir
order #100103556 - trade server response: 10.410 ms, gateway response: 68.195 ms (reque
```

"Source" field of these messages contains "Monitor" indication. Order index, relative to which the measurement is performed, is shown after # mark. Let us examine each message separately.

```
order #100103556 - process time: 78.855 ms (request process: 12.088 ms, order execute: 66
```

The following information is displayed here:

- **process time** total time of trade operation processing at the gateway. The value is calculated as the time passed from the moment when a request was transferred to the gateway up to the moment when a trade server received a notification on placing the order in an external trading system. Processing time consists of two components shown in parentheses:
- **request process** time for making a decision on how the order will be processed (for example, before receiving IMTConfirm confirmation with MT_RET_REQUEST_PLACED response code meaning that the order will be processed in an external system).
- **order execute** time for placing an order in an external system (arrival of the appropriate IMTExecution trade execution).

order #100103556 - gateway API overhead: 0.254 ms (request lock: 0.037 ms, request confir

The following information is displayed here:

- **gateway API overhead** time spent for processing data in Gateway API. This parameter consists of three components shown in parentheses:
- **request lock** time spent by Gateway API for locking the request from the trade server's queue.
- **request confirm** time for the request confirmation processing in Gateway API (processing IMTConfirm confirmation received from the gateway).
- **execution process** time for processing the trade execution in Gateway API (processing IMTExecution trade execution received from the gateway).

order #100103556 - trade server response: 10.410 ms, gateway response: 68.195 ms (reques

The following information is displayed here:

- **trade server response** time between sending Gateway API request for locking the trade request and receiving Gateway API server notification on locking it.
- **gateway response** total time spent waiting for a response from an external system. This parameter consists of two components shown in parentheses:
- **request response** time spent waiting for a request confirmation (for example, waiting for a confirmation that the order has been placed in an external system).
- **execution response** time spent waiting for a trade request execution (for example, filling the order in an external trading system).

- All parameters are in milliseconds.
- More information about IMTConfirm confirmation object and IMTExecution trade execution object can be found in MetaTrader 5 Gateway API documentation.

Context Menu

The context menu of the journal of gateways contains the following commands:

-  **Request** request logs;

MetaTrader 5 trading platform

- **Copy** this command allows copying information from the journal to the clipboard;
- **Export** export the requested logs in a CSV or HTML file;
-  **Find** search through requested logs;
- **Auto arrange** If this option is enabled, the size of columns is selected automatically;
- **Grid** show/hide grid to separate fields;
- **Columns** show/hide columns of IP and Message in the Journal.

MetaTrader 5 Trading Platform / Platform Setup / Gateways / Positions

Positions

The tab is used to request the current state of positions from the trading accounts used by the gateway in an external system. Depending on the gateway tab, positions can be displayed via one or several accounts.

This tab may be absent if the ability to request external system positions is not supported by the gateway. Also, the tab is not displayed if the gateway configuration is disabled.

Symbol	Type	Volume	Price	Comment
GOLD	sell	1.00	146100	
AGRO	sell	2.00	31798	
PRIM	sell	20.00	16359	
DIOD	sell	47.00	19237	
ROST	buy	145.00	146620	
QIWI	buy	1.00	31798	
NKSH	buy	5.00	146620	

Positions total: 7 Positions time: 2012.09.11 12:20

Request

Status Positions Journal

Click "Request" to view positions.

The following information is displayed for each position:

- **Symbol** symbol, for which the position is opened;
- **Type** position type, buy or sell;
- **Volume** position volume in lots;
- **Price** opening price;
- **Comment** a comment to a position.

The total line below shows the total number of positions and the time the states of positions have been fixed. Depending on the gateway (and external trading system), states of positions can be submitted either in real time mode or only at the end of a trading session.

Context Menu

The context menu of this section allows performing the following commands:

MetaTrader 5 trading platform

-  **Request** execute positions request;
- **Copy** this command is used for copying data on positions to clipboard;
-  **Export** export requested positions as *.HTM, *.HTML files or *.CSV file;
-  **Find** open the search window;
- **Auto Arrange** if this option is enabled, the size of columns will be selected automatically;
- **Grid** show/hide grid to separate fields in the table with positions;
- **Comment** show/hide "Comment" column.

MetaTrader 5 Trading Platform / Platform Setup / Gateways / Setup of Routing

Setup of Routing

For a gateway to start processing trade requests, you should set up their routing in the corresponding section of the administrator terminal.

Common

The key options among those at the "Common" tab of the routing rule created for a gateway is the **"Perform action: Process to dealers"**.

Routing

Common Dealers

Using routing rules, one can adjust processing of trade requests by different conditions. Please specify conditions, for which the rule will be applied.

☒ Enable this rule

Name: Processing via gateway

Perform action: Process to dealers ☐ skip this rule if no dealers online

Where request is: Exchange Execution

Where order is: Buy, Sell, Buy Limit, Sell Limit, Buy Stop, Sell Stop

Where conditions are:

Type	Condition	Value
ab Group	Equal (=)	real*


Add Edit Delete

OK Cancel Help

Once the other parameters of the routing rule are set, you should proceed with the "Dealers" tab.

Dealers

At this tab you should select the gateway as a dealer that processes the requests:



MetaTrader 5 trading platform

In addition to the manager logins, the list of dealers contains the gateways (ID and name specified at the "Common" tab).

After the rule is set up, you should place it in a necessary position in the list, since the rules are executed from the first one to the last one.

MetaTrader 5 Trading Platform / Platform Setup / Gateways / Setup as Service

Gateway Installation as a Service

Gateways may run on any remote servers. They are not restricted to the server machine containing the history server.

In order to configure this gateway, you will need to copy the gateway .exe file and the GatewayAPI64.dll library (available in [history server installation directory]\Gateway) to the target server. Then launch the executable file and configure connection to the gateway in the remote mode.

In order not to run the gateway file every time when starting the server, you can install the gateway as a service. In that case, the gateway is launched automatically every time the operating system download starts.

Operation as a service is supported in all gateways developed by MetaQuotes. Support for this mode in third-party gateways is not guaranteed, while it depends on the gateway developers.

Service Setup

Copy the gateway .exe file and the GatewayAPI64.dll library (available in [history server installation directory]\Gateway) to the target server. Save both files to the same directory.

To install the gateway as a service, run its executable file with the /install key. The following parameters may be additionally specified:

- /name:<name> name of the service to be registered in the system.
- /display:<display_name> service full name.
- /desc:<description> service description.

All parameters are optional. If they are not specified, the default values are used.

Sample setup command:

```
DGCXGateway64.exe /install /name:dgcx
```

Service Start

After the setup is complete, launch the gateway service. Run the executable file with the /start key. The gateway launched in such a manner waits for the history server connection. If the history server interrupts connection (for example, in case of a restart), the gateway waits for the next connection. There is no need to restart it.

Sample launch command:

```
DGCXGateway64.exe /start
```

- If you need to migrate the gateway to another server, do not forget to additionally migrate the GatewayAPI64.dll library. The gateway will not work without this library.
- A gateway that runs on the remote server, as well as the GatewayAPI64.dll library, are not updated automatically when new versions of the platform are released. You will need to update these files manually.

Configuring the Service

To configure the gateway service, create a text .cfg settings file having the same name and located in the same directory as the gateway executable file. For example, if the gateway executable file is named DGCXGateway64.exe, then the settings file should be named DGCXGateway64.cfg. The file should contain the following parameters:


- name=<name> gateway name to be displayed in the log.
- address=<address>:<port> address and port where the gateway waits for the history server connection. The address cannot be specified in the format of history.server:[port] since the remote gateway does not know the platform environment.
- login=<login> login used by the history server when connecting to the gateway.
- password=<password> password used by the history server when connecting to the gateway.
- timezone time zone in minutes. The default time used for the remote gateway log is GMT+00:00. If the trade server is working in a different time zone, the time of server logs and gateway logs will be different. To avoid this, specify the time zone of the trade server in the gateway settings. The time zone should be specified in minutes. For example, the value of 60 corresponds to GMT +01:00, and -60 corresponds to GMT -01:00.
- timecorrect daylight saving time mode: 0 DST is not used, 1 enable DST change. It is recommended to set the mode used on the trade server.

Sample settings file:

```
name=DGCX Gateway
address=10.1.55.159:16100
login=100
password=apxjz3
```

Configuring the Gateway Connection on the Server Side

Create the gateway configuration via the Administrator terminal.



Specify the following parameters:

- Module Remote gateway,
- Gateway server address and port where the gateway waits for the history server connection (set in the [configuration file](#)).
- Gateway login gateway connection login set in the configuration file.
- Password gateway connection password set in the configuration file.

All other parameters are specified the same way as for a gateway running in normal mode.

Stop and Uninstall

To stop the gateway service, run its executable file with the /stop key. The current connection to the history server is interrupted and the service is stopped. Example:

```
DGCXGateway64.exe /stop
```

To uninstall the previously installed service, run the executable gateway file with the /uninstall key and [/name:<name>] parameter. The "name" parameter specifies the name of the uninstalled service. If the service was installed with the default name (without the "name" parameter), the /name parameter is not specified. Example:

```
DGCXGateway64.exe /uninstall /name:dgcx
```

If you uncheck "Enable" in a gateway configuration, the platform servers will be disconnected from the gateway service, while the service itself will not be stopped.

MetaTrader 5 Trading Platform / Platform Setup / Gateways / Operation on Weekend

Operation on Weekend

There may be cases when the gateway should work during the weekends, for example, on Saturday. In order to allow this, implement the necessary changes to the trading platform and the gateway settings.

Configure the platform working time

Allow the platform operation during a weekend in the Time section:

MetaQuotes - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Import Export Apply + Settings X Back Forward Sort

Administrator

- Servers
 - MetaTrader Server**
 - Network Cluster
 - Integrations
 - Automations
 - Security
 - Time**
 - Holidays
 - Groups (547)
 - Clients & Accounts
 - Orders & Deals
 - Payments
 - Gateways

Property	Value
Common settings	
01 Time zone	GMT+01:00
Daylight Saving Time correction	Yes
ab Time synchronization with	pool.ntp.org
Day settings	
Sunday	
Monday	00:00-24:00
Tuesday	00:00-24:00
Wednesday	00:00-24:00
Thursday	00:00-24:00
Friday	00:00-24:00
Saturday	00:00-24:00

For Help, press F1


3384 / 0 KB

Change the platform working time settings back at the end of the trading day.

Configure the gateway working time

Trading Calendar Holidays parameter used for re-defining working/non-working time is supported at all gateways on Gateway API level.

To add a non-working day, specify a value of the form +DDMMM. The date is specified as two digits, the month is specified as the first three letters of the month name in English. For example, +01JAN. To add a working day on Saturday or Sunday, specify a value of the type -DDMMM, for example, -07FEB. You can specify multiple working/non-working days, separated by semicolons, for example, + 01JAN;-07FEB.



Delete this parameter at the end of the trading day.
--

Some gateways may ignore the 'Trading Calendar Holidays' parameter. It depends on their implementation and trading venue specifics:

- The MetaTrader 4 and MetaTrader 5 gateways remain active on holidays and weekends regardless of the parameter. Their working hours are determined by the platform settings.
- Gateways to liquidity providers, such as Integral, Currenex and others are disabled on holidays and weekend regardless of the parameter. It is believed that liquidity from these providers is always unavailable on weekends and holidays.
- The MOEX Derivatives gateways receives an operation schedule directly from the exchange and it ignores the parameter.
- The MOEX Securities and MOEX FX gateways operate only on weekdays by default. The parameter can be used for these gateways.

For further details please read the relevant gateway documentation.

Configure trade symbol working time

Add trade and quotation sessions on a weekend for trade symbols. You can edit multiple symbols simultaneously. To do that, select them in the list while holding Ctrl or Ctrl+Shift.

MetaTrader 5 trading platform

MetaQuotes - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Import Export Apply + Settings X Left Right Sort

Symbol	Description	Sector	Digits	Type
CADCHF	Canadian Dollar vs Swiss Franc	currency	5	forex
EURAUD	Euro vs Australian Dollar	currency	5	forex
EURCAD	Euro vs Canadian Dollar	currency	5	forex

For Help, press F1

Symbol

Common Currency Quotes Trade Execution Margin Margin Rates Swaps Sessions

The setting up of trade and quotation sessions of the symbol by days. During the quotation session it is possible to view the price dynamics but trading is prohibited.

Day	Quotes	Trade
Sunday		
Monday	00:00-24:00	00:00-24:00
Tuesday	00:00-24:00	00:00-24:00
Wednesday	00:00-24:00	00:00-24:00
Thursday	00:00-24:00	00:00-24:00
Friday	00:00-24:00	00:00-24:00
Saturday	00:00-24:00	00:00-24:00

Edit

☐ Use time limits From: 1970.01.01 00:00 To: 1970.01.01 00:00

OK Cancel Help

Change the settings back at the end of the trading day.

MetaTrader 5 Trading Platform / Platform Setup / Gateways / Symbol and Price Translation

Symbol and Price Translation

Gateways are able to import necessary sets of trading symbols, manage their settings, update them if necessary and provide quotes. Gateway settings allow you to easily change data passed from the external system:


- Rename trading symbols
- Convert quotes
- Copy price data to different symbols

To do that, use settings on the Translations tab.

To let a gateway manage settings of trading symbols on the MetaTrader 5 side, enable the "Allow importing symbols settings" option.


Renaming trading symbols

Data on any symbol can be passed from an external system to the MetaTrader 5 platform under any name. For example, if the symbol name in an external system is EURUSD_ABC, and it is called EURUSD in the MetaTrader 5, enter EURUSD in the "Symbol" field and EURUSD_ABC in the "Source" field.




If another source of quotes is already specified in symbol settings (in its Source field), this symbol cannot be specified as the receiver symbol. Also symbols with the disabled Allow real-time quotes from data feeds option cannot be specified as receivers. Conversion settings containing such symbols will be ignored by the platform.

Use the * mask for renaming multiple symbols. For example, in order to add the .delayed suffix to all gateway symbols, specify:



Only simple masks with a single * symbol are supported. Settings with more complicated masks (for example, having two * or ! negation symbol) are ignored.

In order to duplicate data to different symbols on the MetaTrader 5 side, create several entries in the Translations section. In the example below, the entire available set of gateway symbols is passed to the platform in two instances: with the .1 and .2 suffixes.



A gateway behavior changes depending on the translations configuration phase:


- The gateway has not yet imported symbols to the platform, while the translation parameters have already been set (for example, renaming) when enabled, the gateway imports only renamed symbols.
- The gateway has not yet imported symbols to the platform and the translation parameters have not been set when enabled, the gateway imports original symbols from the external system.
- The gateway has already imported original symbols, while the translation parameters have been set during operation after saving the settings, the gateway imports a new set of symbols, broadcasts data and manages the settings for the both symbol sets.

Price translation

A gateway broadcasts a flow of quotes from an external trading system to the MetaTrader 5 platform and is able to change it on the fly. Clients receive prices according to the translation settings. However, while processing trading operations on the gateway and passing them back to the external system, initial (not transformed) prices are used.

If trading tool names in the platform are not different from the ones in the external system, simply specify a symbol name in the platform and translation value for Bid and Ask prices.

MetaTrader 5 trading platform




The above screenshot shows price conversion: at every tick, the Bid price will be reduced by 3 points, and the Ask price will be increased by 2 points. Below is a schematic example of the conversion:

External system	>>>	ask price	EURGBP 0.83004	>>>	MetaTrader 5 server
MetaTrader 5 server	>>>	ask price	EURGBP 0.83006	>>>	Client terminal
Client terminal	>>>	buy limit	EURGBP 0.83006	>>>	MetaTrader 5 server
MetaTrader 5 server	>>>	buy limit	EURGBP 0.83004	>>>	External system
External system	>>>	buy limit execution	EURGBP 0.83004	>>>	MetaTrader 5 server
MetaTrader 5 server	>>>	buy limit execution	EURGBP 0.83006	>>>	Client terminal

A broker gains 2 pips of profit in this example. The price is sent to the client terminal only after the correction, so the clients work only with the corrected prices. If no correction is set for a symbol, the client will work with the original prices submitted by an external system.

Using the previously described possibilities of symbols mass renaming and duplication, you are able to customize different flows of quotes. For example, original and converted ones:

MetaTrader 5 trading platform




The .wide suffix stands for converted quotes, while the .original stands for non-converted ones.

Features of trade operations

If only one translation parameter or no parameters at all are set for a gateway, trades are conducted without any peculiarities since the platform is able to match symbols on its side with the ones at the external trading system.

If more than one translation parameter is set for the gateway, the platform attempts to match the symbols correctly. For example, the two translation parameters are set for the gateway:

MetaTrader 5 trading platform



If an order is placed on the platform side, a symbol in the external system response is defined by the original order ticket. For example, a trader places an order #145269 Buy 1.00 EURUSD.2. It is sent to the external system as #145269 Buy 1.00 EURUSD. When receiving a response, the platform converts the symbol back to EURUSD.2 by the original order ticket.

However, there are some trading operations/events that are not preceded by placing an order on the trading platform side. For example, charging a variation margin in an external system. In that case, the platform cannot clearly define which of the two symbols the event is related to: EURUSD.1 or EURUSD.2.

In this situation, the platform attempts to select the correct symbol by its availability to certain accounts the event is related to. For example, if only EURUSD.2 is available for an account, the platform performs an operation for it. Availability of symbols for clients is defined on the Symbols tab of the group settings.

If both symbols are available for the account, the operation is performed for the first one in the translation list. It is EURUSD.1 in our example.

Thus, if there are multiple translation settings, the following rule is used: trading operations are performed for the first symbol available for a client group. All subsequent translation settings are used only to pass price data.

The table below contains trading operations and events preceded by placing an order on MetaTrader 5 side, which means that symbols can be accurately matched for them regardless of the number of translation settings. For other operations, the platform attempts to define the necessary symbol by its availability for a client group.

A symbol is accurately matched by an original order	A symbol is defined by its availability for a client
Placing an order of any type Executing an order Rejecting an order Modifying an order Canceling an order Changing an order ID in an external system Closing a position by an opposite one	Charging a variation margin Re-calculating a profit/loss by trades performed during the current session Removing intraday orders at the end of a trading session Executing a trade in an external system without an order Performing a repo trade A futures or option contract delivery date coming into effect Relocating a position to a new symbol with the same underlying asset Removing all active pending orders Charging rollovers for open positions

MetaTrader 5 Trading Platform / Platform Setup / Data Feeds


Data Feeds

Data feeds deliver quotes and news from various providers. Use the data feeds to provide the following essential trading tools to your clients:

- Real-time financial news to assist in making trading decisions
- Price data from different exchanges and ECNs for analysis and for the development of trading strategies

The platform offers a variety of built-in turnkey data feeds for integration with major data providers: Dow Jones, IBTimes, DTN and others. You can test them right away. Additional third-party solutions are featured in the App Store. Using the Gateway API, you can create your own data feeds for integration with any data providers.

In the Data Feeds section, available solutions can be viewed in two modes: product showcase and configuration list. You can switch between them using buttons  and .



Name	Source	Server	Symbols	Last active	Status
MetaTrader 5 Feeder	N + Q	access....	*	Online	2430048 / 0
IQ Feeder	N + Q		*	2022.02.14 17:13:01	Offline
UniFeeder	N + Q	localhos...	*	2022.02.14 10:44:40	Offline

The product showcase provides basic information: data feed name, connection status and the amount of transmitted Market Depth and tick data. The Selected tab displays all data feeds for which you have configurations. The Available tab features all data feed modules available on the History server. You can configure them at any time.

The list mode enables the management of existing data feed configurations. It provides quick access to the main parameters:

- **Name** the name of the data feed.
- **Source** data type provided by the data feed, news (N) or quotes/Market Depth (Q).
- **Server** the address and port of the server from which the data feed receives data.
- **Symbols** symbols available to the data feed.
- **Last active** data and time of the last successful connection of the data feed to the data provider.
- **State** total transmitted ticks and Market Depth changes/the number of transmitted news items.

Using the context menu, you can adjust the set of displayed data.

How Data Feeds Work

Data feeds are executable files (*.exe) that run as separate processes. They are stored on the History server, in the "Datafeed" directory. Data feeds interact with the platform through the MT5APIGateway.dll library.

Data feeds connect to an external data source and transmit information to the History server. From this server, data is forwarded to Access servers and terminals. Several sources can be used. If data delivery from one source fails, you can instantly switch to another one.

Switching between Data Feeds

The position of a data feed in the list defines its priority in the delivery of data: the higher the position is, the higher the priority of the feeder is. However, a server is permanently receiving information from all data feeds at once. Such a solution allows to immediately switch to another feed in case of problems. For example, several data feeds deliver quotes of the same symbol from different financial companies - the priority defines what data feed should be used. If the required data are not received from the selected feed for a certain period of time, the server automatically switches to the next data feed that provides information on the same symbol. However, as soon as data from the feed with higher priority are received, the server will switch back to it.

- The idle timeout of a feed is set up on the history server settings in "Datafeeds timeout".
- For symbols with the depth of market enabled the current data source (a gateway of a data feed) is determined by the first quote that comes after

starting the history server.

- Switching of data feeds for a symbol can be tracked in the "Ticks" section.
- Flow of quotes for a symbol coming from a gateway has a higher priority than a flow from a data feed. Switching to quotes from a data feed occurs in case the data flow from the gateway has stopped.
- Switching of data feeds is performed independently for each symbol.

To move data feeds use "↑ Move Up" and "↓ Move Down" located in the Edit menu, on the Standard toolbar and in the context menu.

The process of activation of a quotes flow from a certain data feed is reflected in the history server journal. To find such records, use the keyword "activation".

Configuration of Data Feeds

In order to add or modify a data feed, press "+ Add" or "⚙ Edit", respectively. In order to delete a data feed, press "✕ Delete". These commands are also available in the Edit menu, on the Standard toolbar and in the context menu.

To open a data feed settings or view its status, select it in the tree-like list in the "Data Feeds" section on the left.

- The standard MetaTrader 5 delivery package includes several ready-to-use data feeds for receiving information from the most popular providers. These data feeds are described in separate sections.
- To view the journal of operation of data feeds, select in in the tree-like list in the "Data Feeds" section on the left and go to the "Journal" tab.
- Additional general information about working with configuration records is given in the "Working with Instructions" section.

Possible delay in the delivery of Market Depth prices after switching gateways

To consume less resources, the history servers does not store the best prices and Market Depth values for each symbol and each available data source. For the same purpose, the Market Depth is passed from the data feed to the server in the form of changes relative to the previous state. Additionally, the full Market Dept snapshot is sent to the server no more than once every 30 seconds.

Therefore, if the main price feed is stopped and the server switches to the reserve one, the server has to wait for the first Market Depth snapshot from the data feed. During this time (up to 30 seconds), the Market Depth data is not updated.

Context Menu

The context menu of the "Data Feed" section contains the following commands:

- **+ Add** add a new data feed;
- **⚙ Edit** edit a selected data feed;


-  **Delete** delete a selected data feed;
-  **Move Up** move a selected data feed up relative to others;
-  **Move Down** move a selected data feed down relative to others;
-  **Sort Alphabetically** sort configurations alphabetically. Please note that sorting is done on the server, not in the local terminal.
-  **Enable** enable the selected configuration.
-  **Disable** disable the selected configuration.
- **Automation triggers** create an automation task for the selected event or edit an existing one. The menu displays only the triggers and tasks associated with the current section.
- **Automation actions** add an automation action to an existing task or create a new task based on the action. The menu displays only the actions associated with the current section.
-  **Export to File** export the settings of data feeds to a file.
-  **Import from File** import the settings of data feeds to a file.
-  **Journal** request logs according to the selected configuration. This will open the trade server logs section, with the name of the selected configuration automatically specified in the query field. You will only need to press the request button.
-  **Find** open the Search window;
- **Auto Arrange** if this option is enabled the size of columns is selected automatically;
- **Grid** this option shows/hides field separators in the table with the data feeds.

MetaTrader 5 Trading Platform / Platform Setup / Data Feeds /
Configuration of Data Feeds

Configuration of Data Feeds

In order to add or modify a data feed, in the corresponding section press "+ Add" or "⚙ Edit", respectively. In order to delete a data feed, press "✗ Delete". These commands are also available in the Edit menu, on the Standard toolbar and in the context menu.

Common



The screenshot shows the 'Data Feed' dialog box with the 'Common' tab selected. The dialog contains the following elements:

- Title Bar:** 'Data Feed' with standard window controls (minimize, maximize, close).
- Tab Bar:** 'Common', 'Symbols', 'Translations', 'Parameters', 'Timeouts'.
- Icon:** A blue circular icon with a white 'M' on the left.
- Description:** 'The datafeed translates quotes and news from remote MetaTrader 5 server'.
- Enable:** A checked checkbox labeled 'Enable'.
- Name:** A text field containing 'MetaTrader 5 Feeder'.
- Module:** A dropdown menu showing 'MetaTrader 5 Feeder'.
- Quotes and News:** A dropdown menu showing 'Quotes and News'.
- Feed server:** A text field containing 'access.metatrader5.com:443'.
- Feed login:** A text field containing '1000'.
- Password:** A text field with masked characters (dots).
- Link:** A blue hyperlink labeled 'Show additional network settings'.
- Buttons:** 'OK', 'Cancel', and 'Help' at the bottom right.

The main information about the data feed server is specified on this tab:

- **Enable** enable/disable the data feed. Working data feeds are automatically turned off at non-working hours of the server. Once the trade server starts working, the data feeds are turned on. For the data feeds running as a service via the "Remote gateway" module, unchecking "Enable" will lead to disconnection of platform servers from the data feed service, while the service itself will not be stopped.
- **Name** name of the data feed. Use of special characters (?, *, <, > etc.) is not allowed, as this may cause issues while working with the data feed log files.
- **Module** name of the data feed module file, as well the type of translated data (news, quotes, market books).
- **Feed server** address of the data source server.
- **Feed login** login to access the data feed server.
- **Password** password to access the data feed server.

When you change any of the parameters, the data feed automatically restarts to apply the changes.

Advanced Network Settings

Additional network settings include history/trade server to data feed connection parameters. These settings are designed to provide the security of operation between the server and the data feed. In most cases, the settings are hidden and do not require configuration (the history server sets the required address and connection parameters).

These parameters need to be specified in two cases: when working in the remote datafeed mode, and if the address/port selected for the data feed is busy. In the second case, the following message is written to the log: datafeed address 'Data feed name' already used, please setup another address for datafeed.

- **Gateway sever** address at which the data feed will receive connections from the history server. The system automatically determines available addresses of network interfaces of the history server and displays them in this field.
- **Gateway login** login that will be used for authorization of the history server on the data feed. Only a positive number can be specified as a login.
- **Password** password that will be used for authorization of the history and trade server on the data feed. The password must fulfill the security requirements (at least 6 characters long with two of three types of symbols: upper case letters, lower case letters and digits).

You can also specify the address 127.0.0.1 or localhost for the gateway server. This is the so-called Loopback or a virtual network interface, which is not linked to any hardware. Such addresses are used by default when the data feed, the history server and trade servers operate on the same computer. For such addresses, the platform performs additional checks to ensure proper operation:

1. The platform receives lists of addresses listened by the history and trade servers


2. If at least one trade server does not have the same address as the history server, it is considered that at least one platform component is installed on another physical computer.
3. In this case, the data feed will not be run on localhost (127.0.0.1), but on a set of listening addresses of the history server. The port specified in the "Gateway server" parameter is used for the port. For example, if the address 127.0.0.1:16387 is specified for a data feed, and the server operates on 192.168.0.1:442, the data feed will run on 192.168.0.1:16387.
4. When connecting to the data feed, the trade server also determines which address to connect to (as in points 1 and 2): Loopback or a set of addresses. The port specified in the "Gateway server" parameter is used for the port. The following addresses are used for the set of addresses (in the order of priority):
 - Public addresses of the history server
 - Local addresses listened by the history server, which coincide with its public points (located on the same subnet).

You can also specify the address as history.server:port. For example, history.server:12345. Peculiarities of using such address:

- ♦ The data feed will accept connections on the specified port of all the IP addresses the history server works on (they are specified in the list of listen addresses on the "Network" tab of the history sever).
- ♦ The data feed will accept connections from the trade servers on the public access points of the history server (they are specified in the list of public addresses on the "Network" tab of the history server).
- ♦ If the list of list addresses of the history server includes 0.0.0.0, then the data feed will use this address for operation. 0.0.0.0 means listening on all addresses.
- ♦ Specifying the address in this way allows automatic switching the history server with set up local data feeds to a backup server without need to set up the addresses of the data feeds manually.
- ♦ An address in this format cannot be used for remote data feeds since they do not know the platform environment.

If you install the data feed as a service on the Loopback address and then move any of the platform components to a different computer, the data feed will become unavailable for that component.

Symbols



This tab is intended for specifying a list of symbols for translating quotes. For example, if you specify EURUSD, quotes for this symbol only will be received from this data feed.

Click "Add" and select the desired symbol or group of symbols. They can also be specified manually: one or multiple symbols separated by commas.

You can additionally use mask "*" and the negation sign "!". For example, Cboe FX*,!Cboe FX\EURUSD all symbols from the Cboe FX group except EURUSD. The exception does not work for a single "*" mask. It always allows all symbols:

- Forex*,!Forex\EURUSD all symbols in the Forex subgroup, except EURUSD.
- *,!Forex\EURUSD all symbols. The EURUSD symbol will not be excluded.

For details, please visit the [Specification of Symbols and Groups](#) section.

If the symbol row in the table is highlighted in red, then this symbol no longer exists. It may have been moved or deleted. Open the entry and edit the symbol path.

This tab is not displayed for data feeds that transmit news only.

Allow importing symbol settings

Using this option, you can enable/disable the import of settings of the symbols quoted and traded through the data feed. The option will only work if the relevant functionality is supported by the gateway.

MetaTrader 5 trading platform

Please pay attention to the following features when importing symbol settings via the gateway:


- If the symbol does not exist in the trading platform, it will be created in the Preliminary group.
- All newly added symbols are imported with the trading option disabled. The platform administrator must check all the settings and manually enable trading.
- If the symbol already exists in the platform, only the symbol settings are updated. Since trading is not executed through data feed, no update can be received for symbol trading parameters, including trading modes, execution and expiration, available order types, volume and margin settings, and options parameters.

Automatic import of symbol settings greatly simplifies the work of the platform administrator. Instead of the manual addition of all settings, you can simply move symbols from the Preliminary group the desired group and allow trading.

When the data feed changes symbol settings, the following log is added to the main trade server journal: "symbol config updated". The name of the data feed is indicated as the IP address of the source in such records (the "IP" field).

When the "Allow importing symbol settings" option is enabled, the data feed can add and edit any symbols in the Preliminary* group, even if they are not indicated in the list above.

Translations



MetaTrader 5 trading platform

Information that is received from data feeds can be transformed:

- **Symbol** name of symbol at the MetaTrader 5 server;
- **Source** name of symbol in the external source (initial name of symbols). This parameter is used for adjusting the names of symbols in external data sources with the names of symbols in the platform;
- **Bid** in this field you can specify a number of points to change the Bid price on.
- **Ask** in this field you can specify a number of points to change the Ask price on.

If a parameter is not specified, default values transmitted by the data feed will be used for it.

If more than one translation settings match the same symbol on the platform side, only the one located higher in the list will be applied. For example, the following settings are available:


- EURUSD.GW | EURUSD | Bid -1 | Ask +1
- *.GW | * | Bid -2 | Ask +2

In this case, EURUSD prices will be changed by -1/+1, and the prices of all other symbols will be changed by -2/+2.

- This tab is not displayed for data feeds that transmit news only.
- When translating prices, make sure the prices are correct. Usually a negative (or zero) value is indicated for the Bid price, and a positive (or zero) value is indicated for Ask. Otherwise, you may get a negative spread.
- Translations also affect the depth of market.
- Find out more in the ["Symbol and Price Translation"](#) section.

Parameters

This tab allows to specify additional parameters of a data feed that are not implemented at the "Server" tab. Presence of this parameters is stipulated by a necessity of passing additional settings to a data feed for its correct operation. For example, if a data feed receives incoming connections, allowed IP address can be specified in those parameters.



The parameters are described in these fields:

- **Parameter** name of a parameter;
- **Value** value of a specified parameter.

- If additional parameters are implemented then while adding a data feed they are automatically specified with default values.
- The description of possible parameters is given separately for each data feed that is included in the standard delivery of the platform.

This tab contains the following commands for managing the parameters:

- **Add** add a new parameter. A new line will appear in this window as soon as you press it. In the "Parameter" field enter the name of the parameter, in "Value" - the necessary value to assign to this parameter;
- **Edit** modify a selected parameter. The same action can be performed by double clicking on the selected field;
- **Delete** delete a selected parameter.
- **Default** set default parameters.

Standard Parameters

All data feeds have a standard set of supported parameters:

- **NewsCategory** the name of the category of news received from this data feed. Further this category name can be used to specify news to be received by

separate groups.

- **Quotes Delay** delay of transmitted quotes in seconds. The maximum duration of quotes delay is 20 minutes (1200 seconds). The flow of delayed quotes is neither thinned out, nor changed. A quote is passed to MetaTrader 5 History Server only after the expiration of delay period since the quote has arrived to Gateway API. If the temporary delay parameter is not defined, the quote delay is not used. Changes in depth of market and price statistics are delayed together with the quotes flow. The parameter is not supported for MetaTrader 4 Feeder and MetaTrader 5 Feeder.
- **Quotes Tickstats Sample** the minimum frequency of sending price statistics in milliseconds. This parameter allows thinning out updates of price statistics reducing the traffic.
- **Quotes Ticks Sample** the minimum frequency of sending quotes in milliseconds. This parameter allows thinning out updates of quotes reducing the traffic. It is recommended for use on demo servers only.
- **Quotes Books Sample** the minimum frequency of depth of market updates in milliseconds. This parameter allows thinning out updates of the depth of market reducing the traffic. It is recommended for use on demo servers only.


The parameters for thinning out of price data can be used together with Quotes Delay. Allowed values are from 100 to 3000 milliseconds.

If a parameter value is incorrect, it won't be used.

News Category and Language

- Usually, news categories are provided by data feeds. News providers supplement news with the information about categories to which the news belong. The same applies to the news language.
- A news category can be additionally specified in the News Category parameter of the data feed. This is a standard parameter supported by all data feeds. The parameter is applied as follows:
 - If a data source does not provide news categories, news items will be added to the category specified in this parameter (the category will be specified in the news).
 - If the data source provides a category, then the data feed will add the "News Category" parameter value before the original category name. The resulting category will look like "[value from News Category] \ [category from data source]". The "\" characters in a category name are interpreted as subcategory separators. Therefore, it means that all news items are added to the category specified in the parameter, within which original categories from the data source will be used.

Timeouts



This tab describes the behavior of data feeds in case data receipt is stopped.

- **Interval between reconnections** time period between the attempts to reconnect to the data feed;
- **Number of reconnection attempts** a number of reconnection attempts is specified in this field. If a series of reconnection attempts doesn't result in establishing a connection, attempts will be stopped for a time period specified in the field below;
- **Interval between series of reconnections** if a series of specified number of reconnection attempts doesn't result in establishing a connection, attempts will be stopped for a time period specified in this field. After this time period another series of reconnections will be performed.

An example of working with timeouts of data feeds is given in a [separate section](#).

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Data Feeds](#) / Status

Status

This page features general information about the data feed: description, version, settings and statistics. From the same page, you can quickly enable and disable the data feed.

To access this section, select a data feed in the tree or click on it in the product showcase.

Broker-Demo - MetaTrader 5 Administrator

File Edit View Services Help

Disconnect Refresh Restart Server Export Import Apply Sort

MetaTrader 5 Feeder

Version: 5.00 build 3144 (10 Jan 2022)

The feeder is currently enabled [Disable](#)

Through this data feed, you can receive news and price data from any MetaTrader 5 broker. Supports the delivery of order books.

Pre-setup

Contact the desired broker and agree on data delivery terms and conditions. To connect to the source broker, you will need a regular trading account (demo or real), with access to required news and trading instruments. The data feed will create a client connection and will deliver data through this connection.

Data feed setup

- **Feed server.** Specify the MetaTrader 5 server address and port, separated by a colon.
- **Feed login.** Account number for connecting to the server.
- **Password.** Account password. If the extended authentication method is enabled on the external server, use the investor password instead of the main one. Otherwise, the connection will be impossible.
- **Quotes Time Original.** If set to *Yes*, the gateway will automatically specify the tick time, taking into account the time zone of the recipient trading server. If set to *No* or the parameter is absent, the tick time will be set by the history server according to its own



Module: MetaTrader 5 Feeder

API version: 5.00 build 3091

Signed by: MetaQuotes Ltd.

Certificate by: thawte SHA256 Code Signing CA

Configuration

Source: Quotes and News

Gateway server: 127.0.0.1:16384

Feed server: access.metatrader5.com:443

Databases

Price ticks: 119845

Price books: 2286240

News: 0

Traffic: 122062 / 7 KB

Copyright 2000-2022, MetaQuotes Ltd.

Status [Journal](#)

For Help, press F1

1169 / 0 KB

Basic Data

Basic information about the data feed is shown at the top of the window:

- **Module** the name of the data feed executable file.
- **API Version** version and data of the Gateway API, which was used for creating the data feed.
- **Signed by** the company by which the data feed executable is signed.
- **Certificate issued by** the certification authority that issued the certificate to the above company.

Configuration

The main data feed settings are shown in this block:

- **Source** data transmitted by the data feed (quotes and/or news).
- **Gateway server** the address at which the data feed accepts connections from the history server.
- **Source server** the address of the data source server.

To move to [detailed setup](#), please click  next to the data feed name.

Databases


Gateway statistics is shown in this block:

- **Price ticks** the number of price changes received from the data source.
- **Price books** the number of Market Depth changes received from the data feed.
- **News** the number of news items received from the data feed.
- **Traffic** incoming and outgoing data feed traffic.

MetaTrader 5 Trading Platform / Platform Setup / Data Feeds / Journal of Data Feeds

Journal of Data Feeds

In order to view the journal of operation of data feeds, select it in the tree-like list in the left part of the terminal and go to the "Journal" tab.



Working with the journal of data feeds is the same as with the server journal. To request logs, specify a keyword, time period and click "Request".

Context Menu

The context menu of the journal of data feeds contains the following commands:

- **Request** request logs;
- **Copy** this command allows copying information from the journal to the clipboard;
- **Export** export the requested logs in a CSV or HTML file;
- **Find** search through requested logs;
- **Auto arrange** If this option is enabled, the size of columns is selected automatically;
- **Grid** show/hide grid to separate fields;
- **Columns** show/hide columns of IP and Message in the Journal.

MetaTrader 5 Trading Platform / Platform Setup / Data Feeds / Restarting Data Feeds

Restarting Data Feeds

Restart of data feeds is required when technical problems with quotes or news receipt occur. This procedure can be performed using command " Restart Datafeeds" in the Services menu. All working data feeds will be restarted.

Data feeds are restarted automatically in the following cases:

- If any of the data feed configurations has changed, it is restarted;
- If the position of the data feed in the list has changed (and therefore its priority has changed), all data feeds are restarted.

MetaTrader 5 Trading Platform / Platform Setup / Data Feeds / Setup as Service

Data Feed Installation as a Service

Data feeds can be running on any remote server different from the server where the history server is installed.

In order to configure this data feed, you will need to copy the data feed .exe file and the GatewayAPI64.dll library (available in [history server installation directory]\Datafeed) to the target server. Then launch the executable file and configure connection to the data feed in the remote mode.

To avoid the necessity to start the data feed file manually every time when starting the server, you should install the data feed as a service. In that case, the data feed is launched automatically every time the operating system download starts.

Operation as a service is supported in all data feeds developed by MetaQuotes, except for those that are built directly into the platform (do not have a separate executable file), such as MetaTrader 4 Feeder, MetaTrader 5 Feeder and MetaTrader 5 UniFeeder. Support for this mode in third-party data feeds is not guaranteed, while it depends on the gateway developers.

Service Setup

Copy the data feed .exe file and the GatewayAPI64.dll library (available in [history server installation directory]\Datafeed) to the target server. Save both files to the same directory.

To install the data feed in the service mode, run the data feed .exe file with the /install key. The following parameters may be additionally specified:

- /name:<name> name of the service to be registered in the system.
- /display:<display_name> service full name.
- /desc:<description> service description.

All parameters are optional. If they are not specified, default values will be used.

Sample setup command:

```
feeder64.exe /install /name:mt5feeder
```

Service Start

After the installation, launch the data feed service by launching its .exe file with the /start switch. The data feed launched in such a manner waits for the history server connection. If the history server interrupts connection (for example, in case of a restart), the data feed waits for the next connection. There is no need to restart it.

Sample launch command:

```
feeder64.exe /start
```

- If you need to migrate the data feed to another server, do not forget to additionally migrate the GatewayAPI64.dll library. The data feed will not work without this library.
- The data feed that runs on the remote server, as well as the GatewayAPI64.dll library, are not updated automatically when new versions of the platform are released. You will need to update these files manually.

Configuring the Service

To configure the data feed service, create a text .cfg settings file having the same name and located in the same directory as the data feed .exe file. For example, if the executable file of the data feed is MetaTrader5Feeder64.exe, the configuration file should be named MetaTrader5Feeder64.cfg. The file should contain the following parameters:


- name=<name> the name of the data feed. This name will be shown in the Journal.
- address=<address>:<port> address and port where the data feed waits for the history server connection. The address cannot be specified in the format of history.server:[port] since the remote data feed does not know the platform environment.
- login=<login> login used by the history server when connecting to the data feed.
- password=<password> password used by the history server when connecting to the data feed.
- timezone time zone in minutes. The default time used for the remote data feed log is GMT+00:00. If the trade server is working in a different time zone, the time of server logs and data feed logs will be different. To avoid this, specify the time zone of the trade server in the data feed settings. The time zone should be specified in minutes. For example, the value of 60 corresponds to GMT +01:00, and -60 corresponds to GMT -01:00.
- timecorrect daylight saving time mode: 0 DST is not used, 1 enable DST change. It is recommended to set the mode used on the trade server.

Sample settings file:

```
name=My Feeder
address=10.1.55.159:16100
login=100
password=apxjjz3
```

Configuring the Data Feed Connection on the Server Side

Create a configuration of the data feed via the administrator terminal.



Specify the following parameters:

- Module Remote datafeed,
- Gateway server address and port where the data feed waits for the history server connection (set in the [configuration file](#)).
- Gateway login data feed connection login set in the configuration file.
- Password data feed connection password set in the configuration file.

All other parameters are specified the same way as for a data feed running in normal mode.

Stop and Uninstall

To stop a data feed service, run its executable file with the /stop key. The current connection to the history server is interrupted and the service is stopped. An example:

```
feeder64.exe /stop
```

To uninstall the previously installed service, run the data feed .exe file with the /uninstall key and [/name:<name>] parameter. The "name" parameter specifies the name of the service that you want to uninstall. If the service was installed with the default name (without the "name" parameter), the /name parameter is not specified. An example:

```
feeder64.exe /uninstall /name:dgcx
```


If you uncheck "Enable" in a data feed configuration, the platform servers will be disconnected from the data feed service, while the service itself will not be stopped.

MetaTrader 5 Trading Platform / Platform Setup / Plugins

Plugins

Plugins are special modules for extending the set of functions of a trading platform as DLL files. Plugins can also be used to change algorithms of some operations performed by servers. For example, they can be used to change calculation of margin or swaps. MetaTrader 5 Server API is used to create plugins.

Each plugin is set up for a certain server. To view plugins configured for a server, select it in the tree located in the left part of the terminal.



The screenshot shows the 'MetaQuotes - MetaTrader 5 Administrator' window. On the left, a tree view is expanded to 'Plugins', showing sub-items: 'Trade Main', 'Trade Server Seco', and 'History'. The main pane displays a table of installed plugins.

Name	Module	Vendor
Server API Test Plugin	ServerAPITest64.dll, v.1.00	Copyright 2001-2017, M
Trade Transaction Rep...	Trades.Transaction.Reports64.dll, v.1.00	Copyright 2000-2023, M
NFA Reports	NFA.Reports64.dll, v.1.00	Copyright 2000-2023, M
EMIR Reports	EMIR.Reports64.dll, v.1.00	Copyright 2000-2023, M
Auto plugin	StopOutReporter64.dll, v.1.00	Copyright 2000-2019, M
StopOut Reporter Plugin	StopOutReporter64.dll, v.1.00	Copyright 2000-2019, M
API Extension	APIExtension64.dll, v.1.00	Copyright 2000-2019, M
API Extension (Used fo...	APIExtension64.dll, v.1.00	Copyright 2000-2019, M
Single Session Plugin	SingleSessionPlugin64.dll, v.1.00	Copyright 2000-2019, M

At the bottom left, it says 'For Help, press F1'. At the bottom right, there is a status bar showing '2230 / 0 KB'.

Installing plugins

Plugins are configured separately for each server. Copy the plugin DLL file to the /plugins directory of the corresponding trade or history server.

When the server starts, it loads all the plugin DLLs in the /plugins directory and all of its subdirectories. The libraries are loaded even if the platform does not have the corresponding plugin configurations. In this regard, we strongly recommend against storing files you plan to use in these directories.

Adding and Editing Plugins

For the plugin to start working, create a configuration for it. Select  Add on the toolbar or in the context menu. To edit the settings of an added plugin, click  Edit.

This section support group editing of plugin configurations. To do it, select several plugins by holding Ctrl or Ctrl+Shift, and then start editing them. Using the group editing you can enable and disable plugins in bulk. Additional general information about working with configuration records is given in the "Working with Instructions" section.

Arrange plugins in the required order, as this affects the hook processing order. The higher the plugin is in the list, the earlier it receives the hook.

Common

MetaTrader 5 trading platform

Plugin: NFA Reports

Common Information

 The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.

☒ Enable ☐ Configurable by managers

☐ Enable plugin profiling

Name: NFA Reports

Module: NFA.Reports64.dll Trade Main, 1

Parameters:

Parameter	Value
 Symbols	*
 Groups	*
 Forex Dealer Member ID	BRK
 Server ID	Main
 Base Directory	NFA.Reports
 SFTP Address	
 SFTP Port	1
 SFTP Login	

Add Edit Delete

OK Cancel Help

Set plugin settings:

- **Enable** enable/disable the plugin. The plugin starts operating immediately after the option is enabled and the configuration is saved. To get started, server restart is not required. If you disable the option, the server will completely unload the plugin from memory. This enables update of plug-in DLL files without the need to reload the platform.
- **Configurable by managers** if this option is enabled, it will be possible to change the settings of the plugin via the manager terminal. To be able to change the plugin settings, a manager account must have the "Setup of plugins" permission enabled.
- **Enable plugin profiling** after enabling the profiling, the server will start collecting the statistics on the plugin, what allows estimating its performance and detecting possible problems of its operation. It is not recommended to keep this option always enabled, as profiling decreases the plugin performance.
- **Name** name of the plugin configuration;
- **Module** in the first field select one of plugin modules. This field displays all the plugins located in the /plugins directory of the trade server specified in the field.

Each configuration of plugin is bound to certain trade server, thus it affects only its operation accordingly.


Parameters

The block of managing external parameters of the plugin is available in the bottom part of the window. Such parameters can be implemented during the development of plugin modules; they allow managing them from the outside.

The following commands are used for managing parameters:

- **Add** add a new parameter. A line appears upon pressing this button. Specify the parameter name in the "Parameter" field, and the value of this parameter in the "Value" field. String type parameters are created by default. To select another type (integer or fractional) click the arrow on the "Add" button.
- **Edit** edit a selected parameter. The same action can be performed by a double click on the required field.
- **Delete** delete a selected parameter.

Information



This tab displays various information on the plugin module: description, copyright, author, version of the plugin module and version of MetaTrader 5 Server API used for developing this plugin.

Profiling

The profiling is enabled using the "Enable plugin profiling option" in the plugin settings. This procedure allows estimating the plugin performance by measuring the time of calls of hooks and event handlers within the plugin. The time is estimated separately for each hook and handler in the plugin.

After enabling the profiling, the server will start gathering the statistics on the plugin operation and outputting the results in the journal every 5 minutes. To request the journal records, use "Profile" keyword.

- It is recommended to enable profiling during testing only, as it slows down plugins.
- Profiling should be enabled before enabling the plugin. If the plugin is already enabled, it should be re-launched after enabling profiling. This is necessary for the correct data collection.

The following information is gathered during profiling:

- **Hook/event handler state** two states are possible: active state (the hook/event handler was executing during estimation), unactive state (the hook/event handler was not executing during estimation). If a hook/handler stays in the active state for more than 5 seconds, a message about a possible deadlock is displayed (the second line in the example). If a hook/handler stays

MetaTrader 5 trading platform

active for more than 0.5 seconds, a message informing that the hook/handler is too slow is displayed (third line in the example).

14:10:01	Simple Plugin	Profile IMTConSymbolSink::OnSymbolUpdate: unactive state
14:10:01	Simple Plugin	Profile IMTConSymbolSink::OnSymbolUpdate: possible deadlock
14:10:01	Simple Plugin	Profile IMTConSymbolSink::OnSymbolUpdate: too slow: max pro

- **Number of calls** the total number of calls of the hook/handler during the plugin operation.

14:10:01	Simple Plugin	Profile IMTConSymbolSink::OnSymbolUpdate: 5 calls
----------	---------------	---

- **Time of last call** time of the last call of the hook/handler accurate to millisecond.

14:10:01	Simple Plugin	Profile IMTConSymbolSink::OnSymbolUpdate: last call at 2013.0
----------	---------------	---

- **Minimal execution time** minimal time of execution of the hook/handler (in milliseconds) during the plugin operation.

14:10:01	Simple Plugin	Profile IMTConSymbolSink::OnSymbolUpdate: time min 0 msc
----------	---------------	--

- **Maximal execution time** maximal time of execution of the hook/handler (in milliseconds) during the plugin operation.

14:10:01	Simple Plugin	Profile IMTConSymbolSink::OnSymbolUpdate: time max 2 msc
----------	---------------	--

- **Average execution time** average time of execution of the hook/handler (in milliseconds) during the plugin operation.

14:10:01	Simple Plugin	Profile IMTConSymbolSink::OnSymbolUpdate: time avg 0 msc
----------	---------------	--

- **Total execution time** total time of execution of the hook/handler (all calls in milliseconds) during the plugin operation.

14:10:01	Simple Plugin	Profile IMTConSymbolSink::OnSymbolUpdate: time total 0 msc
----------	---------------	--

Context Menu

The context menu of the "Plugins" section contains the following commands:

- **+ Add** add a new plugin configuration;
- **⚙ Edit** edit a selected plugin configuration;
- **✗ Delete** delete a selected plugin configuration;
- **↑ Move Up** move a selected plugin configuration up relative to others;
- **↓ Move Down** move a selected plugin configuration down relative to others;

MetaTrader 5 trading platform


-  **Sort Alphabetically** sort configurations alphabetically. Please note that sorting is done on the server, not in the local terminal.
-  **Enable** enable the selected configuration.
-  **Disable** disable the selected configuration.
-  **Export to File** export the settings of plugins to a file.
-  **Import from File** import the settings of plugins to a file.
-  **Journal** request logs according to the selected configuration. This will open the trade server logs section, with the name of the selected configuration automatically specified in the query field. You will only need to press the request button.
-  **Find** open a search window;
- **Auto Arrange** if this option is enabled the size of columns is selected automatically;
- **Grid** this option shows/hides field separators in the table .

MetaTrader 5 Trading Platform / Platform Setup / Reports

Reports

Reports allow analyzing clients' trading activity. Report settings are managed in the administrator terminal, because they are generated exactly on the trade server side. Reports are viewed in a manager terminal. A manager requests a report with certain parameters, the server generates it and sends back ready HTML files.

The trading platform features multiple standard reports. Additional reports can be created using MetaTrader 5 Report API.




For easy access and efficiency, all reports are displayed as a tree list, in which reports are grouped by servers, for which they are configured. You can also [create subdirectories](#) to separate reports by purpose: "Accounts", "Daily Reports", "Gateways", etc.

Adding and Editing Reports

To add or edit a report, click  or  in the Edit menu or in the Standard toolbar.

It is possible to edit multiple configurations. Select multiple reports using the Ctrl or Ctrl+Shift keys and proceed to editing. Using this functionality, you can enable and disable reports in bulk.

Common



Report: Trade Transactions

Common Information

Reports are server plugins providing built-in or custom reports. Please specify report name, select report plugin, and specify additional parameters if needed.

☒ Enable

Name: Trade Transactions

Type: Trade Transactions Trade Main, 1

Parameter	Value
ab Base Directory	Trade Transaction Report
ab Show group owner	Yes
ab Show daily transactions	Yes
ab Show reason	No
ab Show retcode	No
ab Show rejected	No

Add Edit Delete

OK Cancel Help

The following parameters should be specified on this tab:

- **Enable** enable/disable the report. If the report is disabled, it will not be available in the manager terminal. Disabled reports are marked with icon  in the list.
- **Name** the name of the report configuration and path to it.

Specify paths to configurations to create a hierarchy of reports by arranging them into directories according to their purpose. A well-created structure can assist in setting individual report access permissions for manager accounts. For example, you can create a separate directory with dealer transaction reports, a separate directory for marketers who are responsible for database analysis and customer acquisition, etc.:

Trades\Daily Reports
Trades\Deals History
Marketing\First Time Deposit
Marketing\Lifetime Value

- **Type** all reports available on the server are displayed here. The list is compiled based on the DLL report files which are located under the /report directory of the main trading server. The platform features a variety of built-in standard reports, while additional reports can be created using the MetaTrader 5 Report API.
- **Trader Server** to the right of the Type field, select a trade server the report is configured for. The report will be generated using the data on the specified server; and it will be available only when a manager connects to the specified server.

- Each report configuration is bound to a certain trade server. Therefore, report generation will be available only when a manager connects to this server;
- Reports are generated for a manager in accordance with his or her access permissions. Reports are generated only for available groups of accounts.


Parameters

The block of additional report parameters is available in the bottom part of the window. The additional parameters are available if they are implemented by the report developer.

The following commands are used for managing additional parameters:

- **Add** add a new parameter. A line appears upon pressing this button. Specify the parameter name and value in it. String type parameters are created by default. To select another type (integer or fractional) click the arrow on the "Add" button.
- **Edit** edit a selected parameter. The same action can be performed by a double click on the required field.
- **Delete** delete a selected parameter.

Information



This tab displays various information on the report module: description, copyright, author, version of the report module and version of MetaTrader 5 Report API used for developing this report.

Furthermore, it displays information on available formats (a report can be generated in the form of a HTML page or in the form of a table), snapshots of databases required for the report generation. A database snapshot is a fixation of a database state on the server for generating the report (for example, the account database).

Standard Reports

The standard delivery package of the trading platform includes several ready-made reports:

- **Accounts Groups** statistical report on accounts in groups on a server.
- **Accounts Grow** report on the growth of the number of accounts in groups on a server.
- **Accounts Lifetime by Countries** lifetime of accounts with a distribution by countries.
- **Agents** report on all transactions connected with agent commissions.
- **Agents Detailed** detailed report on agent commissions.
- **Credit Facility** credit operations report for the selected period.
- **Daily** report on the financial state of the requested accounts as of the end of the day.
- **Daily Detailed** detailed report on the financial state of the one selected account as of the end of the day.

- **Daily Server Logs** statistical report on the operation of the platform for the specified day.
- **Daily Dealing** daily report on the activity of dealers.
- **Daily Trades** report on trade operations for the specified day.
- **Daily Orders** report on client orders open at the end of the selected day.
- **Daily Positions** report on client orders open at the end of the selected day.
- **Daily Expert Advisors** report on trading operations performed by Expert Advisors of clients.
- **Deals History** summary report on the deals for the selected period.
- **Deals Profit** detailed report on deals for the selected period.
- **Deals Initiators** deal initiators (reasons) report.
- **Deals Geography** trading activity distribution by country.
- **Deals Weekly** trader activity report.
- **Deposit and Withdrawal** report on deposit and withdrawal operations for the selected period.
- **Equity** report on the financial state of the requested accounts as at the end of the day. The accounts are grouped according to their "Comment" field value. This report allows to generate reports on clients' accounts grouping them by custom criteria.
- **Margin Calls** report on the state of margin call or stop out accounts.
- **Orders History** summary report on the orders for the selected period.
- **Positions History** summary report on positions for the selected period.
- **Segregated** summary report on the change of financial state of the requested accounts for the specified period.
- **Summary** summary motion of funds and funds cycles for the selected period.
- **Gateways Turnover** report on volumes of the deals handled by gateways.
- **Gateways Profit** report on volumes of the deals handled by gateways, as well as the profit earned by a broker when handling these deals.
- **Gateways White Label** report on volumes of the deals performed on a trading server by external brokers via MetaTrader 5 Gateway (standard or White Label version).
- **Execution Type** report on the number, volume and type of preformed trades.
- **Trade Accounts** report on the current trading statuses of client accounts.
- **Trade Transactions** provides detailed data on trading operations on MetaTrader 5 servers.
- **Trade Modifications** report on trade operations manually changed by an administrator, manager or API.
- **Trade Performance Summary** detailed trading statistics of trading accounts.
- **Trade Group Statistics** detailed statistics of groups: the number of accounts, commission amounts, share of trades by type, and more.
- **StopOut Compensations** report on operations associated with the compensation of a negative balance in the situation of Stop out. All trades with the "so compensation" type are included into this report.
- **Money Flow Daily** a group of reports presenting the movement of funds on client accounts.
- **Money Flow Weekly** a group of reports representing the weekly movement of funds on client accounts.
- **Lifetime Value** a group of reports concerning client LTVs.

MetaTrader 5 trading platform

- **First Time Deposit** a group of reports on first-time deposits on client accounts.
- **Retention of Clients** new client retention report.
- **Retention of Trading Accounts** new client retention report by individual accounts.
- **NFA** a group of reports to be submitted to NFA regulator.
- **EMIR** a report to be submitted to a regulator according to EMIR.
- **Fund Overview** a report reflecting the key characteristics of a hedge fund.
- **Risk Appetite** a report reflecting the risk level accepted by traders.
- **Fast Profit Deals** this report is designed to detect traders exploiting arbitrage opportunities through quote delays.


The availability of these reports is determined by an administrator when setting up the platform.

- DLL modules of these reports are located in the /report folder of the main trade server.
- A DLL module is automatically unloaded from the memory of the trade server once all the report configurations of this module are disabled.

Additional reports

A wide variety of additional reports is available in the App Store on the technical support website. The App Store showcase is featured directly in Manager Terminals, allowing managers to view and order additional products without leaving their workspace:

MetaTrader 5 trading platform



Furthermore, you can develop your own reports using [MetaTrader Report API](#). The package contains all the necessary tools, alongside the source code examples of standard reports. You can modify the source codes to create your own reports.

Context Menu

The context menu of the "Reports" section contains the following commands:

-  **Add** add a new report;
-  **Edit** edit a selected report;
-  **Delete** delete a selected report;
-  **Move Up** move a selected report up relative to others;
-  **Move Down** move a selected report down relative to others;
-  **Sort Alphabetically** sort configurations alphabetically. Please note that sorting is done on the server, not in the local terminal.
-  **Enable** enable the selected configuration.
-  **Disable** disable the selected configuration.
-  **Export to File** [export](#) the settings of reports to a file.
-  **Import from File** [import](#) the settings of reports to a file.
-  **Journal** request [logs](#) according to the selected configuration. This will open the trade server logs section, with the name of the selected configuration automatically specified in the query field. You will only need to press the request button.
-  **Find** open a [search](#) window;
- **Auto Arrange** if this option is enabled the size of columns is selected automatically;
- **Grid** this option shows/hides field separators in the table with the reports.

MetaTrader 5 Trading Platform / Platform Setup / Reports / Accounts Groups

Accounts Groups Report

Accounts Groups Report is a statistical report on accounts groups on the server. The following data is provided for each group:

- **Accounts** number of accounts in a group;
- **Active** number of active accounts in a group. An account is deemed to be active, if it performed at least one connection to the server over the past three months.
- **Balance** current total balance of all accounts in a group;
- **Floating P/L** current total floating profit/loss of all accounts in a group;
- **Equity** current total amount of funds on all accounts in a group;
- **Currency** deposit currency in a group.

The settings are not provided for this report. All parameters are relevant at the moment of the report request.

MetaTrader 5 Trading Platform / Platform Setup / Reports / Accounts Growth

Accounts Growth Report

Accounts Grow Report is a report on the increase of accounts number in groups on the server. The report contains several diagrams:


- **Accounts Grow** increase of accounts number by months in the following types of groups: Real, Preliminary, Demo and Contest.
- **Real Accounts for the last 5 years by months** increase of real accounts (Real* groups accounts) number for the last 5 years by months.
- **Preliminary Accounts for the last 5 years by months** increase of preliminary accounts (Preliminary* groups accounts) number for the last 5 years by months.
- **Demo Accounts for the last 5 years by months** increase of demo accounts (Demo* groups accounts) number for the last 5 years by months.
- **Contest Accounts for the last 5 years by months** increase of contest accounts (Contest* groups accounts) number for the last 5 years by months.
- **Active Accounts for the last 3 months** diagram displaying accounts distribution by their activity. An account is deemed to be active, if it performed at least one connection to the server over the past three months. All active accounts are distributed according to the groups types (demo, contest, preliminary and real).

The settings are not provided for this report. All parameters are relevant at the moment of the report request.

[MetaTrader 5 Trading Platform](#) / [Platform Setup](#) / [Reports](#) / Accounts
Lifetime by Countries

Accounts Lifetime by Countries

The report shows the duration for which your traders remain active after opening their accounts. The information is presented by country. The lifetime is calculated from the account creation date to the date of the last connection.



Configuration in MetaTrader 5 Manager

The following parameters should be configured in the Manager terminal before requesting the report:

- **Groups** groups for which account reports should be generated. You can specify one or several accounts separated by commas.
- **Period** the start and end dates of the period for which the report will be generated.

Information in the report

Information on the lifetime of trading accounts is presented in the form of an interactive map. It is followed by a table with more detailed information on the top 1000 accounts with the longest lifetime:

- **Login** account number.
- **Name** account holder's name.
- **Lifetime** account lifetime in days.
- **Registration** account creation date.
- **Last Access** date of the last connection to the account.
- **Country** client's country of residence.
- **Group** group the account belongs to.
- **Account Comment** comment to the accounts.

MetaTrader 5 Trading Platform / Platform Setup / Reports / Agents

Agents Report

Agents Report is a report on all transactions connected with charging agent commissions.

Setup

The following parameters must be set in the manager terminal before requesting the report:

- **Groups** groups containing the accounts, on which the report will be created;
- **Period** starting and ending date of the period, the deals for which will be requested.

The following data on agent commissions charging deals is provided:

- **Deal** commission charging deal ticket;
- **Login** number of the account charged by the commission;
- **Name** account holder name;

- **Group** group the account belongs to;
- **Country** client's country of residence;
- **Account comment** comment to the trading account;

- **Time** commission charging time;
- **Type** deal type;
- **Comment** comments on the deal. The comments contain the number of the account, from which an agent receives commission when performing deals on it;
- **Profit** commission size;
- **Currency** commission currency.

MetaTrader 5 Trading Platform / Platform Setup / Reports / Agents
Detailed

Agents Detailed Report

Agents Detailed Report is a detailed report on agent commissions. The report reflects deals related to paying commissions accumulated during a trading day/month, as well as client deals, for which the agent received immediate commissions.

Setup

The following parameters should be specified before requesting a report in the manager terminal:

- **Groups** the report will be generated on accounts listed in these groups.
- **Period** trades performed during this period will be requested for the report.

Report

Information in the report is presented in blocks for each agent, containing a list of client deals and commission paying operations, as well as the total commission amount.

The following details are shown for deals, for which the client immediately received commission (immediate charge):

- **Deal** the ticket of the deal.
- **Account** the number of the account, at which the deal was performed.
- **Name** account holder's name.
- **Time** time of the deal. The record has a format of YYYY.MM.DD HH:MM (year.month.day hour:minute).
- **Position** the ticket of the position, to which the deal is related.
- **Symbol** the symbol, for which the deal was executed.
- **Volume** deal volume in lots.
- **Action** deal type: buying or selling.
- **Entry** deal direction: market entry (in), market exit (out), position reversal (in/out), closing by an opposite position (out by).
- **Price** the price at which the deal is executed.
- **Commission** standard commission for the deal.
- **Group** the group the account belongs to.
- **Type** commission type: instant agent commission, daily agent commission, monthly agent commission.
- **Agents Commission** amount of calculated commission which the agent received for the deal.
- **Currency** commission currency.

The following data is provided for deals related to agent commissions accumulated during a day/month:

MetaTrader 5 trading platform

- **Account** the number of the account, for which the commission on deals was accumulated.
- **Name** account holder's name.
- **Time** commission charging time. The record has a format of YYYY.MM.DD HH:MM (year.month.day hour:minute).
- **Type** commission type: instant agent commission, daily agent commission, monthly agent commission.
- **Agents Commission** amount of calculated commission to be transferred to the agent.
- **Currency** commission currency.

Information about the agent is given below each block. It includes the agent's login, name and total amount of commission.

The amount of commissions to all agents over the selected period is provided at the end of the table.