

Indian Institute of Information Technology, Sri City, Chittoor

(An Institute of National Importance under an Act of Parliament)

Computer Communication Networks

Transport Layer


Dr. Raja Vara Prasad

Assistant Professor


IIIT Sri City

TCP

- TCP is a full duplex service
- No multicasting
- Maximum segment size (MSS) is the maximum amount of data that a TCP segment can contain.



TCP Segment




TCP Segment

- The 16-bit receive window indicates the number of bytes that a receiver is willing to accept
- Header length filed is 4-bytes, specifies the length of the TCP header in 32-bit words.
- Options are used to negotiate MSS, include time-stamping, etc.
- The flag field contains 6 bits, RST, SYN, FIN are used for connection setup and teardown.
- PSH indicates that data has to be sent to upper layers immediately.
- URG is used to mark the segment as urgent, when it is on there will be a 16-bit urgent data pointer filed at the end of urgent data.


TCP Sequence Numbers

- The sequence number of a segment is the byte-stream number of the first byte of data.
- The acknowledge number is the sequence number of the next byte that is receiver is expecting from source.
- TCP provides cumulative acknowledgments; Out-of-order segements?
- Sequence numbers may not always start from '0'.




TCP Timeout


- SampleRTT: RTT of a freshly transmitted packet. Computed for each RTT.
- Exponentially weighted moving average: EstimatedRTT = $(1-\alpha)$ EstmiatedRTT + α SampleRTT
- $\alpha = 0.125$
- DevRTT = (1β) DevRTT + β | SampleRTT EstimatedRTT|
- $\beta = 0.25$
- Timeout = EstimatedRTT + 4. DevRTT



Example: TELNET



Example: Different scenarios of Reliability aspects



Doubling the Timeout interval:


intervals grow exponentially after each retransmission

Fast Retransmit:

duplicate ACK multiple times
Example: three duplicate ACKs are received → the TCP sender performs a **fast retransmit**, retransmitting the missing segment *before* that segment's timer expires

Selection: Go-Back-N or Selective Repeat?


TCP's error-recovery mechanism is probably best categorized as a hybrid of GBN and SR protocols



Flow Control

Flow control is thus a speed-matching service \rightarrow matching the rate at which the sender is sending against the rate at which the receiving application is reading

receive window: give the sender an idea of how much free buffer space is available at the receiver



```
LastByteRcvd - LastByteRead ≤ RcvBuffer
```


The receive window, denoted rwnd is set to the amount of spare room in the buffer:


```
rwnd = RcvBuffer - [LastByteRcvd - LastByteRead]
```

LastByteSent - LastByteAcked ≤ rwnd


TCP Connection Establishment

TCP Connection Termination






TCP States at Cleint




TCP States at Server



Congestion


- Why does Congestion occur?
- Packet arrival rate at a router is near or higher than the output link capacity.
- Consequences?
- Buffer overflows, retransmissions to compensate for lost packets
- Unneeded retransmissions

Congestion Scenario - 1





- (a) Host A knows whether buffer in the router has free space or not (Magic!)
- (b) Host A retransmits only if it is sure that packet is lost (Someone has to give this information)
- (c) Host A retransmits on timeouts!

Congestion Scenario - 1



Congestion Scenario - 2






Congestion Control

- End-to-end congestion control: no explicit information about congestion the network
- Network-assisted Congestion Control: Choke packet
- How does TCP identify congestion?
- No assistance form IP
- Identify congestion through timeouts and duplicate ACKs

Congestion Control






Figure 3.50 • Congestion-control framework for ATM ABR service

EFCI bit. Each data cell contains an explicit forward congestion indication (EFCI) bit.


Cl and NI bits: congestion indication (CI) bit and a no increase (NI) bit

ER setting. Each RM cell also contains a 2-byte explicit rate (ER) field.


TCP's Congestion Control

- How does TCP control the sending rate?
- Defines a new variable called cwnd.
- LastByteSent LastByteAcked ≤ min{cwnd,rwnd}
- Sends cwnd bytes of infomration per RTT (approximately)
- Can we adjust the speed? Slef-clocking
 - A lost segment triggers the sender to reduce rate of transmission
 - An acknowledgment indicates all is well! Increase the rate
 - Bandwidth Probing


TCP Slow Start



TCP Congestion Control



TCP Congestion Window



AIMD




Figure 3.54 • Additive-increase, multiplicative-decrease congestion control

additive-increase, multiplicative decrease (AIMD) form of congestion control:

TCP linearly increases its congestion window size (and hence its transmission rate) until a triple duplicate-ACK event occurs.