

系统默认没有安装插件，需要进行安装：

```
1 #安装插件
2 sudo apt install gstreamer1.0-rtsp
```

推流前需要启动RTSP服务器，需要运行mediamtx

访问：[mediamtx](#)，下载mediamtx_vx.x.x_linux_arm64v8.tar.gz


或者访问[资料网盘/6-开发软件/mediamtx_v1.9.1_linux_arm64v8.tar.gz](#)

将mediamtx_v1.9.1_linux_arm64v8.tar.gz传到板卡解压并运行：

```
1 tar xvf mediamtx_v1.9.1_linux_arm64v8.tar.gz
2
3 #运行mediamtx
4 sudo ./mediamtx &
5
6 #信息输出如下
7 2024/09/18 16:24:54 INF MediaMTX v1.9.1
8 2024/09/18 16:24:54 INF configuration loaded from /home/cat/mediamtx.yml
9 2024/09/18 16:24:54 INF [RTSP] listener opened on :8554 (TCP), :8000 (UDP/RTSP), :8001 (UDP/RTCP)
10 2024/09/18 16:24:54 INF [RTMP] listener opened on :1935
11 2024/09/18 16:24:54 INF [HLS] listener opened on :8888
12 2024/09/18 16:24:54 INF [WebRTC] listener opened on :8889 (HTTP), :8189 (ICE/UDP)
13 2024/09/18 16:24:54 INF [SRT] listener opened on :8890 (UDP)
```


看信息输出可得知，使用的是同目录下的 mediamtx.yml 配置文件，所以修改配置文件就行，用 cp 命令复制两份配置文件再操作。

然后就是，原本的配置文件开了很多的直播协议，可以关掉，以 rtmp 为例子，关闭方法如下：



框选的部分改成 no，就不会启用 rtmp 协议了，其他协议同理。

然后是 rtsp 本身，文档本身只用到了 tcp 协议，所以也可以把 udp，multicast 都关掉，这样只修改 tcp 的端口就可以了，修改方法如下：



```
C:\Users\Administrator\AppData\Local\Temp\72003CBA2EC> ! mediامتx.yml
215 # If the server receives a request from one of these entries, it in logs
216 # will be taken from the X-Forwarded-For header.
217 playbackTrustedProxies: []
218 #####
219 # Global settings -> RTSP server.
220
221 # Enable publishing and reading streams with the RTSP protocol.
222 rtsp: yes
223 # List of enabled RTSP transport protocols.
224 # UDP is the most performant, but doesn't work when there's a NAT/firewall between
225 # server and clients, and doesn't support encryption.
226 # UDP-multicast allows to save bandwidth when clients are all in the same LAN.
227 # TCP is the most versatile, and does support encryption.
228 # The handshake is always performed with TCP.
229 protocols: [udp, multicast, tcp]
230 # Encrypt handshakes and TCP streams with TLS (RTSPS).
231 # Available values are "no", "strict", "optional".
232 encryption: "no"
233 # Address of the TCP/RTSP listener. This is needed only when encryption is "no" or "optional".
234 rtspAddress: :8554
235 # Address of the TCP/TLS/RTSPS listener. This is needed only when encryption is "strict" or "optional".
236 rtspAddress: :8322
237 # Address of the UDP/RTP listener. This is needed only when "udp" is in protocols.
238 rtpAddress: :8000
239 # Address of the UDP/RTCP listener. This is needed only when "udp" is in protocols.
240 rtcpAddress: :8001
241 # IP range of all UDP-multicast listeners. This is needed only when "multicast" is in protocols.
242 multicastIPRange: 224.1.0.0/16
243 # Port of all UDP-multicast/RTP listeners. This is needed only when "multicast" is in protocols.
244 multicastRTPPort: 8002
245 # Port of all UDP-multicast/RTCP listeners. This is needed only when "multicast" is in protocols.
246 multicastRTCPPort: 8003
247 # Path to the server key. This is needed only when encryption is "strict" or "optional".
248 # This can be generated with:
249 # openssl genrsa -out server.key 2048
```

框选的部分只保留 tcp。

最终效果图如下：

```
cat@lubancat:~$ cd mediامتx
cat@lubancat:~/mediامتx$ ls
LICENSE mediامتx mediامتx.yml
cat@lubancat:~/mediامتx$ vim mediامتx.yml
cat@lubancat:~/mediامتx$ mv mediامتx.yml mediامتx8554.yml
cat@lubancat:~/mediامتx$ ls
LICENSE mediامتx mediامتx8554.yml
cat@lubancat:~/mediامتx$ cp mediامتx8554.yml mediامتx8555.yml
cat@lubancat:~/mediامتx$ ls
LICENSE mediامتx mediامتx8554.yml mediامتx8555.yml
cat@lubancat:~/mediامتx$ vim mediامتx8555.yml
cat@lubancat:~/mediامتx$ sudo ./mediامتx mediامتx8554.yml
2025/08/08 09:33:23 INF MediaMTX v1.9.1
2025/08/08 09:33:23 INF configuration loaded from /home/cat/mediامتx/mediامتx8554.yml
2025/08/08 09:33:23 INF [RTSP] listener opened on :8554 (TCP), :8000 (UDP/RTP), :8001 (UDP/RTCP)
^C2025/08/08 09:33:29 INF shutting down gracefully
2025/08/08 09:33:29 INF [RTSP] listener is closing
2025/08/08 09:33:29 INF waiting for running hooks
cat@lubancat:~/mediامتx$ sudo ./mediامتx mediامتx8555.yml
2025/08/08 09:33:36 INF MediaMTX v1.9.1
2025/08/08 09:33:36 INF configuration loaded from /home/cat/mediامتx/mediامتx8555.yml
2025/08/08 09:33:36 ERR RTP port must be even
2025/08/08 09:33:36 INF waiting for running hooks
cat@lubancat:~/mediامتx$ vim mediامتx8555.yml
cat@lubancat:~/mediامتx$ vim mediامتx8555.yml
cat@lubancat:~/mediامتx$ sudo ./mediامتx mediامتx8555.yml
2025/08/08 09:36:05 INF MediaMTX v1.9.1
2025/08/08 09:36:05 INF configuration loaded from /home/cat/mediامتx/mediامتx8555.yml
2025/08/08 09:36:05 INF [RTSP] listener opened on :8555 (TCP)
^C2025/08/08 09:36:14 INF shutting down gracefully
2025/08/08 09:36:14 INF [RTSP] listener is closing
2025/08/08 09:36:14 INF waiting for running hooks
cat@lubancat:~/mediامتx$ sudo ./mediامتx mediامتx8555.yml &
[1] 31885
cat@lubancat:~/mediامتx$ 2025/08/08 09:36:17 INF MediaMTX v1.9.1
2025/08/08 09:36:17 INF configuration loaded from /home/cat/mediامتx/mediامتx8555.yml
2025/08/08 09:36:17 INF [RTSP] listener opened on :8555 (TCP)
sudo ./mediامتx mediامتx8554.yml &
[2] 32204
cat@lubancat:~/mediامتx$ 2025/08/08 09:36:23 INF MediaMTX v1.9.1
2025/08/08 09:36:23 INF configuration loaded from /home/cat/mediامتx/mediامتx8554.yml
2025/08/08 09:36:23 INF [RTSP] listener opened on :8554 (TCP), :8000 (UDP/RTP), :8001 (UDP/RTCP)
```

