Overview of Synchronization

- In computer science synchronization refers to the relationships among events, e.g., before, during or after
- There are two constraints of synchronization:
 - → Serialization: Event A must happen before event B
 - → Mutual Exclusion: Event A and B must not happen at the same time
- In multi-threaded programs, the programmer has no control over when a thread runs, as the scheduler makes this decision
- Concurrent programs are often non-deterministic, which means it is not possible to tell, by looking at the program what will happen when it will execute
- Concurrent access to shared data may result in data inconsistency, so we need to apply some concurrency control mechanism using which multiple threads can access shared data without any conflict

Example: Deposit and Withdrawal

Consider a bank account having a balance of Rs.100/. A deposit process deposits Rs. 25/- thus updating the balance of that account to Rs.125/. A withdrawal process runs and withdraws Rs.10/-, thus updating the balance of that account to Rs.115/. The instruction that updates the balance variable can be written in assembly as shown below:

Deposit Process

D1: MOV R1, balance

D2: ADD R1, deposit amt

D3: MOV balance, R1

Withdrawal Process

W1: MOV R2, balance

W2: SUB R2, wdr_amt

W3: MOV balance, R2

Suppose both the processes run concurrently

- Scenario 1: D1, D2, D3, W1, W2, W3 (balance = Rs.115/-)
- Scenario 2: D1, D2, W1, W2, D3, W3 (balance = Rs.90/-)
- Scenario 2: D1, D2, W1, W2, W3, D3 (balance = Rs.125/-)

₩ Data Sharing Among Threads

Normally modifying an object requires several steps. While these steps are being carried out the object is typically not in a well formed state. If another thread tries to access the object during that time, it will likely get a corrupt information. The entire program might have undefined behavior after wards

What data is shared?

- Global data and static local data. The case of static local data is only significant if two (or more) threads execute the function containing static local variable at the same time
- Dynamically allocated data (in heap) that has had its address put into a global/static variable
- Data members of a class object that has two (or more) of its member functions called by different threads at the same time

Data Sharing among Threads (cont...)

What Data is not Shared?

- Local variables are not shared. Even if two threads call the same function they will have different copies of the local variable in that function. This is because the local variables are kept on stack and every thread has its own stack
- Function parameters are not shared. In Languages like C, the parameters of function are also put on the stack & thus every thread will have its own copy of those as well

What is Mutex?

- A mutex is a **MUT**ual **EX**clusion device, and is useful for protecting shared data structures from concurrent modifications, and implementing critical sections
- A mutex has two possible states: unlocked (not owned by any thread), and locked (owned by one thread). It can never be owned by two different threads simultaneously
- A thread attempting to lock a mutex that is already locked by another thread is suspended until the owner thread unlocks the mutex
- Linux guarantees that race condition do not occur among threads attempting to lock a mutex

丛 How to Use a Mutex?

- i. Create and initialize a mutex variable
- ii. Several threads attempt to lock the mutex
- iii. Only one thread succeed and that thread owns the mutex
- iv. The owner thread carry out operations on shared data
- v. The owner threads unlock the mutex
- vi. Another thread acquires the mutex and repeats the process
- vii. Finally the mutex is destroyed

Mutex Initialization

<u>Static Initialization</u>: In case where default mutex attributes are appropriate, the following macro can be used to initialize a mutex that is statically allocated.

```
pthread mutex t mut = PTHREAD MUTEX INITIALIZER;
```

Run time initialization: In all other cases, we must dynamically initialize the mutex using pthread mutex init()

• This function initializes the mutex object pointed to by mptr according to the mutex attributes specified in attr. If attr is NULL, default attributes are used instead

Locking, Unlocking and Destroying mutex

```
int pthread_mutex_lock(pthread_mutex_t *mptr);
int pthread_mutex_unlock(pthread_mutex_t *mptr);
int pthread_mutex_trylock(pthread_mutex_t *mptr);
int pthread_mutex_destroy(pthread_mutex_t *mptr);
```

- The lock() call will lock the pthread_mutex_t object referenced by mptr. If mutex is already locked, the calling thread blocks until the mutex is unlocked
- The **trylock()** is similar to lock except that if the mutex object is currently locked, the call returns immediately with the error code EBUSY
- The unlock () call release the mutex object. The manner in which a mutex is released is dependent on the mutex's attribute type. If there are threads blocked on the mutex object referenced by mptr when unlock () is called, the scheduling policy shall determine which thread shall acquire the mutex
- The destroy () call destroys the mutex object

Be sure to observe following points to avoid dead locks while using mutexes:

- No thread should attempt to lock or unlock a mutex that has not been initialized
- ii. Only the owner thread of the mutex (i.e the one which has locked the mutex) should unlock it
- iii.Do not lock a mutex that is already locked
- iv.Do not unlock a mutex that is not locked
- v. Do not destroy a locked mutex

Mutex Attributes

PTHREAD MUTEX INITIALIZER (fast mutex)

- Locking an already locked mutex results in suspending the calling thread
- · Unlocking an already unlocked mutex results in undefined behavior
- Unlocking a mutex that is not locked by calling thread results in undefined behavior

PTHREAD_ERRORCHECK_MUTEX_INITIALIZER_NP(error checking mutex)

- Locking an already locked mutex returns immediately with an error EDEADLK
- · Unlocking an already unlocked mutex returns an error
- · Unlocking a mutex that is not locked by calling thread returns an error

PTHREAD RECURSIVE MUTEX INITIALIZER NP (recursive mutex)

- Locking an already locked mutex returns immediately with a success return code.
 The number of times the thread owning the mutex has locked it is recorded in the
 mutex. The owning thread must call pthread_mutex_unlock() the same number of
 times before the mutex returns to the unlocked state
- · Unlocking an unlocked mutex returns an error
- Unlocking a mutex that is not locked by calling thread results in undefined behavior

Mutex Attributes

- A mutex has a set of attributes which can be set before creating it and passed to the pthread_mutex_init() function as its second argument. (which we have kept NULL in previous examples)
- The **pthread_mutexattr_init()** function initializes the mutex attribute object attr and fills it with default values for the attributes
- The pthread_mutexattr_settype() sets the mutex kind attribute in attr to the value specified by second argument kind
- LinuxThreads supports only one mutex attribute, the mutex kind:
 - →PTHREAD MUTEX FAST NP for fast mutex
 - →PTHREAD MUTEX RECURSIVE NP for recursive mutex
 - → PTHREAD MUTEX ERRORCHECK NP for error checking mutex

Note: NP means, these are non-portable extension to POSIX standard

Condition Variables

Producer-Consumer Problem

- Producer produces information that is consumed by a consumer process. To allow producer and consumer run concurrently we must have a buffer that can be filled by the producer and emptied by the consumer. The buffer can be bounded or unbounded
- **Unbounded Buffer:** Places no practical limit on the size of the buffer. The consumer may have to wait for new items if the buffer is empty, but the producer can always produce new items
- **Bounded Buffer:** Assumes a fixed size buffer. The consumer must wait if the buffer is empty and the producer must wait if the buffer is full

While an item is being added to or removed from the buffer, the buffer is in an inconsistent state. Therefore, threads must have exclusive access to the buffer. If a consumer thread arrives while the buffer is empty, it blocks until a producer adds a new item

Producer-Consumer Problem (cont...)

Implicit Synchronization:

\$ grep prog1.c | wc -1

grep is a producer process and wc is a consumer process. grep writes into the pipe and wc reads from the pipe. The required synchronization is handled implicitly by the kernel. If producer gets ahead of the consumer (i.e. the pipe fills up), the kernel puts the producer to sleep when it calls write(), until more room is available in the pipe. If consumer gets ahead of the producer (i.e. the pipe is empty), the kernel puts the consumer to sleep when it calls read(), until some data is there in the pipe

Explicit Synchronization:

When we as programmers are using some shared memory/data structure, we use some form of IPC between the procedure and the consumer for data transfer. We also need to ensure that some type of explicit synchronization must be performed between the producer and consumer

Producer-Consumer Problem (cont...)

Implicit Synchronization:


\$ grep prog1.c | wc -1

grep is a producer process and wc is a consumer process. grep writes into the pipe and wc reads from the pipe. The required synchronization is handled implicitly by the kernel. If producer gets ahead of the consumer (i.e. the pipe fills up), the kernel puts the producer to sleep when it calls write(), until more room is available in the pipe. If consumer gets ahead of the producer (i.e. the pipe is empty), the kernel puts the consumer to sleep when it calls read(), until some data is there in the pipe

Explicit Synchronization:

When we as programmers are using some shared memory/data structure, we use some form of IPC between the procedure and the consumer for data transfer. We also need to ensure that some type of explicit synchronization must be performed between the producer and consumer

Producer-Consumer Example




to by in and places a number val at that location.

out and removes the number val from that location.

Condition Variables

- Solution to such problems like the producer-consumer, reader-writer, barber-shop and so on are condition variables
- A condition variable is a synchronization construct that allows threads to suspend execution and relinquish the processors until some condition is satisfied
- The two basic operations on condition variables are:
- signal (): Wake up a sleeping thread on this condition variable
- wait(): Release lock, goto sleep, reacquire lock after you are awoken up
- So we can say that a condition variable enable a thread to sleep inside a CS. Any lock held by the thread is automatically released when the thread is put to sleep
- A mutex is for locking and a condition variable is for waiting

Producer Consumer with Condition Variables



With every condition variable there is an associated mutex variable. Whenever a thread wants to invoke wait() or signal() operation, it must hold the mutex associated with that condition variable

Initializing pthread_cond_t Variable

Static Initialization: In case where default attributes are appropriate, the following macro can be used to initialize a pthread cond t variable

```
pthread cond t cond = PTHREAD COND INITIALIZER;
```

Run time initialization: In all other cases, we must dynamically initialize the condition variable using pthread cond init()

• This function initializes the condition variable object pointed to by cond using the condition attributes specified in attr. If attr is NULL, default attributes are used instead. LinuxThreads implementation supports no attributes for conditions, hence the attr parameter is actually ignored

Operations on pthread cond t Variable

- The pthread_cond_signal() restarts one of the threads that are waiting on the condition variable cond. If no threads are waiting on cond, nothing happens. If several threads are waiting on cond, exactly one is restarted, but it is not specified which
- The thread that calls pthread_cond_wait() atomically unlocks its second argument mutex and waits for the condition variable cond to be signaled by suspending its execution

Example: wait() and signal()

- Consider the buffer protected by mutex mut, and a condition variable empty
- A call to **pthread_cond_wait()** should be done as part of a conditional statement, e.g., the consumer thread will wait on condition variable empty only when the buffer gets empty
- The producer thread will give a signal on condition variable empty, when it places the first item in the buffer
- When the condition variable cond is signaled by a consumer thread, pthread_cond_wait() will implicitly lock the mutex again before returning. That is the reason the pthread_mutex_unlock() statement is required after modifying the buffer by the producer thread

Consumer Thread

```
pthread_mutex_lock(&mut);
while(buffercount == 0)
    pthread_cond_wait(&empty, &mut);
//modify the buffer
pthread_mutex_unlock(&mut);
```

Producer Thread

```
pthread_mutex_lock(&mut);
//modify the buffer
if(buffercount == 1)
    pthread_cond_signal(&empty);
pthread_mutex_unlock(&mut);
```