ConcretePage.com

HOME ALL TUTORIALS JAVA 8 SPRING BOOT ANGULAR ANDROID Search Tutorials Search

Home > Spring

Spring Bean Life Cycle Tutorial

By Arvind Rai, June 17, 2016

This page will walk through spring bean life cycle tutorial. In spring bean life cycle, initialization and destruction callbacks are involved. Different spring bean aware classes are also called during bean life cycle. Once dependency injection is completed, initialization callback methods execute. Their purposes are to check the values that have been set in bean properties, perform any custom initialization or provide a wrapper on original bean etc. Once the initialization callbacks are completed, bean is ready to be used. When IoC container is about to remove bean, destruction callback methods execute. Their purposes are to release the resources held by bean or to perform any other finalization tasks. When more than one initialization and destructions callback methods have been implemented by bean, then those methods execute in certain order. Here on this page we will discuss spring bean life cycle step by step. We will discuss the order of execution of initialization and destruction callbacks as well as spring bean aware classes.




Contents

- Spring Bean Life Cycle Diagram and Steps
- Initialization Callbacks
- Destruction Callbacks
- Spring Bean Life Cycle Order
- BeanNameAware
- BeanFactoryAware
- BeanPostProcessor
- @PostConstruct and @PreDestroy
- InitializingBean and DisposableBean
- init-method and destroy-method in XML and initMethod and destroyMethod in JavaConfig
- Download Source Code

Spring Bean Life Cycle Diagram and Steps

Find the spring bean life cycle diagram. Here are showing the steps involved in spring bean life cycle.



A bean life cycle includes the following steps.

1. Within IoC container, a spring bean is created using class constructor.

Angular Select Option Set Se Dynamically

Angular 2 Radio Button and Example

Angular minlength and maxl Validation Example

Angular Pattern Validation Example

Angular HttpClient post

- 2. Now the dependency injection is performed using setter method.
- **3.** Once the dependency injection is completed, BeanNameAware.setBeanName() is called. It sets the name of bean in the bean factory that created this bean.
- **4.** Now < code>BeanClassLoaderAware.setBeanClassLoader() is called that supplies the bean class loader to a bean instance.
- **5.** Now < code>BeanFactoryAware.setBeanFactory() is called that provides the owning factory to a bean instance.
- **6.** Now the IoC container calls BeanPostProcessor.postProcessBeforeInitialization on the bean. Using this method a wrapper can be applied on original bean.
- 7. Now the method annotated with @PostConstruct is called.
- **8.** After @PostConstruct, the method InitializingBean.afterPropertiesSet() is called.
- 9. Now the method specified by init-method attribute of bean in XML configuration is called.
- **10.** And then BeanPostProcessor.postProcessAfterInitialization() is called. It can also be used to apply wrapper on original bean.
- 11. Now the bean instance is ready to be used. Perform the task using the bean.
- **12.** Now when the ApplicationContext shuts down such as by using registerShutdownHook()) then the method annotated with PereDestroy is called.
- **13.** After that <code>DisposableBean.destroy()</code> method is called on the bean.
- 14. Now the method specified by destroy-method attribute of bean in XML configuration is called.
- **15.** Before garbage collection, finalize() method of Object is called.

Initialization Callbacks

In the bean life cycle initialization callbacks are those methods which are called just after the properties of the bean has been set by IoC container. The spring InitializingBean has a method as afterPropertiesSet() which performs initialization work after the bean properties has been set. Using InitializingBean is not being recommended by spring because it couples the code. We should use @PostConstruct or method specified by bean attribute initmethod in XML which is the same as initMethod attribute of @Bean annotation in JavaConfig. If all the three are used together, they will be called in below order in bean life cycle.

- 1. First @PostConstruct will be called.
- 2. Then InitializingBean.afterPropertiesSet() is called
- 3. And then method specified by bean init-method in XML or initMethod of @Bean in JavaConfig.



Destruction Callbacks

In bean life cycle when a bean is destroyed from the IoC container, destruction callback is called. To get the destruction callback, bean should implement spring <code>DisposableBean</code> interface and the method <code>destroy()</code> will be called. Spring recommends not to use <code>DisposableBean</code> because it couples the code. As destruction callback we should use <code>@PreDestroy</code> annotation or bean attribute <code>destroy-method</code> in XML configuration which is same as <code>destroyMethod</code> attribute of <code>@Bean</code> in JavaConfig. If we use all these callbacks together then they will execute in following order in bean life cycle.

- 1. First @PreDestroy will be called.
- 2. After that <code>DisposableBean.destroy()</code> will be called.
- 3. And then method specified by bean destroy-method in XML configuration is called.

Spring Bean Life Cycle Order

Here we will provide a demo in which we will use all initialization and destructions callbacks and bean aware to check their order of execution in bean life cycle. We will use XML configuration.

build.gradle

```
apply plugin: 'java'
apply plugin: 'eclipse'
archivesBaseName = 'SpringDemo'
version = '1'
```

Popular Post

Angular Select Option using

Jackson @JsonIgnore, @JsonIgnoreProperties and @JsonIgnoreType

Angular 2 Http post() Examp

Angular FormArray setValue(patchValue()

Jackson @JsonProperty and Example

Ketto

My son want to be a cricked but now he fighting can Save him

DONATE NO



Featured Post

Jackson Ignore Null and Emp

Angular valueChanges and statusChanges

Angular Material Select : Gel Setting value

Angular Material Radio Butto

Angular 2 Decimal Pipe, Perc and Currency Pipe Example

```
repositories {
    mavenCentral()
}
dependencies {
    compile 'org.springframework.boot:spring-boot-starter:1.3.3.RELEASE'
    compile 'javax.inject:javax.inject:1'
}
```

Book.java

```
package com.concretepage:
import javax.annotation.PostConstruct;
import javax.annotation.PreDestroy;
import org.springframework.beans.BeansException;
import org.springframework.beans.factory.BeanClassLoaderAware;
import org.springframework.beans.factory.BeanFactory;
import org.springframework.beans.factory.BeanFactoryAware;
import org.springframework.beans.factory.BeanNameAware;
import org.springframework.beans.factory.DisposableBean;
import org.springframework.beans.factory.InitializingBean;
public class Book implements InitializingBean, DisposableBean, BeanFactoryAware, BeanNameAware, Bea
        private String bookName;
        private Book() {
                System.out.println("---inside constructor---");
        @Override
        public void setBeanClassLoader(ClassLoader classLoader) {
               System.out.println("---BeanClassLoaderAware.setBeanClassLoader---");
        @Override
        public void setBeanName(String name) {
               System.out.println("---BeanNameAware.setBeanName---");
        public void myPostConstruct() {
                 System.out.println("---init-method---");
        @PostConstruct
        public void springPostConstruct() {
                 System.out.println("---@PostConstruct---");
        }
        @Override
        public void setBeanFactory(BeanFactory beanFactory) throws BeansException {
                System.out.println("---BeanFactoryAware.setBeanFactory---");
        }
        @Override
        public void afterPropertiesSet() throws Exception {
                System.out.println("---InitializingBean.afterPropertiesSet---");
        public String getBookName() {
                return bookName;
        public void setBookName(String bookName) {
                this.bookName = bookName;
                System.out.println("setBookName: Book name has set.");
        public void myPreDestroy() {
                System.out.println("---destroy-method---");
        @PreDestroy
        public void springPreDestroy() {
                System.out.println("---@PreDestroy---");
        @Override
        public void destroy() throws Exception {
                System.out.println("---DisposableBean.destroy---");
```

```
@Override
protected void finalize() {
          System.out.println("---inside finalize---");
}
}
```

MyBeanPostProcessor.java

spring-config.xml

SpringDemo.java

```
package com.concretepage;
import org.springframework.context.support.AbstractApplicationContext;
import org.springframework.context.support.ClassPathXmlApplicationContext;
public class SpringDemo {
    public static void main(String[] args) {
        AbstractApplicationContext context = new ClassPathXmlApplicationContext("spring-conf Book book = (Book)context.getBean("book");
        System.out.println("Book Name:"+ book.getBookName());
        context.registerShutdownHook();
    }
}
```

Output

```
---inside constructor---
setBookName: Book name has set.
---BeanNameAware.setBeanName---
---BeanClassLoaderAware.setBeanClassLoader---
---BeanFactoryAware.setBeanFactory---
BeanPostProcessor.postProcessBeforeInitialization
---@PostConstruct---
```

```
---InitializingBean.afterPropertiesSet---
---init-method---

BeanPostProcessor.postProcessAfterInitialization

Book Name:Mahabharat
---@PreDestroy---
---DisposableBean.destroy---
---destroy-method---
```

BeanNameAware

In bean life cycle org.springframework.beans.factory.BeanNameAware interface is aware of bean name in bean factory. This interface needs to be implemented by the bean and the method setBeanName() of BeanNameAware
should be implemented. BeanNameAware.setBeanName() is called just after the dependency injection is completed. Find the sample example. Book.java

```
package com.concretepage;
import org.springframework.beans.factory.BeanNameAware;
public class Book implements BeanNameAware {
    private String bookName;
    @Override
    public void setBeanName(String name) {
        System.out.println("Bean Name:" + name);
    }
    public String getBookName() {
        return bookName;
    }
    public void setBookName(String bookName) {
        this.bookName = bookName;
    }
}
```

AppConfig.java

```
package com.concretepage;
import org.springframework.context.annotation.Bean;
import org.springframework.context.annotation.Configuration;
@Configuration
public class AppConfig {
         @Bean(name = "myBook")
         public Book getBean() {
               Book book = new Book();
                book.setBookName("Mahabharat");
                return book;
          }
}
```

SpringDemo.java

```
package com.concretepage;
import org.springframework.context.annotation.AnnotationConfigApplicationContext;
public class SpringDemo {
   public static void main(String[] args) {
        AnnotationConfigApplicationContext ctx = new AnnotationConfigApplicationContext();
        ctx.register(AppConfig.class);
        ctx.refresh();
        Book book = ctx.getBean(Book.class);
```

```
System.out.println("Book Name:"+ book.getBookName());
    ctx.close();
}
```

Output

```
Bean Name:myBook
Book Name:Mahabharat
```

BeanFactoryAware

In bean life cycle org.springframework.beans.factory.BeanFactoryAware interface is implemented by beans when it wants to aware of its owning BeanFactory. We need to override setBeanFactory() method. This method is called just after the dependency injection is completed. Using this method we can change the bean properties value. Find the example.

Book.java

```
package com.concretepage:
import org.springframework.beans.BeansException;
import org.springframework.beans.factory.BeanFactory;
import org.springframework.beans.factory.BeanFactoryAware;
public class Book implements BeanFactoryAware {
        private String bookName;
        public String getBookName() {
                return bookName;
        public void setBookName(String bookName) {
                this.bookName = bookName;
        @Override
        public void setBeanFactory(BeanFactory beanFactory) throws BeansException {
                Book b = beanFactory.getBean(Book.class);
                b.setBookName(getBookName()+"-Updated");
        }
}
```

Output

```
Book Name:Mahabharat-Updated
```

BeanPostProcessor

org.springframework.beans.factory.config.BeanPostProcessor interface is used for custom modification of newly created bean properties. To use BeanPostProcessor we need to create a class and override its two method postProcessBeforeInitialization() and postProcessAfterInitialization(). In bean life cycle BeanPostProcessor is called before and after initialization callbacks such as InitializingBean.afterPropertiesSet(), @PostConstruct and Init-method. Here in our example we will use InitializingBean.afterPropertiesSet() and this will be called between postProcessBeforeInitialization() and postProcessAfterInitialization() methods of BeanPostProcessor.

MyBeanPostProcessor.java

Book.java

```
package com.concretepage;
import org.springframework.beans.factory.InitializingBean;
public class Book implements InitializingBean {
    private String bookName;
    public String getBookName() {
        return bookName;
    }
    public void setBookName(String bookName) {
        this.bookName = bookName;
        System.out.println("---Inside setBookName---");
    }
    @Override
    public void afterPropertiesSet() throws Exception {
        System.out.println("---afterPropertiesSet---");
        bookName = bookName + "-Hello";
    }
}
```

AppConfig.java

```
package com.concretepage;
import org.springframework.context.annotation.Bean;
import org.springframework.context.annotation.ComponentScan;
import org.springframework.context.annotation.Configuration;
@Configuration
@ComponentScan(basePackages="com.concretepage")
public class AppConfig {
     @Bean(name = "myBook")
     public Book getBean() {
          Book book = new Book();
          book.setBookName("Mahabharat");
          return book;
     }
}
```

Output

```
---Inside setBookName---

postProcessBeforeInitialization: Bean Name- myBook
---Inside setBookName---
---afterPropertiesSet---

postProcessAfterInitialization: Bean Name- myBook
---Inside setBookName---

Book Name:Mahabharat-Before-Hello-After
```

@PostConstruct and @PreDestroy

Here we will discuss the role of JSR-250 <code>@PostConstruct</code> and <code>@PreDestroy</code> annotation in spring bean life cycle. Spring recommends these annotations to use as initialization and destruction callbacks. <code>@PostConstruct</code> annotated method executes just after dependency injection is completed to perform any initialization. It is customary to specify name as <code>init()</code>. <code>@PreDestroy</code> annotated method executes before the bean is being removed from spring container. It is commonly used to release resources held by bean. It is customary to specify name as <code>destroy()</code>.

This method is called on calling of close() method of spring context. Find the sample example.

Book.java

```
package com.concretepage;
import javax.annotation.PostConstruct;
import javax.annotation.PreDestroy;
public class Book {
        private String bookName;
        @PostConstruct
        public void init() {
                System.out.println("inside init()");
        public String getBookName() {
                return bookName;
        public void setBookName(String bookName) {
                this.bookName = bookName;
                System.out.println("---Inside setBookName---");
        @PreDestroy
        public void destroy() {
                System.out.println("inside destroy()");
}
```

Output

```
---Inside setBookName---
inside init()
Book Name:Mahabharat
inside destroy()
```

InitializingBean and DisposableBean

In bean life cycle org.springframework.beans.factory.InitializingBean interface is a initialization callback whose method afterPropertiesSet() executes once the dependency injection is completed. This method is used to check if all properties have been initialized or to perform any custom initialization.

org.springframework.beans.factory.DisposableBean interface is a destruction callback whose method destroy() executes before bean is going to be removed from spring container. This method is used to release resources and is called on calling of close() method of spring context.

Book.java

```
package com.concretepage;
import org.springframework.beans.factory.DisposableBean;
import org.springframework.beans.factory.InitializingBean;
{\tt public\ class\ Book\ implements\ Initializing Bean,\ Disposable Bean\ \{}
        private String bookName;
        @Override
        public void afterPropertiesSet() throws Exception {
                System.out.println("Inside afterPropertiesSet()");
                bookName+= "-Updated";
        public String getBookName() {
                return bookName;
        }
        public void setBookName(String bookName) {
                this.bookName = bookName;
                System.out.println("---Inside setBookName---");
        @Override
        public void destroy() throws Exception {
                System.out.println("Inside dispose()");
}
```

Output

```
---Inside setBookName---
Inside afterPropertiesSet()
Book Name:Mahabharat-Updated
Inside dispose()
```

init-method and destroy-method in XML and initMethod and destroyMethod in

JavaConfig

In spring bean life cycle init-method and destroy-method attributes are used to specify initialization and destruction callbacks custom method respectively in XML configuration. The equivalent attributes in JavaConfig are initMethod and destroyMethod respectively in a Bean annotation. The customary method name for init-method or initMethod is init(). The customary method name for destroy-method or destroyMethod is destroy(). init() is called just after bean properties are set. This method is used to perform any custom initialization or to check if the values are set to the properties. destroy() method is called to release any resources before the spring container removes the bean. destroy() will be called before bean is removed from spring container. This method is called on calling of close() method of spring context. Find the example.

Book.java

AppConfig.java

```
package com.concretepage;
import org.springframework.context.annotation.Bean;
import org.springframework.context.annotation.Configuration;
@Configuration
public class AppConfig {
         @Bean(name = "myBook", initMethod="init", destroyMethod="destroy")
         public Book getBean() {
                Book book = new Book();
                      book.setBookName("Mahabharat");
                      return book;
                      }
}
```

In XML configuration init-method and destroy-method attributes are declared as follows.

Output

```
---Inside setBookName---
inside init()
Book Name:Mahabharat
inside destroy()
```

Now I am done. Happy spring learning!