```
printable/sistema.s
                     Sun Sep 22 23:58:52 2019
# [...]
# EXTENSION 2019-06-12
   # The interrupt 3 IDT gate DPL must be redifed to User Level in order for
   # the User module processes to call the int3 instruction.
   #-----
   carica_gate 3 breakpoint LIV_UTENTE
# EXTENSION 2019-06-12
# [...]
# EXTENSION 2019-06-12
   # initialize IDT gate for the TIPO_B (breakpoint() primitive) interrupt
   carica_gate TIPO_B a_breakpoint LIV_UTENTE
# EXTENSION 2019-06-12
# [...]
# SOLUTION 2019-06-12
#------
# When the breakpoint() primitive is called, if everything goes well the calling
# process is placed in the system global breakpoint descriptor queue. Otherwise,
# in case of error, the calling process is aborted. In either case the state
# of the current process has to be saved and the state of a new process must be
# loaded.
#-----
a_breakpoint:
   .cfi_startproc
   .cfi_def_cfa_offset 40
   .cfi_offset rip, -40
   .cfi_offset rsp, -16
   call salva_stato
                           # save current process state
                          # call C++ implementation
   call c_breakpoint
                          # load new process state
   call carica_stato
                           # return from interrupt
   iretq
   .cfi_endproc
# SOLUTION 2019-06-12
# [...]
# Interrupt 3 - Breakpoint Exception handler
# The breakpoint exception handler must be redefined in order for the user
# process which called the breakpoint() primitive to be rescheduled. When the
# breakpoint exception is handled, if the breakpoint was inserted by the
# breakpoint() primitive both processes must be place in the system ready
# processes queue and a new process must be scheduled. If it is a breakpoint
# exception not related to the breakpoint() primitive, the calling process
# must be aborted a new one must be scheduled. In either case the current
# process state must be saved and a new process state must be loaded.
#-----
breakpoint:
   .cfi_startproc
   .cfi_def_cfa_offset 40
   .cfi_offset rip, -40
   .cfi_offset rsp, -16
   call salva_stato
# SOLUTION 2019-06-12
                               # interrupt type
   movq $3, %rdi
   movq $0, %rsi
                               # error type
   movq %rsp, %rdx
                               # address contained in %rsp
```

[...]