# **Fault-tolerant quantum memory**

#### Path to fault-tolerant quantum computation based on stabilizer codes

- 1) Fault-tolerant error correction
- 2) Logical Clifford + classical operations
  - -- If a self-dual CSS code is used, these can be implemented transversally
  - -- With other codes, the implementation is more complex J
- 3) Add some non-Clifford gates to achieve universality
  - -- Use "magic" ancillas, e.g.  $\frac{1}{\sqrt{2}} (|0\rangle + e^{i\pi/4} |1\rangle)$
  - -- Other methods

# Alternative paths

- -- Non-Abelian anyons
- -- Continuous variables codes

This lecture is focused on tasks 1 and 2 assuming sparse faults (at most one per gadget and not in adjacent gadgets). To deal with faults occurring at a constant rate and to prove the threshold theorem, one can use either surface codes or concatenated codes. In the later case, the two tasks are interdependent.

# Elementary physical operations and their logical counterparts

0) Idling or	leakage	cleanu
o, raining or	icanage	olouliu

Physical gubits can be out of the computational subspace (in states 12) 13,...). We include an elementary operation that replaces any leaked state by 10> or 11> but does not alter any superposition of the latter.



(fault-tolerant error correction circuit)

At the logical level, "leaked" (or uncorrectable) states are the result of bad errors. They have to be considered if one wants to add another error correction layer on top of an existing one.



The circuit Enc can be realized as the encoding for the trivial code,  $|\S\rangle \mapsto |0^{k-1}\rangle \otimes |\S\rangle$ followed by a sequence of Clifford gates

2) Measurements in the  $|0\rangle$ ,  $|1\rangle$  basis

3) Classically controlled Clifford gates

Fault-tolerant realization: Use the error-correcting circuit for the code  $\mathcal{M}_{\mathbf{p}}$  obtained from  $\mathcal{M}$  by adding  $Z_{i}$  as an extra stabilizer operator.

The eigenvalue of  $Z_{L}$  can be measured as part of


the syndrome for  $\mathcal{M}_{\lambda}$ .

4) Operations with classical bits (assumed to be absolutely reliable)

# Faults in a unitary gate ${\cal U}$

A general fault involves interaction of the qubits with the environment

Actual gate: 
$$\widetilde{V} \approx U \otimes V_0$$
, unitary acting on the qubits unitary acting on the environment



Pauli

In the simplest case, faults are incoherent (i.e. the corresponding operators  $Y_i$  leave the environment in mutually orthogonal states) and occur with total probability  $P = \sum_{i \neq 0} \|Y_i\|^2 = O(\delta^2)$ 

In general, the total error is quantified by the operator norm:  $\|\widetilde{\mathcal{V}} - \mathcal{V} \otimes Y_{\mathfrak{d}}\| \leq \sum_{j \neq 0} \|Y_{j}\| = O(\delta)$ 

The second case is worse due to the possibility of quantum interference between a fault and faultless operation:


**Mitigation of error interference** (in the case where *U* is a Clifford gate)

Choose a Pauli operator 
$$P$$
 at random. Implement  $U$  as a product of three gates:  $P \cdot U \cdot (V^{-1}P \cup V)$ 

The error  $E_{i}$  in the <u>middle *U*</u> becomes  $P E_{i} P$  and averages to 0 because *P* is random (This trick is commonly used in NMR to cancel unwanted interactions between nuclear spins.)

# Fault patterns in a gadget (i.e. a circuit operating on a code blocks)

We decompose each physical gate  $\widetilde{\mathcal{V}}_{\mathbf{k}}$  into the "correct" term  $\mathcal{V}_{\mathbf{k}}^{\otimes \mathbf{Y}_{\mathbf{k},\mathbf{0}}}$  and fault terms  $\sum_{j\neq 0} \mathcal{E}_{\mathbf{k},j} \mathcal{V}_{\mathbf{k}} \otimes \mathcal{Y}_{\mathbf{k},j}$ 



The location of fault terms define a *fault pattern*. Fault patterns are subdivided into "admissible" and "bad". For example, we may call a fault pattern admissible if it contains at most one fault.

$$\widetilde{U} = \underbrace{\widetilde{U}_{\text{admissible}}} + \widetilde{U}_{\text{bad}}, \qquad \|\widetilde{U}_{\text{bad}}\| \leq O(n \delta)$$

should represent a logical gate W in a pair of subsystem codes. (A *subsystem code* is a combination of a usual code and a choice of admissible errors that may be left uncorrected.)

# Subsystem encoding (recap)

$$\widetilde{V}: \mathcal{L} \otimes \mathcal{E}' \to \mathcal{N}$$

reduced error space:  $\xi' = \xi/\xi_o$ , where  $\xi_o$  is the space of errors annihilating all code vectors

the usual code

$$\bigvee \left( \left| \bigvee \right\rangle \otimes \left| E' \right\rangle \right) = E \bigvee \left| \bigvee \right\rangle$$
logical reduced a corresponding error operator

encodina for

# Realization of logical gates using subsystem encodings

Logical gate:  $W: \mathcal{L}_{1} \longrightarrow \mathcal{L}_{2}$ 

Subsystem encodings: 
$$\widetilde{V}_1: \mathcal{L}_1 \otimes \mathcal{E}_1^l \to \mathcal{N}_1$$
,  $\widetilde{V}_2: \mathcal{L}_2 \otimes \mathcal{E}_2^l \to \mathcal{N}_2$ , input output  $\widetilde{V}_2: \mathcal{L}_2 \otimes \mathcal{E}_2^l \to \mathcal{N}_2$  output  $\widetilde{V}_3$  admissible:  $\widetilde{V}_4 \otimes \widetilde{V}_4 \to \mathcal{N}_2 \otimes \widetilde{V}_3 \to \widetilde{V}_4 \otimes \widetilde{V}_4$  admissible  $\widetilde{V}_4 \otimes \widetilde{V}_4 \to \mathcal{N}_2 \otimes \widetilde{V}_3 \to \widetilde{V}_4 \otimes \widetilde{V}_4$ 

(Part of) the physical operator: 
$$\widetilde{\mathcal{V}}_{\text{admissible}}$$
:  $\mathcal{N}_{1} \otimes \mathcal{F}_{1} \longrightarrow \mathcal{N}_{2} \otimes \mathcal{F}_{2}$ ,  $\widetilde{\mathcal{V}}_{1} \otimes \mathcal{F}_{2} \longrightarrow \mathcal{N}_{2} \otimes \mathcal{F}_{2}$ ,

The realization condition

environment before and after (sum over combinations)

$$\vec{f} : \mathcal{E}_{1} \otimes \mathcal{F}_{1} \to \mathcal{E}_{2} \otimes \mathcal{F}_{2} \quad \text{(not necessarily unitary) that makes this diagram commute:}$$

$$\mathcal{N}_{1} \otimes \mathcal{F}_{1} \xrightarrow{\widehat{V}_{\text{admissible}}} \mathcal{N}_{2} \otimes \mathcal{F}_{2}$$

$$\uparrow_{\widehat{V}_{1} \otimes \widehat{J}_{2}}$$

environment before and after

(sum over combinations of error terms)

The previous formalism can be extended to measurements. However, we will treat them less rigorously...

### Fault-tolerant error correction (basic scheme)

We use stabilizer code  $\mathcal{M}$  of type [[n, 1]] that protects from one error.

In certain cases, one residual error is allowed.

<u>Usual encoding</u> (no residual errors):  $V: \mathcal{B} \to \mathcal{B}^{en}$ 

Subsystem encoding (up to 1 residual error):  $\widetilde{V}: \mathcal{B} \otimes \mathcal{E} \to \mathcal{B}$ , where  $\mathcal{E} = \mathcal{E}(h, 1)$ 

At most one fault in the error correction circuit is allowed

#### Requirements for the EC circuit

If there are no faults:


A single error is corrected, i.e. the circuit realizes the identity operator from encoding V to encoding V. (Since V is a special case of  $\widetilde{V}$ , the circuit will also accept a qubit encoded by V.

In general (assuming up to 1 fault):

A single error may be introduced, i.e. the circuit realizes the identity operator from V to  $\widetilde{V}$ .

#### How it works

If we run the EC circuit multiple times and there is at most one fault in any pair of adjacent runs, then the encoded qubit remains intact.



# Problem with syndrome measurement (recap)

Consider the eigenvalue measurement for

$$S = P_1 \cdots P_m$$

$$e.v.(S) = (-1)^{M}$$

 $P_1$   $P_2$   $P_3$ 

A fault in the controlled  $P_2$  has multiple effects:

- -- This code qubit is affected directly
- -- An X error in the ancilla <u>propagates</u>, effecting the operator  $P_3$   $P_4$
- -- A Z error in the ancilla does not propagate but results in the incorrect measurement of M

#### **Comments**

- -- An incorrectly measured  $\mu$  can be fixed by repeated measurements
- -- Errors in the code qubits may be considered up to the stabilizer S. For example,

measurement in the H>, H> basis

$$P_{2}P_{3}P_{4} = P_{1}S = P_{1}$$


 $\Lambda(S)$  (controlled S)

The worst case is when the error hits in the middle, e.g.  $E = P_3 P_4 = P_2 P_2$ 

### Fault-tolerant stabilizer measurement based on a cat ancilla

(used by Shor in his original paper)

To avoid error propagation, the ancillary qubit is replaced by its encoding using the repetition code. An X error can be detected by an additional measurement. If the test fails, the cat ancilla is replaced by a dummy state,  $10^{k}$ 



A fault in this gate propagates, but is then stopped

If there is at most 1 fault, no more than 1 code qubit is affected. But the measurement result may still be incorrect.

## **Fixing measurement errors**

Since all syndrome bits are used, we must ensure the consistency of the whole syndrome.

## The simplest procedure

Measure the syndrome twice, get two vectors  $M^{\binom{1}{2}}$ ,  $M^{\binom{2}{2}}$ . If  $M^{\binom{2}{2}}$ , infer and correct the error. Otherwise stop.

If  $\mu^{(i)} \neq \mu^{(2)}$ , there must be a fault in the current circuit, and therefore, we are not required to correct any pre-existing errors.

### A more advanced procedure


Measure the whole syndrome 3 times, and choose a consistent result:

If 
$$M^{(1)} = M^{(2)}$$
 use  $M^{(1)}$ , otherwise use  $M^{(3)}$ 

Possible outcomes by fault location: 
$$(M^{(2)}, M^{(2)} = M^{(3)}), (M^{(1)}, M^{(2)}, M^{(3)}), (M^{(1)} = M^{(2)}, M^{(2)})$$


# Fault-tolerant error correction circuit based on encoded $|0\rangle$ and $|+\rangle$ ancillas

(Due to Steane; works for CSS codes)



#### **Z stabilizer measurement** (= X error detection): general idea


If we perform a logical CNOT like this,



then the logical state is unchanged, but any X errors in the physical qubits are propagated from the first code block (representing the logical qubit) to the second block (a  $|+\rangle$  ancilla), where they can be measured <u>destructively</u>, by measuring every qubit.

#### Problem and its conceptual solution

Also, Z errors propagate from the (+) ancilla to the code qubits. If there was a fault during the preparation of the ancilla, there may be many such errors! But we can detect them before too late.



# Destructive measurement of X or Z errors in a + ancilla

Let the code stabilizers be 
$$S_{i}^{(2)} = G^{(2)}(f_{i}^{(2)}), \qquad S_{k}^{(x)} = G^{(x)}(f_{k}^{(x)})$$

The state  $|+\rangle$  is determined by those stabilizers together with  $\chi = 6^{-\alpha} (h^{(\alpha)})$ .

$$\widetilde{D}_{z} = D_{z} = \text{linear span } \left\{ f_{j}^{(z)} \right\}, \qquad \widetilde{D}_{x} = D_{z}^{\perp} = \text{linear span } \left\{ f_{j}^{(x)}, h^{(x)} \right\}$$

To detect X errors (up to  $\widetilde{D}_x$ ) and find the  $\widetilde{D}_z$  syndrome:

Measure each qubit in the  $|0\rangle$ ,  $|1\rangle$  basis. Let the outcome be  $g^{(x)}$ .


Then the Z-syndrome is given by  $\mathcal{M}_{j} = \left(g^{(x)}, f^{(z)}\right)$ 

**To detect Z errors** (up to  $\widetilde{D}_{z}$ ) and find the  $\widetilde{D}_{r}$  syndrome:

Measure each qubit in the  $+ \ / -$  basis. Let the outcome be  $g^{(z)}$ .

Then the Z-syndrome is given by  $M_{j} = (g^{(z)}, f^{(x)}_{j})$  and  $M_{j} = (g^{(z)}, h^{(x)}_{j})$ .

#### Z stabilizer measurement: schematic



#### **Detailed circuit**

