# Lecture 04 Floating Point

CS213 – Intro to Computer Systems Branden Ghena – Winter 2022

Slides adapted from:

St-Amour, Hardavellas, Bustamente (Northwestern), Bryant, O'Hallaron (CMU), Garcia, Weaver (UC Berkeley)

## Regarding in-person classes returning

- As currently scheduled, we'll be back in person on Tuesday
  - Tech, Ryan Auditorium
- Rationale from the University is that classrooms are safe due to:
  - Vaccination mandate
  - Mask mandate
  - Testing strategy
- CS213 is going to roll with whatever we've got to do
  - · We'll do our best to make sure you have an environment for learning
  - Definitely need buy-in from you all too
    - Wear masks, Don't come in when you're sick, Support your classmates

#### Administrivia

- Homework 1 due today! (11:59 pm Central)
  - Submit on Gradescope
  - About half of the class has submitted so far

Data Lab due next week Thursday

Homework 2 and Bomb Lab next week Thursday

# Today's Goals

• Explore representing real (decimal) numbers with binary

Understand IEEE754 encoding

• Discuss encoding impacts on floating-point arithmetic

#### **Outline**

Fractional Binary Numbers

Representing Floating Point

Smaller Floating Point


Floating Point Arithmetic

## Floating point numbers

- In decimal:
  - 123450<sub>10</sub>
  - 123.450<sub>10</sub>
  - 1.23450<sub>10</sub>
- We can use this same system in binary as well:
  - 1010110<sub>2</sub> (86<sub>10</sub>)
  - $1010.110_2$   $(10.75_{10} = \frac{86}{2^3})$
  - $1.010110_2$   $(1.34375_{10} = \frac{86}{26})$

## Fractional Binary Numbers

- Representation
  - Bits to right of "binary point" represent fractional powers of 2
  - Represents rational number:



# Fractional Binary Number Examples

• 
$$5+3/4 = 0b101.11$$
 Note:

This the number 3!

• 
$$2+7/8 = 0b10.\overline{111}$$
 This is the number 7!

• 
$$63/64 = 0b0.111111$$
 This is the number  $63!$ 

#### Real numbers are possible in binary

Some problems remain:

- 1. Computers are finite, but real numbers are not
  - Need to choose how many bits to use
  - Many decimal numbers would take infinite binary bits to represent perfectly
    - $3.14_{10} = 11.0010001111010111_2$  (we could keep going)
- 2. We also need to represent where the "binary point" is located
  - We'll use some of our bits to do so
- 3. Should do signed numbers while we're at it

#### **Outline**

Fractional Binary Numbers

Representing Floating Point

Smaller Floating Point

Floating Point Arithmetic

#### **IEEE Floating Point**

- Floating point representations
  - Encodes rational numbers of the form  $V = m \times 2^e$
  - Base 2 scientific notation!
- IEEE Standard 754 (IEEE floating point)
  - Established in 1985 as uniform standard for floating point arithmetic
    - Before that, many idiosyncratic formats
  - Headed by William Kahan, CS prof. at UC Berkeley (later won Turing Award)
  - Supported by all major CPUs
- Driven by numerical concerns and numerical analysts
  - Nice standards for rounding, overflow, underflow
  - Had to be implementable in fast hardware as well and support many languages

#### Floating Point Representation

#### Numerical form

• 
$$V = (-1)^{S} * M * 2^{E}$$
 Exponent

Sign bit Significand (Mantissa)

- Sign bit S determines whether number is negative or positive
- Significand M normally a fractional value in range [1.0,2.0) or [0.0,1.0)
  - Called mantissa or significand
- Exponent *E* weights value by power of two

#### Encoding

- MSb is sign bit (can still look at most-significant bit alone to determine sign!)
- exp field encodes E, k-bits (note: "encodes E"!= "is E")
- frac field encodes M, *n*-bits


s	exp	frac

## Floating Point Precision

- Sizes
  - Single precision: k = 8 exp bits, n= 23 frac bits (32b total). float in C



• Double precision: k = 11 exp bits, n = 52 frac bits (64b total). double in C



## Categories for Encoded Values


- Value encoded three cases, depending on value of exp
  - 1. Normalized, the most common



2. Denormalized (very small values)

s	00000000	frac

3. Special values – infinity and NaN



## Categories for Encoded Values

- Value encoded three cases, depending on value of exp
  - 1. Normalized, the most common

s	≠ 0 && not all 1s	frac
---	-------------------	------

2. Denormalized

s	00000000	frac
"		rrac

3. Special values – infinity and NaN

Infinity	s	11111111	00000000000000000000
NaN	s	11111111	≠∩
INGIN	5	1111111	<del>/</del> 0

#### Normalized Numeric Values

$$V = (-1)^S * M * 2^E$$

- Condition: not a special exponent (all zeros or ones)
- Significand coded with implied leading 1
  - $M = 1.xxx...x_2$  (1+f where  $f = 0.xxx_2$ )
    - xxx...x: bits of frac
- Exponent coded as biased value
  - E = Exp Bias
    - Exp: unsigned value denoted by exp
    - Bias : Bias value =  $2^{k-1}$  1, k is number of exponent bits
      - Single precision (8-bit exp): 127 (Exp: 1...254, E: -126...127)
      - Double precision (11-bit exp): 1023 (Exp: 1...2046, E: -1022...1023)

# Decoding example for normalized floating point (32-bit)

- - exp is not all zeros or all ones => not a special case

- E = exp bias = 131 127 = 4
  - bias =  $2^{k-1}$  -1,  $k=8 \rightarrow 2^{7}$ -1 = 127
- Result =  $(-1)^0 * 1.001_2 * 2^4 = 10.01_2 * 2^3 = 10010_2 = 18$

$$V = (-1)^S * M * 2^E$$
 s exp frac

#### Normalized Encoding Example

#### Value

- float F = 15213.0; // single precision: 8 exp bits, 23 frac bits
- $15213_{10} = 11101101101101_2 = 1.1101101101101_2 \times 2^{13}$

#### Significand

- $M = 1.1101101101101_{2}$
- frac = 11011011011010000000000

pad with 0s *on the right*. (example: 1.5 = 1.500)

#### Exponent

- E = 13
- Bias = 127

•  $\exp = E + Bias = 140 = 10001100_2$ 

More examples in the bonus slides after the end

```
      Floating Point Representation:

      Hex:
      4
      6
      6
      D
      B
      4
      0
      0

      Binary:
      0100
      0110
      0110
      1101
      1011
      0100
      0000
      0000

      exp:
      100
      0110
      0
      0100
      0000
      0000
      0000

      frac:
      110
      1101
      1011
      0100
      0000
      0000
```

## Normalized Numbers: Why These Choices?

- Significand coded with <u>implied leading 1</u>
  - Any non-zero integer will start with a 1 bit somewhere
  - Leading 1 carries no information, so don't need to store it!
  - Can express mantissas between:
    - 1.0 when frac is all 0s
    - 2.0 (nearly) when frac is all 1s
      - Want smaller? Use a smaller exponent!
- Exponent coded as biased value
  - E = Exp Bias
  - Alternative to using two's complement to represent signed integers
  - Reasons are a bit tricky
    - Floating point binary values increase in the same order as unsigned = share comparisons!
    - Bias provides a more useful range (when considering denormalized)

## Question + Break

- - exp is not 0...0 or 1...1 => not a special case
- M =
- E = exp bias =
  - bias =  $2^{k-1}$  -1,  $k=8 \rightarrow 2^{7}$ -1 = 127

$$V = (-1)^S * M * 2^E$$

ß	exp	frac

#### Question + Break

- - exp is not 0...0 or 1...1 => not a special case
- $E = \exp bias = 127 127 = 0$ 
  - bias =  $2^{k-1}$  -1, k=8 ->  $2^{7}$ -1 = 127
- Result =  $(-1)^0 * 1.0_2 * 2^0 = 1$

$$V = (-1)^s * M * 2^E$$

s exp frac

#### Live Practice

- - S = 1 (negative number)

  - Exp = 11100100 = 128+64+32+4 = 228
    - Bias =  $2^{k-1}-1 = 128-1 = 127$
    - E = Exp Bias = 228 127 = 101
  - Value =  $(-1)^1 * 1.0011001_2 * 2^{101} = -(1 + 1/8 + 1/16 + 1/128) * 2^{101}$

$$V = (-1)^{S} * M * 2^{E}$$

## Categories for Encoded Values

- Value encoded three cases, depending on value of exp
  - 1. Normalized, the most common

s   \neq 0 && not all 1s   frac
---------------------------------

#### 2. Denormalized


s	0000000	frac
---	---------	------

3. Special values – infinity and NaN


Infinity	s	11111111	0000000000000000000
NaN	s	11111111	≠0

# Normalized floating point leaves a gap around zero

Gap is the size of 1.0000 \* 2<sup>Min Exponent</sup> (due to leading 1 bit)




- Solution: fill in numbers between 0 and 1 \* 2<sup>Min Exponent</sup>
  - Using same spacing as the previous range, in the form **0**.XXXXX



#### **Denormalized Values**

$$V = (-1)^S * M * 2^E$$

- Purpose: gracefully represent numbers approaching ±0
- Condition:  $exp = 000...0_2$



- Value
  - Exponent value E = 1 Bias
    - Note: not simply E = 0 Bias as it would be if we followed the previous rules
    - This means we're re-using the spacing from smallest normalized numbers
  - Significand value  $M = \mathbf{0}.xxx...x_2 (0.f)$ 
    - xxx...x: bits of frac. Leading 0 instead of leading 1
- Cases
  - $\exp = 000...0$ , frac = 000...0 = > Represents value 0
    - Note that we have distinct values +0 and -0
  - exp = 000...0,  $frac \neq 000...0 => Numbers very close to 0.0$

## Categories for Encoded Values


- Value encoded three cases, depending on value of exp
  - 1. Normalized, the most common

s   \neq 0 && not all 1s   frac
---------------------------------

#### 2. Denormalized

s	00000000	frac
---	----------	------

#### 3. Special values – infinity and NaN




#### Special Values

- Purpose: represent quantities that  $(-1)^{s} * M * 2^{E}$  cannot
- Condition:  $exp = 111...1_2$
- Cases
  - $\exp = 111...1_2$ , frac =  $000...0_2$ 
    - Represents value ∞ (infinity)
    - Both positive and negative infinity (sign bit to tell apart)
    - Operation that overflows: nicer mathematical behavior than modulo!
    - E.g.,  $1.0/0.0 = -1.0/-0.0 = +\infty$ ,  $-1.0/0.0 = -\infty$
  - $\exp = 111...1_2$ , frac  $\neq 000...0_2$ 
    - Not-a-Number (NaN)
    - Represents case when no numeric value can be determined
      - Fraction could be used to distinguish sources (rarely used in practice)
    - E.g.,  $\sqrt{-1}$ ,  $\infty$   $\infty$ ,  $\infty$  \* 0

#### Floating Point in C

- C guarantees two levels
  - float single precision
  - double double precision
- Conversions
  - int → float
    - maybe rounded
    - less bits for actual value (32 → 23)
  - int Or float → double
    - exact value preserved
    - double has greater range and higher precision (52 bits for frac)
  - double → float
    - may overflow, underflow (too small to represent), or be rounded (IEEE 754)
    - C99 standard says undefined if value out of range
  - double Or float → int
    - rounded toward zero (-1.999  $\rightarrow$  -1)
    - C99 standard says undefined if value out of range

# Break + Summary of FP Real Number Encodings



$$V = (-1)^{s} * M * 2^{E}$$

	Normalized	Denormalized
S	0/1 means +/-	0/1 means +/-
exp	$exp \neq 0000_2$ and $exp \neq 1111_2$	$exp = 0000_2$
frac	$X_1X_2X_3X_j$	$X_1X_2X_3X_j$
Bias=	$2^{(k-1)} - 1$ , for $k$ exponent bits	$2^{(k-1)} - 1$ , for $k$ exponent bits
E=	exp – Bias	1 - Bias
M=	1. $x_1 x_2 x_3 x_j$ a.k.a. 1.frac	0. $x_1 x_2 x_3 x_j$ a.k.a. 0.frac
V=	$(-1)^s \times (1.frac) \times 2^{(exp - Bias)}$	$(-1)^s \times (0.\text{frac}) \times 2^{(1-\text{Bias})}$

#### **Outline**

Fractional Binary Numbers

Representing Floating Point

Smaller Floating Point

Floating Point Arithmetic

#### Floating point examples


- We'll often do floating point in custom bit widths
  - Rather than 32-bit (float) or 64-bit (double)

#### Reasons

- 1. They are just too many bits to write out and think about
- 2. Make sure you understand the concepts of floating point
  - Smaller versions still demonstrate concepts! (e.g., 8-bit)

## Example: Tiny Floating Point

- 8-bit Floating Point Representation
  - Sign bit is in the most significant bit.
  - Next four (k) bits are exp, with a bias of 7  $(2^{k-1}-1)$
  - Last three (n) bits are frac
- Same general form as IEEE 754 format
  - normalized, denormalized numbers
  - representation of 0, NaN, infinity




Sidebar: increasingly useful for Machine Learning use!

Models often don't need
 32-bits of precision

## Exponents for 8-bit tiny floats

Bias =  $2^{4-1} - 1 = 7$  (4-bit exp)



## Dynamic Range of 8-bit tiny float

```
0 0000 000
0 0000 001
0 0000 010
0 0000 110
0 0000 111
0 0001 000
0 0001 001
0 0110 110
0 0110 111
0 0111 000
0 0111 001
0 0111 010
0 1110 110
0 1110 111
0 1111 000
0 1111 001
0 1111 111
```

#### Dynamic Range of 8-bit tiny float

```
s exp frac
0 0000 000
0 0000 001
0 0000 010
0 0000 110
0 0000 111
0 0001 000
0 0001 001
0 0110 110
0 0110 111
0 0111 000
0 0111 001
0 0111 010
0 1110 110
0 1110 111
0 1111 000
0 1111 001
0 1111 111
```

# Dynamic Range of 8-bit tiny float

```
Bias = 7
                    s exp frac
V = (-1)^{s}
                    0 0000 000
   × (0.frac)
                    0 0000 001
   \times 2^{(1 - \text{Bias})}
                    0 0000 010
Denormalized
                    0 0000 110
numbers
                    0 0000 111
                    0 0001 000
                    0 0001 001
Normalized
numbers
                    0 0110 110
V = (-1)^{s}
                    0 0110 111
   x (1.frac) 0 0111 000
                    0 0111 001
   x 2(exp – Bias)
                    0 0111 010
                    0 1110 110
         0 1110 111
                    0 1111 000
Special
                    0 1111 001
values
                    0 1111 111
```

# Dynamic Range of 8-bit tiny float


Bias = 7	s exp frac	E	Value
V= $(-1)^s$ $\times (0.\text{frac})$ $\times 2^{(1 - \text{Bias})}$	0 0000 000 0 0000 001 0 0000 010	-6 -6 -6	0 $1/8*1/64(2^{-6}) = 1/512$ $2/8*1/64 = 2/512$
Denormalized numbers		-6	
Normalized numbers	0 0001 000 0 0001 001	-6	8/8*1/64 = 8/512 9/8*1/64 = 9/512
V= (−1) <sup>s</sup>	0 0110 110 0 0110 111 0 0111 000	-1	14/8*1/2 = 14/16 15/8*1/2 = 15/16 8/8*1 = 1
× 2(exp – Bias)	0 0111 001 0 0111 010	0	9/8*1 = 9/8 10/8*1 = 10/8
***************************************	0 1110 110 0 1110 111	7 7	14/8*128 = 224 15/8*128 = 240
Special values	0 1111 000 0 1111 001	n/a n/a	inf NaN
	0 1111 111	n/a	NaN

# Dynamic Range of 8-bit tiny float

Bias = 7	s exp	frac	E	Value	<b>Notes of Interest</b>
$V= (-1)^{s}$ $\times (0.frac)$ $\times 2^{(1-Bias)}$	0 0000 0 0000 0 0000	001	-6 -6 -6	0 $1/8*1/64(2^{-6}) = 1/512$ $2/8*1/64 = 2/512$	closest to zero
Denormalized numbers	0 0000 0 0000	111	-6 -6	6/8*1/64 = 6/512 7/8*1/64 = 7/512	largest denorm
Normalized numbers	0 0001 0 0001		-6 -6	8/8*1/64 = 8/512 9/8*1/64 = 9/512	smallest norm > 0
V= (-1) <sup>s</sup>	0 0110 0 0110	111	-1 -1	14/8*1/2 = 14/16 15/8*1/2 = 15/16	closest to 1 below
× (1.frac) × 2 <sup>(exp – Bias)</sup>	0 0111 0 0111 0 0111	001	0 0 0	8/8*1 = 1 9/8*1 = 9/8 10/8*1 = 10/8	closest to 1 above
	 0 1110 0 1110	_	7 7	14/8*128 = 224 15/8*128 = 240	largest norm
Special values	0 1111 0 1111  0 1111	000 001	n/a n/a n/a	inf NaN NaN	
	0 1111		11/ a	11011	


#### Distribution of Values

- 6-bit IEEE-like format
  - exp = 3 exponent bits
  - frac = 2 fraction bits
  - Bias is  $3(2^{3-1}-1)$
- Notice how the distribution gets denser toward zero.




## Distribution of Values (Close-up View)

- 6-bit IEEE-like format
  - exp = 3 exponent bits
  - frac = 2 fraction bits
  - Bias is  $3(2^{3-1}-1)$



- Smooth transition between normalized and de-normalized numbers due to definition E = 1 - Bias for denormalized values
  - Zeros are denormalized numbers too! (+0 and -0)



### **Outline**

Fractional Binary Numbers

Representing Floating Point

Smaller Floating Point

Floating Point Arithmetic

### Floating Point Operations

Conceptual view

```
x +<sub>float</sub> y = Fit(x +<sub>math</sub> y)
x *<sub>float</sub> y = Fit(x *<sub>math</sub> y)
```

- First compute exact, mathematical result
  - Compute the numerical value of the operands
  - Do the operation as in grade school arithmetic
- Then make it fit into desired precision
  - **Step 1**: Determine frac, exp
    - Frac must be of the form 1.xxxx (0.xxx if denormalized)
    - Change exp if needed to get frac to that form (e.g., result is 101.xxx)
  - Step 2: Possibly overflow if exponent too is large
    - Unlike integer overflow, result is mathematically reasonable: infinity
  - Step 3: Possibly round to fit into frac if we have too many mantissa bits

### Rounding

- Default rounding mode for IEEE floating point is Round-to-even
  - Other methods are statistically biased (round up, round down, round-to-zero)
    - Sum of set of positive numbers will consistently be over- or under- estimated
  - Round to nearest number
    - If exactly in between, round to nearest even number
- Round-to-even example
  - Illustrated with rounding of money (round to whole number)

Rounded \$1 \$2

### Rounding

- Default rounding mode for IEEE floating point is Round-to-even
  - Other methods are statistically biased (round up, round down, round-to-zero)
    - Sum of set of positive numbers will consistently be over- or under- estimated
  - Round to nearest number
    - If exactly in between, round to nearest even number
- Round-to-even example
  - Illustrated with rounding of money

### Rounding

- Default rounding mode for IEEE floating point is Round-to-even
  - Other methods are statistically biased (round up, round down, round-to-zero)
    - Sum of set of positive numbers will consistently be over- or under- estimated
  - Round to nearest number
    - If exactly in between, round to nearest even number
- Round-to-even example
  - Illustrated with rounding of money

#### Closer Look at Round-to-even

- Rounding to other decimal places than the decimal point
  - When exactly halfway between two possible values
    - Round so that least significant digit is even
  - E.g., round to nearest hundredth (i.e., 2 decimal digits in fractional part)
    - 1.23 **49999** => 1.23 (Less than half way)
    - 1.2350001 => 1.24 (Greater than half way)
    - 1.23<u>**50000**</u> => 1.24 (Half way—round to even)
    - 1.24<u>**50000**</u> => 1.24 (Half way—round to even)

### Rounding Binary Numbers

- Binary fractional numbers
  - Are "even" when least significant bit is 0
  - Are half-way when bits to right of rounding position =  $100...0_2$  General form  $XX...X.YY...Y100...0_2$  last Y is the position to which we want to round

### Examples

Round to nearest 1/4 (2 bits right of binary point)

Value	Binary	Rounded	Action	Rounded Value
2+3/32	10.00 <u><b>011</b></u> 2	10.00 <sub>2</sub>	(<1/2—down)	2
2+3/16	10.00 <u><b>110</b></u> 2	$10.01_{2}^{-}$	(>1/2—up)	2+1/4
2+3/8	10.01 <u><b>100</b></u> 2	10.10 <sub>2</sub>	(1/2—up to even)	2+1/2
2+5/8	10.10 <u><b>100</b></u> 2	10.10 <sub>2</sub>	(1/2—down to even)	2+1/2
2+7/8	10.11 <u><b>100</b></u> 2	11.00 <sub>2</sub>	(1/2—up to even)	3

### Mathematical Properties of FP Arithmetic

- Mathematical properties of FP Addition
  - Addition is Associative? NO
    - (x + y) + z = x + (y + z)
    - Possibility of overflow and inexactness of rounding
      - (3.14 + 1e10) 1e10 = 0 (rounding)
      - 3.14 + (1e10 1e10) = 3.14
- Mathematical properties of FP Multiplication
  - Multiplication is Associative? NO
    - $(x \times y) \times z = x \times (y \times z)$
    - Possibility of overflow, inexactness of rounding
  - Multiplication distributes over addition? NO
    - $x \times (y + z) = (x \times y) + (x \times z)$
    - Possibility of overflow, inexactness of rounding
- More in bonus slides

## Floating Point Summary

- IEEE Floating point (IEEE 754) has clear mathematical properties
  - But not always the ones you may expect!
- Represents numbers of form  $(-1)^S \times M \times 2^E$
- One can reason about operations independent of implementation
  - As if computed with perfect precision and then rounded
- Not the same as arithmetic on real numbers
  - Violates associativity/distributivity
  - Makes life difficult for compilers & serious numerical applications programmers

### **Outline**

Fractional Binary Numbers

Representing Floating Point

Smaller Floating Point

Floating Point Arithmetic

### **Outline**

- Bonus slides
  - Use these for additional practice
  - And if you're interested in additional topics


## Interesting Numbers for float/double

Description	exp	frac	Numeric Value (single prec., double prec.)
Zero	0000	0000	0.0
Smallest Pos. Denorm.  • Single ~ 1.4 X 10 <sup>-2</sup> • Double ~ 4.9 X 10 <sup>-2</sup>		0001	2-{23,52} X 2-{126,1022}
<ul> <li>Largest Denormalized</li> <li>Single ~ 1.18 X 10</li> <li>Double ~ 2.2 X 10</li> </ul>	-38	1111	$(1.0 - \varepsilon) \times 2^{-\{126,1022\}}$
Smallest Pos. Normalized  • Just slightly larger largest denormalize	than	0000	1.0 X 2 <sup>-{126,1022}</sup>
One	0111	0000	1.0
<ul> <li>Largest Normalized</li> <li>Single ~ 3.4 X 10<sup>38</sup></li> <li>Double ~ 1.8 X 10<sup>3</sup></li> </ul>	3	1111	$(2.0 - \varepsilon) \times 2^{\{127,1023\}}$

### Normalized Encoding Example

- Value
  - float F = 12345.0; // single precision: k=8, n=23
  - $12345_{10} = 11000000111001_2 = 1.1000000111001_2 \times 2^{13}$
- Significand
  - $M = 1.1000000111001_2$
  - frac = 1000000111001*000000000* (drop leading 1, add 10 zeros)
- Exponent
  - E = 13
  - Bias = 127
  - E =  $\exp$  Bias  $\rightarrow$   $\exp$  = E + Bias = 140 = 10001100<sub>2</sub>

### Creating a Floating Point Number



#### Steps

- Is the number within the range  $(-2^{1-Bias}, +2^{1-Bias})$ ?
  - If yes, "denormalize" to have a leading 0
  - otherwise, normalize to have leading 1
- Round to fit within fraction
- Postnormalize to deal with effects of rounding

- QUIZ in next three slides
  - Convert 8-bit unsigned numbers to tiny floating point format

# Step 1: Normalize

S	ехр	frac
1	4-bits	3-bits

### Requirement

- Set binary point so that numbers of form 1.xxxxx
- Adjust all to have leading one
  - Decrement exponent as shift left

Value	Binary	Fraction	Exponent
128	10000000	1.0000000	7
13	00001101	1.1010000	3
17	00010001	1.0001000	4
19	00010011	1.0011000	4
138	10001010	1.0001010	7
63	00111111	1.1111100	5

## Step 2: Rounding

1.BBGRXXX

**Guard bit: LSB of result -**

-

Sticky bit: OR of remaining bits

Round bit: 1st bit removed

- Round up conditions
  - round up if  $\langle$ Guard, Round, Sticky $\rangle$  =  $\langle$ x11 $\rangle$  because  $\rangle$ 0.5
  - round up if  $\langle Guard, Round, Sticky \rangle = \langle 110 \rangle$  as per round to even rules

Value	Fraction	GRS	Incr?	Rounded
128	1.0000000	000	N	1.000
13	<b>1.1010</b> 000	100	N	1.101
17	1.0001000	010	N	1.000
19	1.001 <mark>1</mark> 000	110	Υ	1.010
138	1.0001010	011	Υ	1.001
63	1.111 <mark>1</mark> 100	111	Υ	10.000

### Step 3: Postnormalize

#### Issue

- Rounding may have caused overflow
- Handle by shifting right once & incrementing exponent

Value	Rounded	Ехр	Adjusted	Result
128	1.000	7		128
13	1.101	3		13
17	1.000	4		16
19	1.010	4		20
138	1.001	7		144
63	10.000	5	M=1.000 exp=6	64

### Floating Point Puzzles

- For each of the following C expressions, either:
  - Argue that it is true for all argument values
  - Explain why not true

```
x == (int) (double) x

int x = ...;
float f = ...;
double d = ...;

Assume neither d nor f is NaN

x == (int) (double) x

x == (int) (float) x

d == (double) (float) d

f == (float) (double) f

1.0/2 == 1/2.0

d*d >= 0.0

(f+d)-f == d
```

### Floating Point Puzzles

- For each of the following C expressions, either:
  - Argue that it is true for all argument values
  - Explain why not true

```
int x = ...;
float f = ...;
double d = ...;
```

x == (int) (double) x Yes
x == (int) (float) x No (x = TMax)
d == (double) (float) d No (d = 1e40)
f == (float) (double) f Yes

# Assume neither d nor f is NaN

## Floating-Point Multiplication, Directly

- For cases where you can't work with exact results
  - E.g., when doing it in hardware
- Operands
  - $(-1)^{s1}$  M1  $2^{E1}$  \*  $(-1)^{s2}$  M2  $2^{E2}$
- Exact result
  - (-1)<sup>s</sup> M 2<sup>E</sup>

  - Sign s: s1 ^ s2
    Significand M: M1 \* M2
  - Exponent E: E1 + E2
- Fixing
  - If M ≥ 2, shift M right, increment E
  - If E out of range, overflow
  - Round M to fit frac precision
- Implementation
  - Biggest chore is multiplying significands

```
E1=3 M1=1.11010010
E2=5 M2=1.11001110
E=8 M=11.01001000111111
E=8+1 M=1.101001000111111
     M=1.1010010010
E=9
```

## Floating-Point Addition, Directly

#### Operands


- (-1)<sup>s1</sup> M1 2<sup>E1</sup>
- (-1)<sup>s2</sup> M2 2<sup>E2</sup>
- Assume  $E^1 > E^2$

#### Exact Result

- (-1)<sup>s</sup> M 2<sup>E</sup>
- Sign s, significand M: Result of signed align & add
- Exponent E: E<sup>1</sup>

#### Fixing

- If M ≥ 2, shift M right, increment E
- if M < 1, shift M left k places, decrement E by k
- Overflow if E out of range
- Round M to fit frac precision



## Mathematical Properties of FP Add

- Compare to those of Abelian Group
  - Closed under addition? YES
    - But may generate infinity or NaN
  - Commutative? YES
  - Associative? NO
    - Overflow and inexactness of rounding
      - (3.14+1e10)-1e10=0 (rounding)
      - 3.14+(1e10-1e10)=3.14
  - 0 is additive identity? YES
  - Every element has additive inverse? ALMOST
    - Except for infinities & NaNs
- Monotonicity
  - $a \ge b \Rightarrow a+c \ge b+c$ ? ALMOST
    - Except for NaNs

### Mathematical Properties of FP Multiplication

- Compare to commutative ring
  - Closed under multiplication?
    - But may generate infinity or NaN
  - Multiplication Commutative?
  - Multiplication is Associative?
    - Possibility of overflow, inexactness of rounding
  - 1 is multiplicative identity?YES
  - Multiplication distributes over addition?
    - Possibility of overflow, inexactness of rounding
- Monotonicity
  - $a \ge b \& c \ge 0 \implies a *c \ge b *c$ ? ALMOST
    - Except for NaNs