Copyright © tutorialspoint.com

Each IP class is equipped with its own default subnet mask which bounds that IP class to have prefixed number of Networks and prefixed number of Hosts per network. Classful IP addressing does not provide any flexibility of having less number of Hosts per Network or more Networks per IP Class.

CIDR or **Classless Inter Domain Routing** provides the flexibility of borrowing bits of Host part of the IP address and using them as Network in Network, called Subnet. By using subnetting, one single Class A IP address can be used to have smaller sub-networks which provides better network management capabilities.

Class A Subnets

In Class A, only the first octet is used as Network identifier and rest of three octets are used to be assigned to Hosts *i. e.* 16777214HostsperNetwork. To make more subnet in Class A, bits from Host part are borrowed and the subnet mask is changed accordingly.

For example, if one MSB MostSignificantBit is borrowed from host bits of second octet and added to Network address, it creates two Subnets ($2^{1}=2$) with ($2^{23}-2$) 8388606 Hosts per Subnet.

The Subnet mask is changed accordingly to reflect subnetting. Given below is a list of all possible combination of Class A subnets:

Network Bits	Subnet Mask	Bits Borrowed	Subnets	Hosts/Subnet
8	255.0.0.0	0	1	16777214
9	255.128.0.0	1	2	8388606
10	255.192.0.0	2	4	4194302
11	255.224.0.0	3	8	2097150
12	255.240.0.0	4	16	1048574
13	255.248.0.0	5	32	524286
14	255.252.0.0	6	64	262142
15	255.254.0.0	7	128	131070
16	255.255.0.0	8	256	65534
17	255.255.128.0	9	512	32766
18	255.255.192.0	10	1024	16382
19	255.255.224.0	11	2048	8190
20	255.255.240.0	12	4096	4094
21	255.255.248.0	13	8192	2046
22	255.255.252.0	14	16384	1022
23	255.255.254.0	15	32768	510
24	255.255.255.0	16	65536	254
25	255.255.255.128	17	131072	126
26	255.255.255.192	18	262144	62
27	255.255.255.224	19	524288	30
28	255.255.255.240	20	1048576	14
29	255.255.255.248	21	2097152	6
30	255.255.255.252	22	4194304	2

In case of subnetting too, the very first and last IP address of every subnet is used for Subnet Number and Subnet Broadcast IP address respectively. Because these two IP addresses cannot be assigned to hosts, sub-netting cannot be implemented by using more than 30 bits as Network Bits, which provides less than two hosts per subnet.

Class B Subnets

By default, using Classful Networking, 14 bits are used as Network bits providing (2^{14}) 16384 Networks and (2^{16} -1) 65534 Hosts. Class B IP Addresses can be subnetted the same way as Class A addresses, by borrowing bits from Host bits. Below is given all possible combination of Class B subnetting:

Network Bits	Subnet Mask	Bits Borrowed	Subnets	Hosts/Subnet
16	255.255.0.0	0	0	65534
17	255.255.128.0	1	2	32766
18	255.255.192.0	2	4	16382
19	255.255.224.0	3	8	8190
20	255.255.240.0	4	16	4094
21	255.255.248.0	5	32	2046
22	255.255.252.0	6	64	1022
23	255.255.254.0	7	128	510
24	255.255.255.0	8	256	254
25	255.255.255.128	9	512	126
26	255.255.255.192	10	1024	62
27	255.255.255.224	11	2048	30
28	255.255.255.240	12	4096	14
29	255.255.255.248	13	8192	6
30	255.255.255.252	14	16384	2

Class C Subnets

Class C IP addresses are normally assigned to a very small size network because it can only have 254 hosts in a network. Given below is a list of all possible combination of subnetted Class B IP address:

Network Bits	Subnet Mask	Bits Borrowed	Subnets	Hosts/Subnet
24	255.255.255.0	0	1	254
25	255.255.255.128	1	2	126
26	255.255.255.192	2	4	62
27	255.255.255.224	3	8	30
28	255.255.255.240	4	16	14
29	255.255.255.248	5	32	6
30	255.252	6	64	2

Loading [MathJax]/jax/output/HTML-CSS/jax.js