The pdfcolparcolumns package

Heiko Oberdiek*

2019/12/29 v1.5

Abstract

Since version 1.40 pdfTeX supports several color stacks. This package uses them to fix color problems in package $\sf parcolumns$.

Contents

1	Usage					
	1.1	Option rulebetweencolor	2			
	1.2	Future	2			
2	Imp	plementation	2			
	2.1	Identification	2			
	2.2	Load packages	2			
		0 1	2			
		0 1	3			
			3			
	2.3		3			
	2.4		3			
		2.4.1 Init stacks	3			
		2.4.2 Switch stack	4			
		2.4.3 Set current stack color	4			
3	Installation					
	3.1	Download	6			
	3.2	Bundle installation	6			
	3.3	Package installation	6			
	3.4	Refresh file name databases	7			
	3.5	Some details for the interested	7			
4	Ref	erences	7			
5	His	tory	8			
	[200	7/07/26 v1.0]	8			
			8			
			8			
			8			
			8			
			8			
6	Ind	ex	8			

^{*}Please report any issues at https://github.com/ho-tex/oberdiek/issues

1 Usage

```
\usepackage{pdfcolparcolumns}
```

The package pdfcolparcolumns loads package parcolums [1]. If color stacks are available then the macros of parcolumns are patched to add support for color stacks.

1.1 Option rulebetweencolor

Package pdfcolparcolumns also fixes the color for the rule between columns (if rulebetween is set). Default color is \normalcolor. But this can be changed by using option rulebetweencolor. It takes a color specification as value. If the value is empty, then the default (\normalcolor) is used. Examples:

```
rulebetweencolor=blue,
rulebetweencolor={red},
rulebetweencolor={}, % \normalcolor is used
rulebetweencolor=[rgb]{1,0,.5} % see below
```

If used inside the optional argument of environment parcolumns and the value contains an optional argument, then whole value must be put in curly braces:

```
\begin{parcolumns}[
  rulebetween,
  rulebetweencolor={[rgb]{1,0,.5}},
]{2}
  ...
\end{parcolumns}
```

This option rulebetweencolor can also be set using \setkeys:

\setkeys{parcolumns}{rulebetweencolor=green}

1.2 Future

Currently package parcolumns does not seem to be maintained. Nevertheless if there will be a new version that adds support for color stacks, then this package may become obsolete.

2 Implementation

2.1 Identification

```
1 \( \*\package \)
2 \NeedsTeXFormat{LaTeX2e}
3 \ProvidesPackage{pdfcolparcolumns}%
4 [2019/12/29 v1.5 Color stacks for parcolumns (HO)]%
```

2.2 Load packages

2.2.1 Package parcolumns

Currently package parcolumns does not define options. Thus it is just a precaution that the options of package pdfcolparcolumns are passed to package parcolumns.

```
5 \DeclareOption*{%
6  \PassOptionsToPackage{\CurrentOption}{parcolumns}%
7 }
8 \ProcessOptions\relax
9 \RequirePackage{parcolumns}[2004/11/25]
```

2.2.2 Package pdfcol

```
10 \RequirePackage{pdfcol}[2007/09/09]
11 \ifpdfcolAvailable
12 \else
13 \PackageInfo{pdfcolparcolumns}{%
14 Loading aborted, because color stacks are not available%
15 }%
16 \expandafter\endinput
17 \fi
```

2.2.3 Package infwarerr

18 \RequirePackage{infwarerr}[2007/09/09]

2.3 Color stack macros

\pcpc@MaxStack

Macro $\protect\operatorname{\mathtt{Macro}}$ the highest number of allocated stacks.

19 \global\chardef\pcpc@MaxStack=\z@

\pcpc@InitStacks

Macro \pcpc@InitStacks takes the number of columns as argument and ensures that there are enough color stacks for all columns.

```
20 \def\pcpc@InitStacks#1{%
    \ifnum#1>\pcpc@MaxStack
21
22
      \begingroup
        \count@\pcpc@MaxStack
23
24
        \loop
           \advance\count@\@ne
25
26
           \pdfcolInitStack{pcpc@\the\count@}%
27
        \ifnum#1>\count@
28
        \repeat
        \global\chardef\pcpc@MaxStack=\count@
29
30
      \endgroup
31
    \fi
32 }
33 \def\pcpc@SwitchStack#1{%
```

\pcpc@SwitchStack

```
33 \def\pcpc@SwitchStack#1{%
34 \pdfcolSwitchStack{pcpc@\number#1}%
35 }
```

\pcpc@SetCurrent

```
36 \def\pcpc@SetCurrent#1{%
37 \pdfcolSetCurrent{pcpc@\number#1}%
38 }
```

2.4 Patches

Now the color stack macros are patched into the macros of package parcolumns.

2.4.1 Init stacks

\pcpc@InitStacks should go into the definition of environment parcolumns. \pc@alloccolumns is executed there and nowhere else, thus we hook into it.

```
39 \g@addto@macro\pc@alloccolumns{%
40 \pcpc@InitStacks\pc@columncount
41 }
```

2.4.2 Switch stack

\pcpc@SwitchStack should be called by marco \colchunk@. However it is easier to patch \pc@setcolumnwidth that is executed in \colchunk@ only.

```
42 \g@addto@macro\pc@setcolumnwidth{%
43 \pcpc@SwitchStack\pc@columnctr
44 }
```

2.4.3 Set current stack color

\pcc@SetCurrent is set at the begin of each line. It must be inserted into \pc@placeboxes. Unhappily there is no easy way. Therefore we check and redefine \pc@placeboxes.

```
45 \begingroup
46
    \left( x_{x}\right)
      \global\let\@tempa\relax
47
      \count@\z@
48
      \hb@xt@\linewidth{%
49
        \vfuzz30ex %
50
        \vbadness\@M
51
        \splittopskip\z@skip
52
        \loop
53
54
        \ifnum\count@<\pc@columncount
          \advance\count@\@ne
55
          \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
56
            \hskip\csname pc@column@width@\number\count@\endcsname
57
          \else
58
            \expandafter\setbox\expandafter\@tempboxa\expandafter
59
60
            \vsplit\csname pc@column@\number\count@\endcsname
                to \dp\strutbox
61
            \vbox{%
62
              \unvbox\@tempboxa
63
            }%
64
65
          \fi
          \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
66
67
            \global\let\@tempa\pc@placeboxes
68
69
          \ifnum\count@<\pc@columncount
70
            \strut
71
            \hfill
72
73
            \ifpc@rulebetween
              \vrule
74
              \hfill
75
76
            \fi
          \fi
77
78
        \repeat
79
      }%
80
      \@tempa
81
    \int x\pc@placeboxes
82
83
      \@PackageWarningNoLine{pdfcolparcolumns}{%
84
        85
86
        Supported versions of package 'parcolumns':\MessageBreak
87
        \space\space 2004/08/05.\MessageBreak
        The redefinition of \string\pc@placeboxes\space may not%
88
        \MessageBreak
89
```

```
90
                                        behave correctly depending on the changes%
                                91
                                      }%
                                    \fi
                                92
                                93 \endgroup
               \pc@placeboxes
                                94 \renewcommand*{\pc@placeboxes}{%
                                    \global\let\@tempa\relax
                                    \count@\z@
                                96
                                    \hb@xt@\linewidth{%
                                97
                                      \vfuzz30ex %
                                98
                                      \vbadness\@M
                                99
                               100
                                      \splittopskip\z@skip
                               101
                                      \loop
                                      \ifnum\count@<\pc@columncount
                               102
                                        \advance\count@\@ne
                               103
                                        \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
                               104
                                          \hskip\csname pc@column@width@\number\count@\endcsname
                               105
                               106
                                          \expandafter\setbox\expandafter\@tempboxa\expandafter
                               107
                               108
                                          \vsplit\csname pc@column@\number\count@\endcsname
                               109
                                              to \dp\strutbox
                                          \vbox{%
                               110
                                            \pcpc@SetCurrent\count@
                               111
                               112
                                            \unvbox\@tempboxa
                                          }%
                               113
                               114
                                        \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
                               115
                                        \else
                               116
                                          \global\let\@tempa\pc@placeboxes
                               117
                                        \fi
                               118
                                        \ifnum\count@<\pc@columncount
                               119
                                          \strut
                               120
                               121
                                          \hfill
                                          \ifpc@rulebetween
                               122
                                            \begingroup
                               123
                               124
                                              \pcpc@RuleBetweenColor
                               125
                                               \vrule
                               126
                                            \endgroup
                                            \hfill
                               127
                                          \fi
                               128
                                        \fi
                               129
                               130
                                      \repeat
                                    }%
                               131
                               132
                                    \@tempa
                               133 }
\pcpc@RuleBetweenColorDefault
                               134 \def\pcpc@RuleBetweenColorDefault{%
                                    \normalcolor
                               135
                               136 }
       \pcpc@RuleBetweenColor
                               138 \define@key{parcolumns}{rulebetweencolor}{%
                                    \edef\pcpc@temp{#1}%
                               139
                                    \ifx\pcpc@temp\@empty
                               140
```

```
141
       \let\pcpc@RuleBetweenColor\pcpc@RuleBetweenColorDefault
     \else
142
143
       \edef\pcpc@temp{%
144
         \noexpand\@ifnextchar[{%
            \def\noexpand\pcpc@RuleBetweenColor{%
145
              \noexpand\color\pcpc@temp
146
           }%
147
            \noexpand\pcpc@GobbleNil
148
         }{%
149
            \def\noexpand\pcpc@RuleBetweenColor{%
150
              \noexpand\color{\pcpc@temp}%
151
152
            \noexpand\pcpc@GobbleNil
153
         }%
154
          \pcpc@temp\noexpand\@nil
155
156
157
       \pcpc@temp
158
159 }
```

\pcpc@GobbleNil

```
160 \long\def\pcpc@GobbleNil#1\@nil{}
161 \langle /package \rangle
```

3 Installation

3.1 Download

Package. This package is available on CTAN¹:

CTAN:macros/latex/contrib/oberdiek/pdfcolparcolumns.dtx The source file.

CTAN:macros/latex/contrib/oberdiek/pdfcolparcolumns.pdf Documentation.

Bundle. All the packages of the bundle 'oberdiek' are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

```
CTAN: install/macros/latex/contrib/oberdiek.tds.zip
```

TDS refers to the standard "A Directory Structure for TEX Files" (CTAN:pkg/tds). Directories with texmf in their name are usually organized this way.

3.2 Bundle installation

Unpacking. Unpack the oberdiek.tds.zip in the TDS tree (also known as texmf tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

3.3 Package installation

Unpacking. The .dtx file is a self-extracting docstrip archive. The files are extracted by running the .dtx through plain T_EX :

```
tex pdfcolparcolumns.dtx
```

 $^{^{1}{\}tt CTAN:pkg/pdfcolparcolumns}$

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as texmf tree):

```
\label{eq:pdfcolparcolumns.sty} $$ pdfcolparcolumns.sty $$ pdfcolparcolumns.pdf $$ \rightarrow doc/latex/oberdiek/pdfcolparcolumns.pdf $$ pdfcolparcolumns.dtx $$ \rightarrow source/latex/oberdiek/pdfcolparcolumns.dtx $$ $$
```

If you have a docstrip.cfg that configures and enables docstrip's TDS installing feature, then some files can already be in the right place, see the documentation of docstrip.

3.4 Refresh file name databases

If your T_EX distribution (T_EX Live, MiKT_EX, ...) relies on file name databases, you must refresh these. For example, T_EX Live users run texhash or mktexlsr.

3.5 Some details for the interested

Unpacking with LATEX. The .dtx chooses its action depending on the format:

plain TEX: Run docstrip and extract the files.

LATEX: Generate the documentation.

If you insist on using LATEX for docstrip (really, docstrip does not need LATEX), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{pdfcolparcolumns.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the .dtx or the .drv to generate the documentation. The process can be configured by the configuration file ltxdoc.cfg. For instance, put this line into this file, if you want to have A4 as paper format:

\PassOptionsToClass{a4paper}{article}

An example follows how to generate the documentation with pdfLATEX:

```
pdflatex pdfcolparcolumns.dtx
makeindex -s gind.ist pdfcolparcolumns.idx
pdflatex pdfcolparcolumns.dtx
makeindex -s gind.ist pdfcolparcolumns.idx
pdflatex pdfcolparcolumns.dtx
```

4 References

- [1] Jonathan Sauer: *The parcolumns package*; 2004/11/25; CTAN:pkg/parcolumns.
- [2] Heiko Oberdiek: *The pdfcol package*; 2007/09/09; CTAN:pkg/pdfcol.

5 History

[2007/07/26 v1.0]

• First version, published in the newsgroup comp.text.tex with the name parcolumns-colorstacks: "Re: xcolor glitches" ²

[2007/09/09 v1.1]

- CTAN version, package name renamed to pdfcolparcolumns.
- Uses package pdfcol.
- Documentation added.
- Test file added.

[2008/08/11 v1.2]

- Code is not changed.
- URLs updated.

[2010/01/11 v1.3]

- Fix for rule color.
- New option rulebetweencolor for environment parcolumns.

[2016/05/16 v1.4]

• Documentation updates.

[2019/12/29 v1.5]

• \PassOptionsToPackage not \PassoptionsToPackage

6 Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; plain numbers refer to the code lines where the entry is used.

${f Symbols}$	\mathbf{C}
\@M 51, 99	\chardef 19, 29
\@PackageWarningNoLine 84	\color 146, 151
\@empty 140	\count@ 23, 25, 26, 27, 29, 48, 54,
\@ifnextchar 144	55, 56, 57, 60, 66, 70, 96, 102,
\One 25, 55, 103	103, 104, 105, 108, 111, 115, 119
\@nil 155, 160	\csname 56, 57, 60, 66, 104, 105, 108, 115
\@tempa 47, 68, 80, 95, 117, 132	\CurrentOption 6
\@tempboxa 59, 63, 107, 112	D
	\DeclareOption 5
${f A}$	\define@key 138
\advance 25, 55, 103	\dp 61, 109

²Url: https://groups.google.com/group/comp.text.tex/msg/56bd897b11bca414

${f E}$	\pcpc@RuleBetweenColor
\endcsname	$\dots \dots 124, \underline{137}, 141, 145, 150$
. 56, 57, 60, 66, 104, 105, 108, 115	\pcpc@RuleBetweenColorDefault
\endinput 16	134, 137, 141
	\pcpc@SetCurrent <u>36</u> , 111
${f G}$	\pcpc@SwitchStack 33, 43
\g@addto@macro	\pcpc@temp
·	. 139, 140, 143, 146, 151, 155, 157
H	\pdfcolInitStack 26
\hb@xt@ 49, 97	\pdfcolSetCurrent 37
\hfill 72, 75, 121, 127	\pdfcolSwitchStack 34
\hskip 57, 105	\ProcessOptions 8
-	\ProvidesPackage3
I	
\ifnum 21, 27, 54, 70, 102, 119	${f R}$
\ifpc@rulebetween 73, 122	\renewcommand 94
\ifpdfcolAvailable 11	\repeat 28, 78, 130
\ifvoid 56, 66, 104, 115	\RequirePackage 9, 10, 18
\ifx 82, 140	~
	S
${f L}$	\setbox
\linewidth 49, 97	\space 85, 87, 88
\loop 24, 53, 101	\splittopskip 52, 100
	\strut 71, 120
\mathbf{M}	\strutbox 61, 109
$\verb \MessageBreak \dots \dots 85, 86, 87, 89 $	${f T}$
N	\the 26
\NeedsTeXFormat 2	${f U}$
\normalcolor 135	\unvbox
\number 34,	(diivbox
37, 56, 57, 60, 66, 104, 105, 108, 115	V
	\vbadness 51, 99
P	\vbox 62, 110
\PackageInfo 13	\vfuzz 50, 98
\PassOptionsToPackage 6	\vrule 74, 125
\pc@alloccolumns 39	\vsplit 60, 108
\pc@columncount 40, 54, 70, 102, 119	- ,
\pc@columnctr 43	\mathbf{X}
$\verb \pc@placeboxes \dots 68, 82, 85, 88, \underline{94} $	\x 46, 82
\pc@setcolumnwidth 42	
$\verb \pcpc@GobbleNil 148, 153, 160 $	${f Z}$
$\verb \pcpc@InitStacks \dots \dots \underline{20}, 40$	\z@ 19, 48, 96
\pcpc@MaxStack 19, 21, 23, 29	\z@skip 52, 100