


# Charge, electric field, and potential


#### Coulomb's law

- Force of *n* source charges on a test charge
  - $\circ$  Force from source charge  $q_i$  acting on test charge Q
    - Coulomb's law  $F_i = \frac{1}{4\pi\varepsilon_0} \frac{q_i Q}{r_i^2} \widehat{r_i}$






• Location of Q: r, location of  $q_i$ :  $r'_i$ 




■ Total force acting on test charge 
$$F = \sum_{i=1}^{n} F_i$$

Not a necessity, but an experimental fact

\* to in textbook is typed as to in our slides (Cursive "r")



#### Coulomb's law




Cavendish's apparatus for determining  $F \propto r^{-2}$  in Coulomb's law

#### Electric field induced by charge

Relation of force and electric field

$$\mathbf{F} = Q\mathbf{E}$$

- Electric field: force per unit charge
- Real physical entity, as a vector field filling the space around charges
- Negated theory of "ether"



Electric field induced by discrete charges

$$\mathbf{E}(\mathbf{r}) \equiv \frac{1}{4\pi\epsilon_0} \sum_{i=1}^n \frac{q_i}{\nu_i^2} \hat{\boldsymbol{\lambda}}_i$$

- Separation vector  $\boldsymbol{r}_i = \boldsymbol{r} \boldsymbol{r}_i'$ , contains  $\boldsymbol{r}$
- Principle of superposition also holds

#### **Electric field induced by charge**


Electric field induced by continuous charge distribution

$$\mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{1}{n^2} \hat{\mathbf{n}} \, dq$$

- Add up contributions from infinitesimal charge elements dq
- Three ways dq can be distributed


#### Line charge $dq \rightarrow \lambda \ dl'$

$$\mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\lambda(\mathbf{r}')}{r^2} \hat{\boldsymbol{\lambda}} dl'$$




## Surface charge $dq \rightarrow \sigma \ da'$ Volume charge $dq \rightarrow \rho \ d\tau'$

$$\mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\sigma(\mathbf{r}')}{r^2} \hat{\boldsymbol{n}} da'$$



$$dq \rightarrow \rho \ d\tau'$$

$$\mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\lambda(\mathbf{r}')}{r^2} \hat{\boldsymbol{\lambda}} dl' \quad \mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\sigma(\mathbf{r}')}{r^2} \hat{\boldsymbol{\lambda}} da' \quad \mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\rho(\mathbf{r}')}{r^2} \hat{\boldsymbol{\lambda}} d\tau'$$




\* $\lambda$ ,  $\sigma$ ,  $\rho$ : charge per unit length, area, volume

#### Electric field induced by charge

Electric field induced by continuous charge distribution

**Example 2.2.** Find the electric field a distance z above the midpoint of a straight line segment of length 2L that carries a uniform line charge  $\lambda$  (Fig. 2.6).




 Integration sometimes can get formidable, need to device new tools to simplify problems.


- Electric field lines
  - Source charge q at the origin

$$\mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} \hat{\mathbf{r}}$$


o Draw vector field – field falls off like  $1/r^2$ 




- Connect up the arrows electric field lines
  - Direction of line indicates field direction
  - Density of line indicates field magnitude




 Field lines begin from positive charges and end on negative ones





• Electric field flux 
$$\Phi_E \equiv \int_{\mathcal{S}} \mathbf{E} \cdot d\mathbf{a}$$

A measure of the number of field lines passing through an area



- Gauss's law
  - The flux through any closed surface is a measure of the total charge inside

$$\oint_{\mathbf{T}} \mathbf{E} \cdot d\mathbf{a} = \int \frac{1}{4\pi\epsilon_0} \left( \frac{q}{r^2} \hat{\mathbf{r}} \right) \cdot (\underline{r^2 \sin\theta \, d\theta \, d\phi \, \hat{\mathbf{r}}}) = \frac{1}{\epsilon_0} q$$
Spherical surface of radius  $r$ 

- The surface integral can be any shape, not necessarily spherical
- $\oint \mathbf{E} \cdot d\mathbf{a} = \sum_{i=1}^{n} \left( \oint \mathbf{E}_{i} \cdot d\mathbf{a} \right) = \sum_{i=1}^{n} \left( \frac{1}{\epsilon_{0}} q_{i} \right)$ Multiple charges

$$\oint \mathbf{E} \cdot d\mathbf{a} = \frac{1}{\epsilon_0} Q_{\text{enc}}$$

 $\oint \mathbf{E} \cdot d\mathbf{a} = \frac{1}{\epsilon_0} Q_{\text{enc}}$ ( $Q_{\text{enc}}$ : total charge enclosed in the integrated surface)

- Gauss's law
  - Gauss's law in the differential form

Divergence theorem
$$\oint_{\mathcal{S}} \mathbf{E} \cdot d\mathbf{a} = \frac{1}{\epsilon_0} Q_{\text{enc}} \quad \text{(integral form)}$$

$$\oint_{\mathcal{S}} \mathbf{E} \cdot d\mathbf{a} = \int_{\mathcal{V}} (\mathbf{\nabla} \cdot \mathbf{E}) \, d\tau$$

$$Q_{\text{enc}} = \int_{\mathcal{V}} \rho \, d\tau$$


$$\Rightarrow \int_{\mathcal{V}} (\mathbf{\nabla} \cdot \mathbf{E}) \, d\tau = \int_{\mathcal{V}} \left(\frac{\rho}{\epsilon_0}\right) \, d\tau$$

$$\Rightarrow \nabla \cdot \mathbf{E} = \frac{1}{\epsilon_0} \rho \quad \text{(differential form)}$$

- Differential form more compact, but integral form easier to use
- Use of Gauss's law to calculate electric field
  - Need (1) Gauss's law in integral form and (2) symmetry arguments

Application of Gauss's law

**Example 2.3.** Find the field outside a uniformly charged solid sphere of radius R and total charge q.





 The field outside the sphere is exactly the same as it would have been if all the charge had been concentrated at the center

- Directly calculate divergence
  - o According to Coulomb's law


$$\mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_{\text{all space}} \frac{\hat{\mathbf{i}}}{\imath^2} \rho(\mathbf{r}') d\tau'$$

$$\nabla \cdot \mathbf{E} = \frac{1}{4\pi\epsilon_0} \int \nabla \cdot \left(\frac{\hat{\mathbf{z}}}{z^2}\right) \rho(\mathbf{r}') d\tau'$$

$$\nabla \cdot \left(\frac{\widehat{r}}{r^2}\right) = \nabla \cdot \left(\frac{\widehat{r}}{r^2}\right) = \frac{1}{r^2} \frac{\partial}{\partial r} \left(r^2 \frac{1}{r^2}\right) = 0$$

 $\circ$  The derivation above is correct anywhere but the origin (r=0), where the divergence should go to infinity


? This seems to contradict the Gauss's law, what went wrong




 Consider special case of point charge and Gauss's law with varying volume to integrate


- Delta function
  - Infinitely high, infinitesimally narrow
  - 1D Delta function

$$\delta(x) = \begin{cases} 0, & \text{if } x \neq 0 \\ \infty, & \text{if } x = 0 \end{cases}$$
with 
$$\int_{-\infty}^{\infty} \delta(x) \, dx = 1$$



Can be understood as the limit of a sequence of functions





- Delta function
  - 1D Delta function
    - When in an integral, "picks out" the value of a function

Since 
$$\delta(x)$$
 anywhere 0 but at  $x = 0$ 

$$f(x)\delta(x) = f(0)\delta(x)$$

[f(x)] being an ordinary function not going to infinity]

And, one can shift  $\delta(x)$  to  $\delta(x-a)$  to pick out another one

$$f(x)\delta(x-a) = f(a)\delta(x-a)$$

$$\int_{-\infty}^{\infty} f(x)\delta(x-a) \, dx = f(a)$$

A frequently used expression  $\delta(kx) = \frac{1}{|k|}\delta(x)$ 

- Delta function
  - o 3D Delta function  $\delta^3(\mathbf{r}) = \delta(x) \, \delta(y) \, \delta(z)$

with 
$$\int_{\text{all space}} \delta^3(\mathbf{r}) d\tau = \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} \delta(x) \, \delta(y) \, \delta(z) \, dx \, dy \, dz = 1$$

- Picks out a function value  $\int_{\mathbf{a}^{11} \text{ space}} f(\mathbf{r}) \delta^3(\mathbf{r} \mathbf{a}) \, d\tau = f(\mathbf{a})$
- Back to calculating divergence of electric field

$$\nabla \cdot \mathbf{E} = \frac{1}{4\pi\epsilon_0} \int \nabla \cdot \left(\frac{\hat{\mathbf{i}}}{\imath^2}\right) \rho(\mathbf{r}') \, d\tau'$$

$$\int \nabla \cdot \left(\frac{\hat{\mathbf{i}}}{\imath^2}\right) = 4\pi\delta^3(\mathbf{i})$$


$$\nabla \cdot \mathbf{E} = \frac{1}{4\pi\epsilon_0} \int 4\pi\delta^3(\mathbf{r} - \mathbf{r}') \rho(\mathbf{r}') \, d\tau' = \frac{1}{\epsilon_0} \rho(\mathbf{r}) \quad \text{Gauss's law recovered}$$

#### Curl of electric field

Calculate curl for point charge at origin

$$\mathbf{E} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} \hat{\mathbf{r}}$$

$$\int d\mathbf{l} = dr \, \hat{\mathbf{r}} + r \, d\theta \, \hat{\boldsymbol{\theta}} + r \sin\theta \, d\phi \, \hat{\boldsymbol{\phi}}$$



$$\int_{\mathbf{a}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l} = \frac{1}{4\pi\epsilon_0} \int_{\mathbf{a}}^{\mathbf{b}} \frac{q}{r^2} dr = \left. \frac{-1}{4\pi\epsilon_0} \frac{q}{r} \right|_{r_a}^{r_b} = \frac{1}{4\pi\epsilon_0} \left( \frac{q}{r_a} - \frac{q}{r_b} \right)$$

• For any closed loop  $(r_a = r_b)$   $\oint \mathbf{E} \cdot d\mathbf{l} = 0$ 

$$\nabla \times \mathbf{E} = \mathbf{0}$$

 $oldsymbol{
abla} imes oldsymbol{\mathrm{E}}=\mathbf{0}$  due to Stoke's theorem

Stoke's theorem  $\int_{S} (\nabla \times \mathbf{v}) \cdot d\mathbf{a} = \oint_{D} \mathbf{v} \cdot d\mathbf{l}$ 

Any static charge distribution

$$\nabla \times \mathbf{E} = \nabla \times (\mathbf{E}_1 + \mathbf{E}_2 + \ldots) = (\nabla \times \mathbf{E}_1) + (\nabla \times \mathbf{E}_2) + \ldots = \mathbf{0}$$


- Vector field **E** cannot take arbitrary form
  - Crucial constraint:  $\nabla \times \mathbf{E} = \mathbf{0}$

$$\frac{\partial E_x}{\partial y} = \frac{\partial E_y}{\partial x} \qquad \frac{\partial E_z}{\partial y} = \frac{\partial E_y}{\partial z} \qquad \frac{\partial E_x}{\partial z} = \frac{\partial E_z}{\partial x}$$

- Any chance the vector field can be described more easily?
- Electric potential:  $V(\mathbf{r}) \equiv -\int_{0}^{\mathbf{r}} \mathbf{E} \cdot d\mathbf{l}$ 
  - Unit: joules per coulomb
  - O: a reference point (usually taken as infinity)
  - Integral does not depend on path

$$\oint \mathbf{E} \cdot d\mathbf{l} = 0$$

•  $\oint \mathbf{E} \cdot d\mathbf{l} = 0$ •  $\int_{-\mathbf{E}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l}$  is path independent



- Electric potential:  $V(\mathbf{r}) \equiv -\int_{0}^{\mathbf{r}} \mathbf{E} \cdot d\mathbf{l}$ 
  - Potential difference between two points is more meaningful

$$V(\mathbf{b}) - V(\mathbf{a}) = -\int_{\mathcal{O}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l} + \int_{\mathcal{O}}^{\mathbf{a}} \mathbf{E} \cdot d\mathbf{l}$$
$$= -\int_{\mathcal{O}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l} - \int_{\mathbf{a}}^{\mathbf{c}} \mathbf{E} \cdot d\mathbf{l} = -\int_{\mathbf{a}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l}$$

On the other hand, the theorem for gradient gives

$$V(\mathbf{b}) - V(\mathbf{a}) = \int_{\mathbf{a}}^{\mathbf{b}} (\nabla V) \cdot d\mathbf{l}$$
  $\mathbf{E} = -\nabla V$ 


- Scalar field V gives full information of vector field E
- Can be off by a constant if choosing a different reference point

$$V'(\mathbf{r}) = -\int_{\mathcal{O}'}^{\mathbf{r}} \mathbf{E} \cdot d\mathbf{l} = -\int_{\mathcal{O}'}^{\mathcal{O}} \mathbf{E} \cdot d\mathbf{l} - \int_{\mathcal{O}}^{\mathbf{r}} \mathbf{E} \cdot d\mathbf{l} = K + V(\mathbf{r})$$

Application of electric potential

Example. Find the potential of a point charge q at origin


**Example 2.7.** Find the potential inside and outside a spherical shell of radius R (Fig. 2.31) that carries a uniform surface charge. Set the reference point at infinity.





- Poisson's equation of potential
  - o Poisson's equation  $\nabla^2 V = -\frac{\rho}{\epsilon_0}$   $\nabla \cdot \mathbf{E} = \nabla \cdot (-\nabla V) = -\nabla^2 V = \frac{\rho}{\epsilon_0}$
  - o In regions with no charge, Laplace's equation  $\nabla^2 V = 0$
  - Curl of a gradient always zero  $\nabla \times \mathbf{E} = \nabla \times (-\nabla V) = \mathbf{0}$
- Potential of a localized charge distribution
  - Pick infinity as the reference point  $\mathcal{O} = \infty$
  - o Principle of superposition holds  $V = V_1 + V_2 + \dots$
  - $\text{O Discrete charges} \quad V(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \sum_{i=1}^n \frac{q_i}{\imath_i} \\ \text{O Continuous charge} \quad V(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\rho(\mathbf{r}')}{\imath} \, d\tau' \\ \text{Can check}$

#### Charge, electric field, and potential



Differential equations need boundary conditions to solve


#### **Boundary conditions**

- Boundary conditions of E across a 2D charged surface
  - Normal component of E

"Gaussian pillbox" with  $\varepsilon \to 0$ 

$$\oint_{S} \mathbf{E} \cdot d\mathbf{a} = \frac{1}{\epsilon_0} Q_{\text{enc}} = \frac{1}{\epsilon_0} \sigma A$$

$$E_{\text{above}}^{\perp} - E_{\text{below}}^{\perp} = \frac{1}{\epsilon_0} \sigma$$




Tangential component of E

Thin loop with  $\varepsilon \to 0$ 

$$\oint \mathbf{E} \cdot d\mathbf{l} = 0$$

$$\mathbf{E}_{\mathrm{above}}^{\parallel} = \mathbf{E}_{\mathrm{below}}^{\parallel}$$




$$\circ$$
 Summarizing above  $\mathbf{E}_{above} - \mathbf{E}_{below} = rac{\sigma}{\epsilon_0} \mathbf{\hat{n}}$ 

#### **Boundary conditions**

- Boundary conditions of *V* across a 2D charged surface
  - Potential is continuous (across any boundary)

$$V_{
m above} - V_{
m below} = -\int_{f a}^{f b} {f E} \cdot d{f l}$$
 Path length  $ightarrow 0$   $V_{
m above} = V_{
m below}$ 



Gradient of potential is discontinuous

$$\mathbf{E}_{\text{above}} - \mathbf{E}_{\text{below}} = \frac{\sigma}{\epsilon_0} \mathbf{\hat{n}}$$

$$\mathbf{E} = -\nabla V$$

$$\nabla V_{\text{above}} - \nabla V_{\text{below}} = -\frac{1}{\epsilon_0} \sigma \mathbf{\hat{n}}$$

$$\Rightarrow \frac{\partial V_{\text{above}}}{\partial n} - \frac{\partial V_{\text{below}}}{\partial n} = -\frac{1}{\epsilon_0} \sigma$$


where we define normal derivative of *V* 

$$\frac{\partial V}{\partial n} = \nabla V \cdot \hat{\mathbf{n}}$$

#### **Energy in electrostatics**

- Work done to move a charge
  - o Integrate force over distance

$$W = \int_{\mathbf{a}}^{\mathbf{b}} \mathbf{F} \cdot d\mathbf{l} = -Q \int_{\mathbf{a}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l}$$
$$= Q[V(\mathbf{b}) - V(\mathbf{a})]$$



- Electrostatic force is conservative (path independent)
- Can confirm the unit of electric potential
- $\circ$  Work for bringing from infinitely far to  $m{r}$

$$W = Q[V(\mathbf{r}) - V(\infty)]$$

 $W = QV(\mathbf{r})$  with the potential reference point set to infinity


#### **Energy in electrostatics**

- Energy of a point charge configuration
  - Equals to the work required to bring charges together from infinity
    - First charge  $q_1$  to  $r_1$ , no work required

• 
$$q_2$$
 to  $\mathbf{r_2}$   $W_2 = \frac{1}{4\pi\epsilon_0} q_2 \left(\frac{q_1}{r_{12}}\right)$ 

• 
$$q_3$$
 to  $\mathbf{r_3}$   $W_3 = \frac{1}{4\pi\epsilon_0} q_3 \left( \frac{q_1}{r_{13}} + \frac{q_2}{r_{23}} \right)$ 

• 
$$W = W_1 + W_2 + W_3$$



Total work (energy) for n charges

$$W = \frac{1}{4\pi\epsilon_0} \sum_{i=1}^n \sum_{j>i}^n \frac{q_i q_j}{\imath_{ij}} = \frac{1}{8\pi\epsilon_0} \sum_{i=1}^n \sum_{j\neq i}^n \frac{q_i q_j}{\imath_{ij}} = \frac{1}{2} \sum_{i=1}^n q_i \left( \sum_{j\neq i}^n \frac{1}{4\pi\epsilon_0} \frac{q_j}{\imath_{ij}} \right)$$
Count once for each pair
$$V(\mathbf{r}_i)$$

Potential  $q_i$  feels due to all **other** charges

#### **Energy in electrostatics**

- Energy of a continuous charge distribution
  - Generalize point charge equation to

$$W = \frac{1}{2} \int \rho V \, d\tau \qquad \text{with $V$: actual potential, without excluding the charge of interest}$$
 
$$\downarrow \rho = \epsilon_0 \nabla \cdot \mathbf{E}$$
 
$$W = \frac{\epsilon_0}{2} \int (\nabla \cdot \mathbf{E}) V \, d\tau$$
 
$$\downarrow \text{Integrate by parts } \int_{\mathcal{V}} f(\nabla \cdot \mathbf{A}) \, d\tau = -\int_{\mathcal{V}} \mathbf{A} \cdot (\nabla f) \, d\tau + \oint_{\mathcal{S}} f \mathbf{A} \cdot d\mathbf{a}$$
 
$$W = \frac{\epsilon_0}{2} \left[ -\int \mathbf{E} \cdot (\nabla V) \, d\tau + \oint V \mathbf{E} \cdot d\mathbf{a} \right] = \frac{\epsilon_0}{2} \left( \int_{\mathcal{V}} E^2 \, d\tau + \oint_{\mathcal{S}} V \mathbf{E} \cdot d\mathbf{a} \right)$$
 
$$Vanishes$$
 when  $\mathcal{V} \to \infty$  all space

Cannot be directly compared to equation of point charge, see textbook


#### Conductors

- Free electrons solid-state metals and doped semiconductors
- Free ions Electrolyte, salt water, lithium ion battery
- Unlimited supply of free charges, which are free to move
- Electrostatics of perfect conductors
  - $\circ$  **E** = 0 inside a conductor
    - If not, charge will flow to induce a new surface charge distribution that exactly cancels the internal field
  - $\circ$   $\rho = 0$  (net charge volume density) inside a conductor
    - Because  $\nabla \cdot \mathbf{E} = \rho/\epsilon_0$
  - A conductor is an equipotential
    - For any two points,  $V(\mathbf{b}) V(\mathbf{a}) = -\int_{\mathbf{a}}^{\mathbf{b}} \mathbf{E} \cdot d\mathbf{l} = 0$


- Electrostatics of perfect conductors
  - Any net charge only resides on the surface (minimizes energy)
  - Surface net charges serves to cancel the internal field
- + - + - + - + - + - E<sub>1</sub> + - + - + - + - + - + - + - +
- E is always perpendicular to the surface, just outside the conductor
  - Recall boundary conditions

$$E_{\text{above}}^{\perp} - E_{\text{below}}^{\perp} = \frac{1}{\epsilon_0} \sigma$$


$$\mathbf{E}_{\text{above}}^{\parallel} = \mathbf{E}_{\text{below}}^{\parallel} = 0$$



- Induced charges
  - Charge placed outside a metal
    - Induced charge serves to cancel field inside conductor
    - Net force of attraction



- Charge in the cavity of a hollow metal
  - Inside the cavity:  $\mathbf{E} \neq 0$
  - Induced charge  $q_{induced} = -q$  at inner wall
  - Inside the conductor:  $\mathbf{E} = 0$
  - Leftover charge  $q_{induced} = q$  at outer wall
  - Outside the conductor:  $\mathbf{E} \neq 0$



- Induced charges
  - Faraday cage
    - If no charge is placed in the cavity of a hollow conductor, E = 0 in the cavity regardless of the outside conditions


If not, can construct a loop of integration, whose trajectory in the cavity follows the field line

$$\oint \mathbf{E} \cdot d\mathbf{l} \neq 0$$

$$ightharpoonup$$
 Contradicts  $\nabla \times \mathbf{E} = 0$ 


$$\mathbf{E} = 0$$

 Protects sensitive apparatus inside the cavity by shielding out external electric fields



#### Induced charges

**Example 2.10.** An uncharged spherical conductor centered at the origin has a cavity of some weird shape carved out of it (Fig. 2.46). Somewhere within the cavity is a charge *q. Question:* What is the field outside the sphere?





- Surface charge and force on a conductor
  - Boundary conditions

$$\left\{ \begin{array}{ll} \mathbf{E}_{above} - \mathbf{E}_{below} = \frac{\sigma}{\epsilon_0} \mathbf{\hat{n}} & \text{On the surface} \\ \frac{\partial V_{above}}{\partial n} - \frac{\partial V_{below}}{\partial n} = -\frac{1}{\epsilon_0} \sigma & \text{conductor} \end{array} \right.$$
 
$$\left\{ \begin{array}{ll} \mathbf{E} = \frac{\sigma}{\epsilon_0} \mathbf{\hat{n}} \\ \text{conductor} \\ \sigma = -\epsilon_0 \frac{\partial V}{\partial n} \end{array} \right.$$

- Force (per unit area) exerted on the conductor
  - Can prove (textbook p.104): for any surface across which is discontinuous, force needs to be calculated by

$$\mathbf{f} = \sigma \mathbf{E}_{\text{average}} = \frac{1}{2} \sigma (\mathbf{E}_{\text{above}} + \mathbf{E}_{\text{below}})$$

• For conductors 
$$\mathbf{f} = \frac{1}{2\epsilon_0} \sigma^2 \hat{\mathbf{n}}$$

#### Capacitors

 We can define a potential difference between two conductors, without specifying locations of the integral

$$V = V_{+} - V_{-} = -\int_{(-)}^{(+)} \mathbf{E} \cdot d\mathbf{l}$$



- Although **E** is geometry dependent, we know **E**  $\propto Q$ , and  $V \propto Q$
- $\circ$  Can define ratio as capacitance  $C \equiv rac{Q}{V}$ 
  - A purely geometrical quantity, determined by shapes, sizes, and separation of the two conductors
  - Unit: farads (F), or Coulomb per volt
  - Always positive