Boost.Chrono 1.0.0

Howard Hinnant Beman Dawes Vicente J. Botet Escriba

Copyright © 2008, 2006, 2009 -2011 Vicente J. Botet Escriba

Distributed under the Boost Software License, Version 1.0. (See accompanying file LICENSE_1_0.txt or copy at http://www.boost.org/LICENSE_1_0.txt)

Table of Contents

| Overview | |
|--------------------------------------|----|
| Motivation | |
| Description | |
| User's Guide | |
| Getting Started | |
| Tutorial | 6 |
| Examples | |
| External Resources | 31 |
| Reference | 31 |
| Included on the C++0x Recommendation | |
| Chrono I/O | 54 |
| Other Clocks | 58 |
| Appendices | 63 |
| Appendix A: History | 63 |
| Appendix B: Rationale | 70 |
| Appendix C: Implementation Notes | 70 |
| Appendix D: FAQ | 71 |
| Appendix E: Acknowledgements | 71 |
| Appendix F. Futura plans | 72 |

Overview

"What is time, then? If nobody asks me, I know; if I have to explain it to someone who has asked me, I do not know.""

-- Augustine

How to Use This Documentation

This documentation makes use of the following naming and formatting conventions.

- Code is in fixed width font and is syntax-highlighted.
- Replaceable text that you will need to supply is in italics.
- Free functions are rendered in the code font followed by (), as in free_function().
- If a name refers to a class template, it is specified like this: class_template<>; that is, it is in code font and its name is followed by <> to indicate that it is a class template.
- If a name refers to a function-like macro, it is specified like this: MACRO(); that is, it is uppercase in code font and its name is followed by () to indicate that it is a function-like macro. Object-like macros appear without the trailing ().



Names that refer to concepts in the generic programming sense are specified in CamelCase.



Note

In addition, notes such as this one specify non-essential information that provides additional background or rationale.

Finally, you can mentally add the following to any code fragments in this document:

```
// Include all of Chrono files
#include <boost/chrono.hpp>
namespace bchrono=boost::chrono;
ckg
```

Motivation

Time

We all deal with time every day of our lives. We've intuitively known it since birth. Thus we are all very familiar with it and believe it to be a simple matter. The modeling of time in computer programs should be similarly simple. The unfortunate truth is that this perceived simplicity is only skin deep. Fortunately, we do not need a terribly complicated solution to meet the bulk of our needs. However, overly simplistic solutions can be dangerous and inefficient, and won't adapt as the computer industry evolves.

Boost.Chrono aims to implement the new time facilities in C++0x, as proposed in **N2661 - A Foundation to Sleep On**. That document provides background and motivation for key design decisions and is the source of a good deal of information in this documentation.

Wall clock versus system and user time

To make the timing facilities of Boost.Chrono more generally useful, the library provides a number of clocks that are thin wrappers around the operating system's process time API, thereby allowing the extraction of wall clock time, user CPU time, and system CPU time of the process. Wall clock time is the sum of CPU time and system CPU time. (On POSIX-like systems, this relies on times(). On Windows, it relies on GetProcessTimes().)

Description

The **Boost.Chrono** library provides:

Standard

- A means to represent time durations: managed by the generic duration class. Examples of time durations include days, minutes, seconds and nanoseconds, which can be represented with a fixed number of clock ticks per unit. All of these units of time duration are united with a generic interface by the duration facility.
- A type for representing points in time: time_point. A time_point represents an epoch plus or minus a duration. The library leaves epochs unspecified. A time_point is associated with a *clock*.
- Several clocks, some of which may not be available on a particular platform: system_clock, steady_clock and high_resolution_clock. A clock is a pairing of a time_point and duration, and a function which returns a time_point representing now.

Other clocks

To make the timing facilities more generally useful, **Boost.Chrono** provides a number of clocks that are thin wrappers around the operating system's time APIs, thereby allowing the extraction of wall clock time, user CPU time, system CPU time spent by the process,



- process_real_cpu_clock, captures wall clock CPU time spent by the current process.
- process_user_cpu_clock, captures user-CPU time spent by the current process.
- process_system_cpu_clock, captures system-CPU time spent by the current process.
- A tuple-like class process_cpu_clock, that captures real, user-CPU, and system-CPU process times together.
- A thread_clock thread steady clock giving the time spent by the current thread (when supported by a platform).

Lastly, **Boost.Chrono** includes typeof registration for duration and time_point to permit using emulated auto with C++03 compilers.

1/0

It provides I/O for duration and time_point. It builds on <boost/ratio/ratio_io.hpp> to provide readable and flexible formatting and parsing for types in <boost/chrono.hpp>. The duration unit names can be customized through a new facet: duration_punct.

Caveat Emptor

The underlying clocks provided by operating systems are subject to many seemingly arbitrary policies and implementation irregularities. That's a polite way of saying they tend to be flakey, and each operating system or even each clock has its own cruel and unusual forms of flakiness. Don't bet the farm on their accuracy, unless you have become deeply familiar with exactly what the specific operating system is guaranteeing, which is often very little.

User's Guide

Getting Started

Installing Chrono

Getting Boost.Chrono

Boost.Chrono is in the latest Boost release in the folder /boost/chrono. Documentation, tests and examples folder are at boost/libs/chrono/.

You can also access the latest (unstable?) state from the Boost trunk directories boost/chrono and libs*chrono. Just go to [@ht-tp:/*svn.boost.org/trac/boost/wiki/BoostSubversion here] and follow the instructions there for anonymous SVN access.

Where to install Boost.Chrono?

The simple way is to decompress (or checkout from SVN) the files in your BOOST_ROOT directory.

Building Boost.Chrono

Boost.Chrono can be configured as a header-only library. When BOOST_CHRONO_INLINED is defined the Boost.Chrono is a header-only library. Otherwise is not a header only library and you need to compile it and build the library before use, for example using:

bjam libs/chrono/build



Requirements



Caution

Boost.Chrono depends on some new traits in Boost.TypeTraits which have been added on Boost 1.45.

In particular, **Boost.Chrono** depends on:

Boost.Config for configuration purposes, ...

Boost.Exception for throw_exception, ...

Boost.Integer for cstdint conformance, ...

Boost.MPL for MPL Assert and bool, logical ...

Boost.Operators for operators, ...

Boost.Ratio for ratio, milli, micro, ...

Boost.System for error_code, ...

Boost.TypeTraits for is_base, is_convertible, common_type, ...

Boost.Utility/EnableIf for enable_if, ...

Building an Executable that Uses Boost.Chrono

In addition to link with the **Boost.Chrono** library you need also to link with the **Boost.System** library. Once **Boost.System** will be configurable to be a header only using BOOST_SYSTEM_INLINED you will no need to link with it.

Exception safety

All functions in the library are exception-neutral and provide strong guarantee of exception safety as long as the underlying parameters provide it.

Thread safety

All functions in the library are thread-unsafe except when noted explicitly.

As Boost. Chrono doesn't use mutable global variables the thread-safety analysis is limited to the access to each instance variable. It is not thread safe to use a function that modifies the access to a user variable if another can be reading or writing it.

Tested compilers

The implementation will eventually work with most C++03 conforming compilers. Current version has been tested on:

Windows with

MSVC 10.0

Cygwin 1.5 with

GCC 3.4.4

Cygwin 1.7 with

• GCC 4.3.4

MinGW with



- GCC 4.4.0
- GCC 4.5.0
- GCC 4.5.0 std = c + +0x
- GCC 4.6.0
- GCC 4.6.0 -std=c++0x

Initial versions were tested on:

MacOS with GCC 4.2.4 (Some test are needed for the specific Mac files).

Ubuntu Linux with GCC 4.2.4



Note

Please let us know how this works on other platforms/compilers.



Note

Please send any questions, comments and bug reports to boost <at> lists <dot> boost <dot> org.

Hello World!

If all you want to do is to time a program's execution, here is a complete program (stopclock_example.cpp):

```
#include <boost/chrono.hpp>
#include <cmath>

int main()
{
    bchrono::system_clock::time_point start = bchrono::system_clock::now();

    for ( long i = 0; i < 10000000; ++i )
        std::sqrt( 123.456L ); // burn some time

    bchrono::duration<double> sec = bchrono::system_clock::now() - start;
        std::cout << "took " << sec.count() << " seconds\n";
        return 0;
    }

getting_starte</pre>
```

Output was:

```
took 0.832 seconds
```



Tutorial

Duration

The duration is the heart of this library. The interface that the user will see in everyday use is nearly identical to that of **Boost.DateTime** time durations authored by Jeff Garland, both in syntax and in behavior. This has been a very popular boost library for 7 years. There is an enormous positive history with this interface.

The library consists of six units of time duration:

- hours
- minutes
- seconds
- milliseconds
- microseconds
- nanoseconds

These units were chosen as a subset of the boost library because they are the most common units used when sleeping, waiting on a condition variable, or waiting to obtain the lock on a mutex. Each of these units is nothing but a thin wrapper around a signed integral count. That is, when you construct minutes(3), all that happens is a 3 is stored inside minutes. When you construct microseconds(3), all that happens is a 3 is stored inside microseconds.

The only context in which these different types differ is when being converted to one another. At this time, unit-specific compile-time conversion constants are used to convert the source unit to the target unit. Only conversions from coarser units to finer units are allowed (in Boost). This restriction ensures that all conversions are always exact. That is, microseconds can always represent any value minutes has.

In **Boost.DateTime**, these units are united via inheritance. **Boost.Chrono** instead unites these units through the class template duration. That is, in **Boost.Chrono** all six of the above units are nothing but typedefs to different instantiations of duration. This change from Boost.DateTime has a far reaching positive impact, while not changing the syntax of the everyday use at all.

The most immediate positive impact is that the library can immediately generate any unit, with any precision it needs. This is sometimes necessary when doing comparisons or arithmetic between durations of differing precision, assuming one wants the comparison and arithmetic to be exact.

A secondary benefit is that by publishing the class template duration interface, user code can very easily create durations with any precision they desire. The ratio utility is used to specify the precision, so as long as the precision can be expressed by a rational constant with respect to seconds, this framework can exactly represent it (one third of a second is no problem, and neither is one third of a femto second). All of this utility and flexibility comes at no cost just by making use of the no-run-time-overhead ratio facility.

In Boost.DateTime, hours does not have the same representation as nanoseconds. The former is usually represented with a long whereas a long long is required for the latter. The reason for this is simply range. You don't need many hours to cover an extremely large range of time. But this isn't true of nanoseconds. Being able to reduce the sizeof overhead for some units when possible, can be a significant performance advantage.

Boost.Chrono continues, and generalizes that philosophy. Not only can one specify the precision of a duration, one can also specify its representation. This can be any integral type, or even a floating-point type. Or it can be a user-defined type which emulates an arithmetic type. The six predefined units all use signed integral types as their representation. And they all have a minimum range of \pm 292 years. nanoseconds needs 64 bits to cover that range. hours needs only 23 bits to cover that range.

So What Exactly is a duration and How Do I Use One?

A duration has a representation and a tick period (precision).



```
template <class Rep, class Period = ratio<1> > class duration;
#
```

The representation is simply any arithmetic type, or an emulation of such a type. The representation stores a count of ticks. This count is the only data member stored in a duration. If the representation is floating-point, it can store fractions of a tick to the precision of the representation. The tick period is represented by a ratio and is encoded into the duration's type, instead of stored. The tick period only has an impact on the behavior of the duration when a conversion between different durations is attempted. The tick period is completely ignored when simply doing arithmetic among like durations.

Example:

```
typedef bchrono::duration<long, boost::ratio<60> > minutes;
   minutes m1(3);
                                  // ml stores 3
   minutes m2(2);
                                  // m2 stores 2
   minutes m3 = m1 + m2;
                                  // m3 stores 5
   typedef bchrono::duration<long long, boost::micro> microseconds;
   microseconds us1(3);
                                  // us1 stores 3
   microseconds us2(2);
                                  // us2 stores 2
   microseconds us3 = us1 + us2; // us3 stores 5
                                   // us4 stores 300000005
   microseconds us4 = m3 + us3;
</code> and
```

In the final line of code above, there is an implicit conversion from minutes to microseconds, resulting in a relatively large number of microseconds.

If you need to access the tick count within a duration, there is a member count () which simply returns the stored tick count.

```
long long tc = us4.count();  // tc is 300000005
#
```

These duration's have very simple, very predictable, and very observable behavior. After all, this is really nothing but the time-tested interface of Jeff's boost time duration library (unified with templates instead of inheritance).

What Happens if I Assign m3 + us3 to minutes Instead of microseconds?

```
minutes m4 = m3 + us3;
3
```

It won't compile! The rationale is that implicit truncation error should not be allowed to happen. If this were to compile, then m4 would hold 5, the same value as m3. The value associated with us3 has been effectively ignored. This is similar to the problem of assigning a double to an int: the fractional part gets silently discarded.

But What if the Truncation Behavior is What I Want to Do?

There is a duration_cast facility to explicitly ask for this behavior:

```
minutes m4 = bchrono::duration_cast<minutes>(m3 + us3); // m4.count() == 5
-
```



In general, one can perform duration arithmetic at will. If duration_cast isn't used, and it compiles, the arithmetic is exact. If one wants to override this exact arithmetic behavior, duration_cast can be used to explicitly specify that desire. The duration_cast has the same efficiency as the implicit conversion, and will even be exact as often as it can.

You can use duration_cast<> to convert the duration into whatever units you desire. This facility will round down (truncate) if an exact conversion is not possible. For example:

```
bchrono::nanoseconds start;
bchrono::nanoseconds end;
typedef bchrono::milliseconds ms;
ms d = bchrono::duration_cast<ms>(end - start);

// d now holds the number of milliseconds from start to end.
std::cout << ms.count() << "ms\n";
ation_hp</pre>
```

We can convert to nanoseconds, or some integral-based duration which nanoseconds will always exactly convert to, then duration_cast<> is unnecessary:

```
typedef bchrono::nanoseconds ns;
ns d = end - start;
std::cout << ns.count() << "ns\n";
V##</pre>
```

If you need seconds with a floating-point representation you can also eliminate the duration_cast<>:

```
typedef bchrono::duration<double> sec; // seconds, stored with a double
  sec d = end - start;
  std::cout << sec.count() << "s\n";
rat</pre>
```

If you're not sure if you need duration_cast<> or not, feel free to try it without. If the conversion is exact, or if the destination has a floating-point representation, it will compile: else it will not compile.

If you need to use duration_cast<>, but want to round up, instead of down when the conversion is inexact, here is a handy little helper function to do so. Writing it is actually a good starter project for understanding **Boost.Chrono**:



Trafficking in floating-point Durations

I don't want to deal with writing duration_cast all over the place. I'm content with the precision of my floating-point representation.

Not a problem. When the destination of a conversion has floating-point representation, all conversions are allowed to happen implicitly.

```
typedef bchrono::duration<double, ratio<60> > dminutes;
dminutes dm4 = m3 + us3; // dm4.count() == 5.000000083333333
```

How Expensive is All of this?

If you were writing these conversions by hand, you could not make it more efficient. The use of ratio ensures that all conversion constants are simplified as much as possible at compile-time. This usually results in the numerator or denominator of the conversion factor simplifying to 1, and being subsequently ignored in converting the run-time values of the tick counts.

How Complicated is it to Build a Function Taking a duration Parameter?

There are several options open to the user:

• If the author of the function wants to accept any duration, and is willing to work in floating-point durations, he can simply use any floating-point duration as the parameter:

```
void f(bchrono::duration<double> d) // accept floating-point seconds
{
    // d.count() == 3.e-6 when passed bchrono::microseconds(3)
}
f(bchrono::microseconds(3));
point J
```

• If the author of the function wants to traffic only in integral durations, and is content with handling nothing finer than say nanoseconds (just as an example), he can simply specify nanoseconds as the parameter:

```
void f(bchrono::nanoseconds d)
{
      // d.count() == 3000 when passed bchrono::microseconds(3)
}

f(bchrono::microseconds(3));
se></c</pre>
```

In this design, if the client wants to pass in a floating-point duration, or a duration of finer precision than nanoseconds, then the client is responsible for choosing his own rounding mode in the conversion to nanoseconds.

```
bchrono::duration<double> s(1./3); // 1/3 of a second f(bchrono::duration_cast<bchrono::nanoseconds>(s)); // round towards zero in conversion to nanoseconds /c
```

In the example above, the client of f has chosen "round towards zero" as the desired rounding mode to nanoseconds. If the client has a duration that won't exactly convert to nanoseconds, and fails to choose how the conversion will take place, the compiler will refuse the call:



```
f(s); // does not compile n
```

• If the author of the function wants to accept any duration, but wants to work with integral representations and wants to control the rounding mode internally, then he can template the function:

• If the author in the example does not want to accept floating-point based durations, he can enforce that behavior like so:

```
template <class Period>
  void f(bchrono::duration<long long, Period> d)
{
    // convert d to nanoseconds, rounding up if it is not an exact conversion
    bchrono::nanoseconds ns = bchrono::duration_cast<nanoseconds>(d);
    if (ns < d)
        ++ns;
    // ns.count() == 333333334 when passed 333333333333 picoseconds
}
// About 1/3 of a second worth of picoseconds
    f(bchrono::duration<long long, boost::pico>(333333333333);
ink> as the
```

Clients with floating-point durations who want to use f will now have to convert to an integral duration themselves before passing the result to f.

In summary, the author of f has quite a bit of flexibility and control in the interface he wants to provide his clients with, and easy options for manipulating that duration internal to his function.

Can Durations Overflow?

This depend on the representation. The default typedefs uses a representation that don't handle overflows. The user can define his own representation that manage overflow as required by its application.

Clocks

While durations only have precision and representation to concern themselves, clocks and time_points are intimately related and refer to one another. Because clocks are simpler to explain, we will do so first without fully explaining time_points. Once clocks are introduced, it will be easier to then fill in what a time_point is.

A clock is a concept which bundles 3 things:

- 1. A concrete duration type.
- 2. A concrete time_point type.



3. A function called now() which returns the concrete time_point.

The standard defines tree system-wide clocks that are associated to the computer time.

- system_clock represents system-wide realtime clock that can be synchronized with an external clock.
- steady_clock can not be changed explicitly and the time since the initial epoch increase in a steady way.
- high_resolution_clock intend to use the system-wide clock provided by the platform with the higest resolution.

Boost.Chrono provides them when supported by the underlying platform. A given platform may not be able to supply all three of these clocks.

The library adds some clocks that are specific to a process or a thread, that is there is a clock per process or per thread.

The user is also able to easily create more clocks.

Given a clock named Clock, it will have:

One can get the current time from Clock with:

```
Clock::time_point t1 = Clock::now();
i
```

And one can get the time duration between two time_points associated with Clock with:

```
Clock::duration d = Clock::now() - t1;
```

And one can specify a past or future time_point with:

```
Clock::time_point t2 = Clock::now() + d;
#
```

Note how even if a particular clock becomes obsolete, the next clock in line will have the same API. There is no new learning curve to come up. The only source code changes will be simply changing the type of the clock. The same duration and time_point framework continues to work as new clocks are introduced. And multiple clocks are safely and easily handled within the same program.

Time Point

A time_point represents a point in time, as opposed to a duration of time. Another way of saying the same thing, is that a time_point represents an epoch plus or minus a duration. Examples of time_points include:



- 3 minutes after the computer booted.
- 03:14:07 UTC on Tuesday, January 19, 2038
- 20 milliseconds after I started that timer.

In each of the examples above, a different epoch is implied. Sometimes an epoch has meaning for several millennia. Other times the meaning of an epoch is lost after a while (such as the start of a timer, or when the computer booted). However, if two time_points are known to share the same epoch, they can be subtracted, yielding a valid duration, even if the definition of the epoch no longer has meaning.

In **Boost.Chrono**, an epoch is a purely abstract and unspecified concept. There is no type representing an epoch. It is simply an idea that relates (or doesn't) time_points to a clock, and in the case that they share a clock, time_points to one another. time_points associated with different clocks are generally not interoperable unless the relationship between the epochs associated with each clock is known.

So What Exactly is a time_point and How Do I Use One?

A time_point has a clock and a duration.

```
template <class Clock, class Duration = typename Clock::duration> class time_point;
#
```

The time_point's clock is not stored. It is simply embedded into the time_point's type and serves two purposes:

- 1. Because time_points originating from different clocks have different types, the compiler can be instructed to fail if incompatible time_points are used in inappropriate ways.
- 2. Given a time_point, one often needs to compare that time_point to "now". This is very simple as long as the time_point knows what clock it is defined with respect to.

A time_point's duration is stored as the only data member of the time_point. Thus time_points and their corresponding duration have exactly the same layout. But they have very different meanings. For example, it is one thing to say I want to sleep for 3 minutes. It is a completely different thing to say I want to sleep until 3 minutes past the time I started that timer (unless you just happened to start that timer now). Both meanings (and options for sleeping) have great practical value in common use cases for sleeping, waiting on a condition variable, and waiting for a mutex's lock. These same concepts and tools are found (for example) in Ada.

A timer example:

```
void f()
{
    bchrono::steady_clock::time_point start = bchrono::steady_clock::now();
    g();
    h();
    duration<double> sec = bchrono::steady_clock::now() - start;
    cout << "f() took " << sec.count() << " seconds\n";
}
e></link</pre>
```

Note that if one is using the duration between two clock time_points in a way where the precision of the duration matters, it is good practice to convert the clock's duration to a known duration. This insulates the code from future changes which may be made to the clock's precision in the future. For example steady_clock could easily be based on the clock speed of the cpu. When you upgrade to a faster machine, you do not want your code that assumed a certain tick period of this clock to start experiencing run-time failures because your timing code has silently changed meaning.

A delay loop example:



```
// delay for at least 500 nanoseconds:
  auto go = bchrono::steady_clock::now() + bchrono::nanoseconds(500);
  while (bchrono::steady_clock::now() < go)
   ;
  o cl</pre>
```

The above code will delay as close as possible to half a microsecond, no matter what the precision of steady_clock is. The more precise steady_clock becomes, the more accurate will be the delay to 500 nanoseconds.

Specific Clocks

system_clock

system_clock is useful when you need to correlate the time with a known epoch so you can convert it to a calendar time. Note the specific functions in the system_clock class.

steady_clock

steady_clock is useful when you need to wait for a specific amount of time. steady_clock time can not be reset. As other steady clocks, it is usually based on the processor tick.

Here is a polling solution, but it will probably be too inefficient:

```
bchrono::steady_clock::time_point start= chrono::steady_clock::now();
bchrono::steady_clock::duration delay= chrono::seconds(5);
while (bchrono::steady_clock::now() - start <= delay) {}
#i</pre>
```

high_resolution_clock

When available, high_resolution_clock is usually more expensive than the other system-wide clocks, so they are used only when the provided resolution is required to the application.

process_cpu_clock

Process and thread clocks are used usually to measure the time spent by code blocks, as a basic time-spent profiling of different blocks of code (Boost.Stopwatch is a clear example of this use).

thread_clock

You can use thread_clock whenever you want to measure the time spent by the current thread. For example:

```
bchrono::thread_clock::time_point start=bchrono::thread_clock::now();
// ... do something ...

typedef bchrono::milliseconds ms;
ms d = bchrono::thread_clock::now() - start;
// d now holds the number of milliseconds from start to end.
std::cout << ms.count() << "ms\n";
the ap</pre>
```

If you need seconds with a floating-point representation you can do:



```
typedef bchrono::duration<double> sec; // seconds, stored with a double.
sec d = end - start;
std::cout << sec.count() << "s\n";
=#i</pre>
```

If you would like to programmatically inspect thread_clock::duration, you can get the representation type with thread_clock::rep, and the tick period with thread_clock::period (which should be a type ratio which has nested values ratio::num and ratio::den). The tick period of thread_clock is thread_clock::period::num / thread_clock::period::den seconds: 1/10000000000 in this case (1 billionth of a second), stored in a long long.

1/0

Any duration can be streamed out to a basic_ostream. The run-time value of the duration is formatted according to the rules and current format settings for duration::rep. This is followed by a single space and then the compile-time unit name of the duration. This unit name is built on the string returned from ratio_string<> and the data used to construct the duration_punct which was inserted into the stream's locale. If a duration_punct has not been inserted into the stream's locale, a default constructed duration_punct will be added to the stream's locale.

duration unit names come in two varieties: long and short. The default constructed duration_punct provides names in the long format. These names are English descriptions. Other languages are supported by constructing a duration_punct with the proper spellings for "hours", "minutes" and "seconds", and their abbreviations (for the short format). The short or long format can be easily chosen by streaming a duration_short() or duration_long() manipulator respectively.

A time_point is formatted by outputting its internal duration followed by a string that describes the time_point::clock epoch. This string will vary for each distinct clock, and for each implementation of the supplied clocks.

Example:



```
#include <iostream>
    #include <boost/chrono/chrono_io.hpp>
    int main()
        using namespace std;
        using namespace boost;
        namespace bchrono=boost::chrono;
        cout << "milliseconds(3) + microseconds(10) = "</pre>
              << bchrono::milliseconds(3) + bchrono::microseconds(10) << '\n';</pre>
        cout << "hours(3) + minutes(10) = "</pre>
              << bchrono::hours(3) + bchrono::minutes(10) << '\n';</pre>
        typedef bchrono::duration<long long, boost::ratio<1, 2500000000> > ClockTick;
        cout << "ClockTick(3) + bchrono::nanoseconds(10) =</pre>
              << ClockTick(3) + bchrono::nanoseconds(10) << '\n';</pre>
        cout << "\nSet cout to use short names:\n";</pre>
        cout << bchrono::duration_short;</pre>
        cout << "milliseconds(3) + microseconds(10) = "</pre>
              << bchrono::milliseconds(3) + bchrono::microseconds(10) << '\n';</pre>
        cout << "hours(3) + minutes(10) = "</pre>
              << bchrono::hours(3) + bchrono::minutes(10) << '\n';</pre>
        cout << "ClockTick(3) + nanoseconds(10) = "</pre>
              << ClockTick(3) + bchrono::nanoseconds(10) << '\n';</pre>
        cout << "\nsystem_clock::now() = " << bchrono::system_clock::now() << '\n';</pre>
    #ifdef BOOST_CHRONO_HAS_CLOCK_STEADY
        cout << "steady_clock::now() = " << bchrono::steady_clock::now() << '\n';</pre>
    #endif
        cout << "\nSet cout to use long names:\n"</pre>
                 << bchrono::duration_long
                 << "high_resolution_clock::now() = "</pre>
                 << bchrono::high_resolution_clock::now() << '\n';
        return 0;
fier">bchrono</phrase><phrase role="speci
```

The output could be

```
milliseconds(3) + microseconds(10) = 3010 microseconds
hours(3) + minutes(10) = 190 minutes
ClockTick(3) + nanoseconds(10) = 56 [1/5000000000]seconds

Set cout to use short names:
    milliseconds(3) + microseconds(10) = 3010 [mu]s
hours(3) + minutes(10) = 190 m
ClockTick(3) + nanoseconds(10) = 56 [1/5000000000]s

system_clock::now() = 129387415616250000 [1/10000000]s since Jan 1, 1970
monotonic_clock::now() = 37297387636417 ns since boot

Set cout to use long names:
    high_resolution_clock::now() = 37297387655134 nanoseconds since boot
nct</phrase>
```



Parsing a duration follows rules analogous to the duration converting constructor. A value and a unit (short or long) are read from the basic_istream. If the duration has an integral representation, then the value parsed must be exactly representable in the target duration (after conversion to the target duration units), else failbit is set. durations based on floating-point representations can be parsed using any units that do not cause overflow.

For example a stream containing "5000 milliseconds" can be parsed into seconds, but if the stream contains "5001 milliseconds", parsing into seconds will cause failbit to be set.

Example:

```
#include <boost/chrono/chrono_io.hpp>
    #include <sstream>
    #include <cassert>
    int main()
        using namespace std;
        namespace bchrono=boost::chrono;
        istringstream in("5000 milliseconds 4000 ms 3001 ms");
        bchrono::seconds d(0);
        in >> d;
        assert(in.good());
        assert(d == seconds(5));
        in >> d;
        assert(in.good());
        assert(d == seconds(4));
        in >> d;
        assert(in.fail());
        assert(d == seconds(4));
        return 0;
role="identifier">durat
```

Note that a duration failure may occur late in the parsing process. This means that the characters making up the failed parse in the stream are usually consumed despite the failure to successfully parse.

Parsing a time_point involves first parsing a duration and then parsing the epoch string. If the epoch string does not match that associated with time_point::clock then failbit will be set.

Example:



```
#include <boost/chrono/chrono_io.hpp>
    #include <sstream>
    #include <iostream>
    #include <cassert>
    int main()
        using namespace std;
        namespace bchrono=boost::chrono;
        bchrono::high_resolution_clock::time_point t0 = bchrono::high_resolution_clock::now();
        stringstream io;
        io << t0;
        bchrono::high_resolution_clock::time_point t1;
        io >> t1;
        assert(!io.fail());
        cout << io.str() << '\n';</pre>
        cout << t0 << '\n';
        cout << t1 << '\n';
        bchrono::high_resolution_clock::time_point t = bchrono::high_resolution_clock::now();
        cout << t << ' n';
        cout << "That took " << t - t0 << '\n';
        cout << "That took " << t - t1 << '\n';
        return 0;
>duration</phrase></code></
```

The output could be:

```
50908679121461 nanoseconds since boot
That took 649630 nanoseconds
a#
```

Here's a simple example to find out how many hours the computer has been up (on this platform):

```
#include <boost/chrono/chrono_io.hpp>
#include <iostream>

int main()
{
    using namespace std;
    using namespace boost;
    namespace bchrono=boost::chrono;

    typedef bchrono::time_point<bchrono::steady_clock, bchrono::duration<double, boost::raJ
tio<3600> >> T;
    T tp = bchrono::steady_clock::now();
    std::cout << tp << '\n';
    return 0;
}
h descriptions</pre>
```

The output could be:



```
17.8666 hours since boot
```

Examples

Duration

How you Override the Duration's Default Constructor

Next we show how to override the duration's default constructor to do anything you want (in this case set it to zero). All we need to do is to change the representation

```
namespace I_dont_like_the_default_duration_behavior {
template <class R>
class zero_default
public:
    typedef R rep;
private:
    rep rep_;
public:
    zero_default(rep i = 0) : rep_(i) {}
    operator rep() const {return rep_;}
    zero_default& operator+=(zero_default x) {rep_ += x.rep_; return *this;}
    zero_default& operator-=(zero_default x) {rep_ -= x.rep_; return *this;}
    zero_default& operator*=(zero_default x) {rep_ *= x.rep_; return *this;}
    zero_default& operator/=(zero_default x) {rep_ /= x.rep_; return *this;}
    zero_default operator+ () const {return *this;}
    zero_default operator- () const {return zero_default(-rep_);}
    zero_default& operator++()
                                      {++rep_; return *this;}
    zero_default operator++(int)
                                      {return zero_default(rep_++);}
    zero_default& operator--()
                                      {--rep_; return *this;}
    zero_default operator--(int)
                                     {return zero_default(rep_--);}
    friend \ zero\_default \ operator + (\ zero\_default \ x \ , \ zero\_default \ y) \ \ \{return \ x \ += \ y; \}
    friend zero_default operator-(zero_default x, zero_default y) {return x -= y;}
    friend zero_default operator*(zero_default x, zero_default y) {return x *= y;}
    friend zero_default operator/(zero_default x, zero_default y) {return x /= y;}
    friend bool operator==(zero_default x, zero_default y) {return x.rep_ == y.rep_;}
    friend bool operator!=(zero_default x, zero_default y) {return !(x == y);}
    friend bool operator< (zero_default x, zero_default y) {return x.rep_ < y.rep_;}</pre>
    friend bool operator <= (zero_default x, zero_default y) {return ! (y < x);}
    friend bool operator> (zero_default x, zero_default y) {return y < x;}</pre>
    friend bool operator>=(zero_default x, zero_default y) {return !(x < y);}</pre>
};
typedef bchrono::duration<zero_default<long long>, boost::nano
                                                                        > nanoseconds;
typedef bchrono::duration<zero_default<long long>, boost::micro
                                                                        > microseconds;
```



```
typedef bchrono::duration<zero_default<long long>, boost::milli > milliseconds;
typedef bchrono::duration<zero_default<long long> > seconds;
typedef bchrono::duration<zero_default<long long>, boost::ratio<60> > minutes;
typedef bchrono::duration<zero_default<long long>, boost::ratio<3600> > hours;
}
ase><phrase role="special">::</phrase><phrase J</pre>
```

Usage

```
using namespace I_dont_like_the_default_duration_behavior;

milliseconds ms;
std::cout << ms.count() << '\n';
enti</pre>
```

See the source file example/i_dont_like_the_default_duration_behavior.cpp

Saturating

A "saturating" signed integral type is developed. This type has +/- infinity and a NaN (like IEEE floating-point) but otherwise obeys signed integral arithmetic. This class is subsequently used as the template parameter Rep in bchrono::duration to demonstrate a duration class that does not silently ignore overflow.

See the source file example/saturating.cpp

xtime Conversions

Example round_up utility: converts d to To, rounding up for inexact conversions Being able to **easily** write this function is a major feature!

To demonstrate interaction with an xtime-like facility:



```
struct xtime
        long sec;
        unsigned long usec;
    template <class Rep, class Period>
    to_xtime_truncate(bchrono::duration<Rep, Period> d)
       xtime xt;
        xt.sec = static_cast<long>(bchrono::duration_cast<seconds>(d).count());
        xt.usec = static_cast<long>(bchrono::duration_cast<microJ
seconds>(d - seconds(xt.sec)).count());
       return xt;
    }
    template <class Rep, class Period>
    to_xtime_round_up(bchrono::duration<Rep, Period> d)
       xtime xt;
       xt.sec = static_cast<long>(bchrono::duration_cast<seconds>(d).count());
       xt.usec = static_cast<unsigned long>(round_up<bchrono::micro-
seconds>(d - bchrono::seconds(xt.sec)).count());
        return xt;
   microseconds
    from_xtime(xtime xt)
        return bchrono::seconds(xt.sec) + bchrono::microseconds(xt.usec);
    void print(xtime xt)
        std::cout << '{' << xt.sec << ',' << xt.usec << "}\n";
/code></link>#tion</phrase></code></
```

Usage

```
xtime xt = to_xtime_truncate(seconds(3) + bchrono::milliseconds(251));
print(xt);
bchrono::milliseconds ms = bchrono::duration_cast<bchrono::milliseconds>(from_xtime(xt));
std::cout << ms.count() << " milliseconds\n";
xt = to_xtime_round_up(ms);
print(xt);
xt = to_xtime_truncate(bchrono::seconds(3) + nanoseconds(999));
print(xt);
xt = to_xtime_round_up(bchrono::seconds(3) + nanoseconds(999));
print(xt);
er#>clock
```

See the source file xtime.cpp



Clocks

Cycle count

Users can easily create their own clocks, with both points in time and time durations which have a representation and precision of their own choosing. For example if there is a hardware counter which simply increments a count with each cycle of the cpu, one can very easily build clocks, time points and durations on top of that, using only a few tens of lines of code. Such systems can be used to call the time-sensitive threading API's such as sleep, wait on a condition variable, or wait for a mutex lock. The API proposed herein is not sensitive as to whether this is a 300MHz clock (with a 3 1/3 nanosecond tick period) or a 3GHz clock (with a tick period of 1/3 of a nanosecond). And the resulting code will be just as efficient as if the user wrote a special purpose clock cycle counter.

```
#include <boost/chrono.hpp>
    #include <boost/type_traits.hpp>
    #include <iostream>
    namespace bchrono=boost::chrono;
    template <long long speed>
    struct cycle_count
        typedef typename boost::__ratio_multiply__<boost::ratio<speed>, boost::mega>::type
            frequency; // Mhz
        typedef typename boost::__ratio_divide__<boost::ratio<1>, frequency>::type period;
        typedef long long rep;
        typedef bchrono::duration<rep, period> duration;
        typedef bchrono::time_point<cycle_count> time_point;
        static time_point now()
            static long long tick = 0;
            // return exact cycle count
            return time_point(duration(++tick)); // fake access to clock cycle count
    };
    template <long long speed>
    struct approx_cycle_count
        static const long long frequency = speed * 1000000; // MHz
        typedef nanoseconds duration;
        typedef duration::rep rep;
        typedef duration::period period;
        static const long long nanosec_per_sec = period::den;
        typedef bchrono::time_point<approx_cycle_count> time_point;
        static time_point now()
            static long long tick = 0;
            // return cycle count as an approximate number of nanoseconds
            // compute as if nanoseconds is only duration in the std::lib
            return time_point(duration(++tick * nanosec_per_sec / frequency));
    };
liseconds</phrase></code></link># << '\n';</pre>
 ٦
```

See the source file cycle_count.cpp



xtime_clock

This example demonstrates the use of a timeval-like struct to be used as the representation type for both duration and time_point.

```
class xtime {
private:
    long tv_sec;
    long tv_usec;
    void fixup() {
        if (tv_usec < 0) {</pre>
           tv_usec += 1000000;
            --tv_sec;
    explicit xtime(long sec, long usec) {
        tv_sec = sec;
        tv_usec = usec;
        if (tv_usec < 0 || tv_usec >= 1000000) {
            tv_sec += tv_usec / 1000000;
            tv_usec %= 1000000;
            fixup();
        }
    explicit xtime(long long usec) {
        tv_usec = static_cast<long>(usec % 1000000);
        tv_sec = static_cast<long>(usec / 1000000);
        fixup();
    // explicit
   operator long long() const {return static_cast<long long>(tv_sec) * 1000000 + tv_usec;}
    xtime& operator += (xtime rhs) {
        tv_sec += rhs.tv_sec;
        tv_usec += rhs.tv_usec;
        if (tv_usec >= 1000000) {
            tv_usec -= 1000000;
            ++tv_sec;
        return *this;
    xtime\& operator -= (xtime rhs)  {
        tv_sec -= rhs.tv_sec;
        tv_usec -= rhs.tv_usec;
        fixup();
        return *this;
    xtime& operator %= (xtime rhs) {
        long long t = tv_sec * 1000000 + tv_usec;
        long long r = rhs.tv_sec * 1000000 + rhs.tv_usec;
        t %= r;
        tv_sec = static_cast<long>(t / 1000000);
        tv_usec = static_cast<long>(t % 1000000);
        fixup();
        return *this;
```



```
friend xtime operator+(xtime x, xtime y) {return x += y;}
        friend xtime operator-(xtime x, xtime y) {return x -= y;}
        friend xtime operator%(xtime x, xtime y) {return x %= y;}
        friend bool operator==(xtime x, xtime y)
            { return (x.tv_sec == y.tv_sec && x.tv_usec == y.tv_usec); }
        friend bool operator<(xtime x, xtime y) {</pre>
            if (x.tv_sec == y.tv_sec)
                return (x.tv_usec < y.tv_usec);</pre>
            return (x.tv_sec < y.tv_sec);</pre>
        friend bool operator!=(xtime x, xtime y) { return !(x == y); }
        friend bool operator> (xtime x, xtime y) \{ return y < x; \}
        friend bool operator<=(xtime x, xtime y) { return !(y < x); }</pre>
        friend bool operator>=(xtime x, xtime y) { return !(x < y); }
        friend std::ostream& operator<<(std::ostream& os, xtime x)</pre>
            {return os << '{' << x.tv_sec << ',' << x.tv_usec << '}';}
boost</phrase><phrase role="special">::</phrase><code><phrase role="identifier">
```

Clock based on timeval-like struct.

```
class xtime_clock
    public:
        typedef xtime
                                                        rep;
        typedef boost::micro
                                                        period;
        typedef bchrono::duration<rep, period> duration;
        typedef bchrono::time_point<xtime_clock> time_point;
        static time_point now()
        #if defined(BOOST_CHRONO_WINDOWS_API)
            time_point t(duration(xtime(0)));
            gettimeofday((timeval*)&t, 0);
            return t;
        #elif defined(BOOST_CHRONO_MAC_API)
            time_point t(duration(xtime(0)));
            gettimeofday((timeval*)&t, 0);
            return t;
        #elif defined(BOOST_CHRONO_POSIX_API)
            //time_point t(0,0);
            timespec ts;
            ::clock_gettime( CLOCK_REALTIME, &ts );
            xtime xt( ts.tv_sec, ts.tv_nsec/1000);
            return time_point(duration(xt));
        #endif // POSIX
cial#>::</phrase>#only 23 bits to
```



Usage of xtime_clock

```
std::cout << "sizeof xtime_clock::time_point = " << sizeof(xtime_clock::time_point) << '\n';
std::cout << "sizeof xtime_clock::duration = " << sizeof(xtime_clock::duration) << '\n';
std::cout << "sizeof xtime_clock::rep = " << sizeof(xtime_clock::rep) << '\n';
xtime_clock::duration delay(bchrono::milliseconds(5));
xtime_clock::time_point start = xtime_clock::now();
while (xtime_clock::now() - start <= delay) {}
xtime_clock::time_point stop = xtime_clock::now();
xtime_clock::duration elapsed = stop - start;
std::cout << "paused " << bchrono::::nanoseconds(elapsed).count() << " nanoseconds\n";
target #</pre>
```

See the source file example/timeval_demo.cpp

Time Point

min Utility

The user can define a function returning the earliest time_point as follows:

Being able to easily write this function is a major feature!

```
BOOST_AUTO(t1, system_clock::now() + seconds(3));
BOOST_AUTO(t2, system_clock::now() + nanoseconds(3));
BOOST_AUTO(t3, min(t1, t2));
Clo
```

See the source file example/min_time_point.cpp



A Tiny Program that Times How Long Until a Key is Struck

```
#include <boost/chrono.hpp>
#include <iostream>
#include <iomanip>
using namespace boost::chrono;
template< class Clock >
class timer
  typename Clock::time_point start;
public:
 timer() : start( Clock::now() ) {}
  typename Clock::duration elapsed() const
    return Clock::now() - start;
  double seconds() const
    return elapsed().count() * ((double)Clock::period::num/Clock::period::den);
};
int main()
  timer<system_clock> t1;
  timer<steady_clock> t2;
  timer<high_resolution_clock> t3;
  std::cout << "Type the Enter key: ";</pre>
  std::cin.get();
  std::cout << std::fixed << std::setprecision(9);</pre>
  std::cout << "system_clock-----: "</pre>
            << t1.seconds() << " seconds\n";
  std::cout << "steady_clock----: "</pre>
            << t2.seconds() << " seconds\n";
  std::cout << "high_resolution_clock--:</pre>
            << t3.seconds() << " seconds\n";
  system_clock::time_point d4 = system_clock::now();
  system_clock::time_point d5 = system_clock::now();
  std::cout << "\nsystem_clock latency-----: " << (d5 - d4).count() << std::endl;
  steady_clock::time_point d6 = steady_clock::now();
  steady_clock::time_point d7 = steady_clock::now();
  std::cout << "steady_clock latency-----: " << (d7 - d6).count() << std::endl;</pre>
  high_resolution_clock::time_point d8 = high_resolution_clock::now();
  high_resolution_clock::time_point d9 = high_resolution_clock::now();
  std::cout << "high_resolution_clock latency--: " << (d9 - d8).count() << std::endl;
  std::time_t now = system_clock::to_time_t(system_clock::now());
```



The output of this program run looks like this:

See the source file example/await_keystroke.cpp

24 Hours Display

In the example above we take advantage of the fact that time_points convert as long as they have the same clock, and as long as their internal durations convert. We also take advantage of the fact that a duration with a floating-point representation will convert from anything. Finally the I/O system discovers the more readable "hours" unit for our duration<double, ratio<3600>>.

There are many other ways to format durations and time_points. For example see ISO 8601. Instead of coding every possibility into operator<<, which would lead to significant code bloat for even the most trivial uses, this document seeks to inform the reader how to write custom I/O when desired.

As an example, the function below streams arbitrary durations to arbitrary basic_ostreams using the format:

```
[-]d/hh:mm:ss.cc
```

Where:

- d is the number of days
- h is the number of hours
- m is the number of minutes
- ss.cc is the number of seconds rounded to the nearest hundreth of a second
 - 1. include <boost/chrono/chrono_io.hpp>
 - 2. include <ostream>
 - include <iostream>



```
// format duration as [-]d/hh::mm::ss.cc
template <class CharT, class Traits, class Rep, class Period>
std::basic_ostream<CharT, Traits>&
display(std::basic_ostream<CharT, Traits>& os,
        bchrono::duration<Rep, Period> d)
    using namespace std;
    using namespace boost;
    namespace bchrono=boost::chrono;
    typedef bchrono::duration<long long, boost::ratio<86400> > days;
    typedef bchrono::duration<long long, boost:centi> centiseconds;
    // if negative, print negative sign and negate
    if (d < bchrono::duration<Rep, Period>(0))
        d = -di
        os << '-';
    // round d to nearest centiseconds, to even on tie
    centiseconds cs = bchrono::duration_cast<centiseconds>(d);
    if (d - cs > bchrono::milliseconds(5)
        | | (d - cs == bchrono::milliseconds(5) && cs.count() & 1))
        ++cs;
    // separate seconds from centiseconds
    bchrono::seconds s = bchrono::duration_cast<br/>bchrono::seconds>(cs);
    cs -= s;
    // separate minutes from seconds
    bchrono::minutes m = bchrono::duration_cast<bchrono::minutes>(s);
    // separate hours from minutes
    bchrono::hours h = bchrono::duration_cast<bchrono::hours>(m);
    m -= h;
    // separate days from hours
    days dy = bchrono::duration_cast<days>(h);
    h = dy;
    // print d/hh:mm:ss.cc
    os << dy.count() << '/';
    if (h < bchrono::hours(10))</pre>
       os << '0';
    os << h.count() << ':';
    if (m < bchrono::minutes(10))</pre>
       os << '0';
    os << m.count() << ':';
    if (s < bchrono::seconds(10))</pre>
       os << '0';
    os << s.count() << '.';
    if (cs < bchrono::centiseconds(10))</pre>
       os << '0';
    os << cs.count();
    return os;
int main()
    using namespace std;
    using namespace boost;
    namespace bchrono=boost::chrono;
    display(cout, bchrono::steady_clock::now().time_since_epoch()
```



```
+ bchrono::duration<long, boost::mega>(1)) << '\n';
display(cout, -bchrono::milliseconds(6)) << '\n';
display(cout, bchrono::duration<long, boost::mega>(1)) << '\n';
display(cout, -bchrono::duration<long, boost::mega>(1)) << '\n';
}
nt"><code><phrase role="identifier#>time_point</phrase></code></l>
```

The output could be:

```
12/06:03:22.95
-0/00:00:00.01
11/13:46:40.00
-11/13:46:40.00
se>#
```

Simulated Thread Interface Demonstration Program

The C++0x standard library's multi-threading library requires the ability to deal with the representation of time in a manner consistent with modern C++ practices. Next is a simulation of this interface.

The non-member sleep functions can be emulated as follows:

```
namespace boost { namespace this_thread {
 template <class Rep, class Period>
 void sleep_for(const chrono::duration<Rep, Period>& d) {
     chrono::microseconds t = chrono::duration_cast<chrono::microseconds>(d);
     if (t < d)
         ++t;
     if (t > chrono::microseconds(0))
         std::cout << "sleep_for " << t.count() << " microseconds\n";</pre>
 template <class Clock, class Duration>
 void sleep_until(const chrono::time_point<Clock, Duration>& t) {
     using namespace chrono;
     typedef time_point<Clock, Duration> Time;
     typedef system_clock::time_point SysTime;
     if (t > Clock::now()) {
         typedef typename common_type<typename Time::duration,
                                       typename SysTime::duration>::type D;
         /* auto */ D d = t - Clock::now();
         microseconds us = duration_cast<microseconds>(d);
         if (us < d)
             ++us;
         SysTime st = system_clock::now() + us;
         std::cout << "sleep_until</pre>
         detail::print_time(st);
        std::cout << " which is " << (st - system_clock::now()).count() << " microseconds away\n";
 }
 } }
bchrono::hours h = bchrono::
```

Next is the boost::thread::timed_mutex modified fuctions



```
{\tt namespace\ boost\ }\{
    struct timed_mutex {
        // ...
        template <class Rep, class Period>
        bool try_lock_for(const chrono::duration<Rep, Period>& d) {
            chrono::microseconds t = chrono::duration_cast<chrono::microseconds>(d);
            if (t <= chrono::microseconds(0))</pre>
                return try_lock();
            std::cout << "try_lock_for " << t.count() << " microseconds\n";</pre>
            return true;
        template <class Clock, class Duration>
        bool \ try_lock_until(const \ chrono::time_point < Clock, \ Duration > \& \ t)
            using namespace chrono;
            typedef time_point<Clock, Duration> Time;
            typedef system_clock::time_point SysTime;
            if (t <= Clock::now())</pre>
                return try_lock();
            typedef typename common_type<typename Time::duration,</pre>
              typename Clock::duration>::type D;
             /* auto */ D d = t - Clock::now();
            microseconds us = duration_cast<microseconds>(d);
            SysTime st = system_clock::now() + us;
            std::cout << "try_lock_until ";</pre>
            detail::print_time(st);
            std::cout << " which is " << (st - system_clock::now()).count()</pre>
              << " microseconds away\n";
            return true;
    };
e days from hours
        days dy ↓
```

boost::thread::condition_variable time related function are modified as follows:



```
namespace boost {
 struct condition_variable
      // ...
      template <class Rep, class Period>
      bool wait_for(mutex&, const chrono::duration<Rep, Period>& d) {
          chrono::microseconds t = chrono::duration_cast<chrono::microseconds>(d);
          std::cout << "wait_for " << t.count() << " microseconds\n";</pre>
          return true;
      template <class Clock, class Duration>
      bool wait_until(mutex&, const chrono::time_point<Clock, Duration>& t) {
          using namespace boost::chrono;
          typedef time_point<Clock, Duration> Time;
          typedef system_clock::time_point SysTime;
          if (t <= Clock::now())</pre>
              return false;
          typedef typename common_type<typename Time::duration,
            typename Clock::duration>::type D;
          /* auto */ D d = t - Clock::now();
          microseconds us = duration_cast<microseconds>(d);
          SysTime st = system_clock::now() + us;
           std::cout << "wait_until</pre>
          detail::print_time(st);
          std::cout << " which is " << (st - system_clock::now()).count()</pre>
           << " microseconds away\n";
          return true;
  };
<< " microseconds away\n";
 ┙
```

Next follows how simple is the usage of this functions:

```
boost::mutex m;
   boost::timed_mutex mut;
   boost::condition_variable cv;
   using namespace boost;
    this_thread::sleep_for(chrono::seconds(3));
    this_thread::sleep_for(chrono::nanoseconds(300));
    chrono::system_clock::time_point time_limit = chrono::sys↓
tem_clock::now() + chrono::__seconds_(4) + chrono::milliseconds(500);
    this_thread::sleep_until(time_limit);
    mut.try_lock_for(chrono::milliseconds(30));
   mut.try_lock_until(time_limit);
    cv.wait_for(m, chrono::minutes(1)); // real code would put this in a loop
    cv.wait_until(m, time_limit); // real code would put this in a loop
    // For those who prefer floating-point
    this_thread::sleep_for(chrono::duration<double>(0.25));
    this_thread::sleep_until(chrono::system_clock::now() + chrono::duration<double>(1.5));
ase role=#identifier
```



See the source file example/simulated_thread_interface_demo.cpp

10

Example use of output in French

```
#include <boost/chrono/chrono_io.hpp>
    #include <iostream>
    #include <locale>
    int main()
        using namespace std;
        using namespace boost;
        using namespace boost::chrono;
        cout.imbue(locale(locale(), new duration_punct<char>
                duration_punct<char>::use_long,
                "secondes", "minutes", "heures",
                "s", "m", "h"
            )));
        hours h(5);
        minutes m(45);
        seconds s(15);
        milliseconds ms(763);
        cout << h << ", " << m << ", " << s << " et " << ms << '\n';
<phrase role=#identifi</pre>
```

Output is:

```
5 heures, 45 minutes, 15 secondes et 763 millisecondes
n
```

See the source file example/french.cpp

External Resources

C++ Standards Committee's current Working Paper

The most authoritative reference material for the library is the C++ Standards Committee's current Working Paper (WP). 20.11 Time utilities "time"

N2661 - A Foundation to Sleep On

From Howard E. Hinnant, Walter E. Brown, Jeff Garland and Marc Paterno. Is very informative and provides motivation for key design decisions

LGW 934. duration is missing operator%

From Terry Golubiewski. Is very informative and provides motivation for key design decisions

LGW 935. clock error handling needs to be specified

From Beman Dawes. This issue has been stated as NAD Future.

Reference

As constexpr will not be supported by some compilers, it is replaced in the code by BOOST_CHRONO_CONSTEXPR for constexpr functions and BOOST_CHRONO_STATIC_CONSTEXPR for struct/class static fields. The documentation doesn't use these macros.



Included on the C++0x Recommendation

Header <boost/chrono.hpp>

```
#include <boost/chrono/duration.hpp>
#include <boost/chrono/time_point.hpp>
#include <boost/chrono/system_clocks.hpp>
#include <boost/chrono/typeof/boost/chrono/chrono.hpp>
se r
```

Limitations and Extensions

Next follows limitation respect to the C++0x recomendations:

- · constexpr not tested yet.
- The recently steady_clock approved is not yet included.

The current implementation provides in addition:

- clock error handling as specified in clock error handling needs to be specified.
- process and thread clocks.

Configuration Macros

How Assert Behaves?

When BOOST_NO_STATIC_ASSERT is defined, the user can select the way static assertions are reported. Define

- BOOST_CHRONO_USES_STATIC_ASSERT: define it if you want to use Boost.StaticAssert.
- BOOST_CHRONO_USES_MPL_ASSERT: define it if you want to use Boost.MPL static asertions.
- BOOST_CHRONO_USES_ARRAY_ASSERT: define it if you want to use internal static asertions.

The default behavior is as BOOST_CHRONO_USES_ARRAY_ASSERT was defined.

When BOOST_CHRONO_USES_MPL_ASSERT is not defined the following symbols are defined as

```
#define BOOST_CHRONO_A_DURATION_REPRESENTATION_CAN_NOT_BE_A_DURATION \
    "A duration representation can not be a duration"
#define BOOST_CHRONO_SECOND_TEMPLATE_PARAMETER_OF_DURATION_MUST_BE_A_STD_RATIO \
    "Second template parameter of duration must be a boost::ratio"
#define BOOST_CHRONO_DURATION_PERIOD_MUST_BE_POSITIVE \
    "duration period must be positive"
#define BOOST_CHRONO_SECOND_TEMPLATE_PARAMETER_OF_TIME_POINT_MUST_BE_A_BOOST_CHRONO_DURATION \
    "Second template parameter of time_point must be a bchrono::duration"
/code>
```

Depending on the static assertion used system you will have an hint of the failing assertion either through the symbol or through the text.

How to Build Boost.Chrono as a Header Only Library?

When BOOST_CHRONO_INLINED is defined the lib is header-only.



If in addition BOOST_USE_WINDOWS_H is defined <windows.h> is included, otherwise files in boost/detail/win are used to reduce the impact of including <windows.h>.

Header chrono/duration.hpp>

This file contains duration specific classes and non-member functions.

```
namespace boost {
 namespace chrono
    template <class Rep, class Period = ratio<1> > class duration;
 template <class Rep1, class Period1, class Rep2, class Period2>
 struct common_type<duration<Rep1, Period1>,
                     duration<Rep2, Period2> >;
 namespace chrono {
    // customization traits
    template <class Rep> struct treat_as_floating_point;
    template <class Rep> struct duration_values;
    // duration arithmetic
    template <class Rep1, class Period1, class Rep2, class Period2>
    typename common_type<duration<Rep1, Period1>, duration<Rep2, Period2> >::type
    operator+(
        const duration<Rep1, Period1>& lhs,
        const duration<Rep2, Period2>& rhs);
    template <class Rep1, class Period1, class Rep2, class Period2>
    typename common_type<duration<Rep1, Period1>, duration<Rep2, Period2> >::type
    operator-(
       const duration<Rep1, Period1>& lhs,
       const duration<Rep2, Period2>& rhs);
    template <class Rep1, class Period, class Rep2>
    duration<typename common_type<Rep1, Rep2>::type, Period>
    operator*(
       const duration<Rep1, Period>& d,
       const Rep2& s);
    template <class Rep1, class Period, class Rep2>
    duration<typename common_type<Rep1, Rep2>::type, Period>
    operator*(
       const Rep1& s,
       const duration<Rep2, Period>& d);
    template <class Rep1, class Period, class Rep2>
    duration<typename common_type<Rep1, Rep2>::type, Period>
    operator/(
       const duration<Rep1, Period>& d,
       const Rep2& s);
    template <class Rep1, class Period1, class Rep2, class Period2>
    typename common_type<Rep1, Rep2>::type
    operator/(
       const duration<Rep1, Period1>& lhs,
       const duration<Rep2, Period2>& rhs);
    #ifdef BOOST_CHRONO_EXTENSIONS
```



```
// Used to get frecuency of events
        template <class Rep1, class Rep2, class Period>
        double operator/(
            const Repl& s,
            const duration<Rep2, Period>& d);
        #endif
        // duration comparisons
        template <class Rep1, class Period1, class Rep2, class Period2>
        constexpr bool operator==(
            const duration<Rep1, Period1>& lhs,
            const duration<Rep2, Period2>& rhs);
        template <class Rep1, class Period1, class Rep2, class Period2>
        constexpr bool operator!=(
            const duration<Rep1, Period1>& lhs,
            const duration<Rep2, Period2>& rhs);
        template <class Rep1, class Period1, class Rep2, class Period2>
        constexpr bool operator<(</pre>
            const duration<Rep1, Period1>& lhs,
            const duration<Rep2, Period2>& rhs);
        template <class Rep1, class Period1, class Rep2, class Period2>
        constexpr bool operator<=(</pre>
            const duration<Rep1, Period1>& lhs,
            const duration<Rep2, Period2>& rhs);
        template <class Rep1, class Period1, class Rep2, class Period2>
        constexpr bool operator> (
           const duration<Rep1, Period1>& lhs,
            const duration<Rep2, Period2>& rhs);
        template <class Rep1, class Period1, class Rep2, class Period2>
        constexpr bool operator>=(
            const duration<Rep1, Period1>& lhs,
            const duration<Rep2, Period2>& rhs);
        // duration_cast
        template <class ToDuration, class Rep, class Period>
        ToDuration duration_cast(const duration<Rep, Period>& d);
        // convenience typedefs
                                                                      // at least 64 bits needed
        typedef duration<boost::int_least64_t, nano> nanoseconds;
        typedef duration<boost::int_least64_t, micro> microseconds; // at least 55 bits needed
        typedef duration<boost::int_least64_t, milli> milliseconds; // at least 45 bits needed
        typedef duration<boost::int_least64_t> seconds;
                                                                      // at least 35 bits needed
        typedef duration<boost::int_least32_t, ratio< 60> > minutes; // at least 29 bits needed
        typedef duration<boost::int_least32_t, ratio<3600> > hours; // at least 23 bits needed
rase role="special">}</phrase>
<phrase role="special">&lt;</phrase><phrase role="identifier">phrase</phra</pre>
```

Time-related Traits

Metafunction treat_as_floating_point<>



The duration template uses the treat_as_floating_point trait to help determine if a duration with one tick period can be converted to another duration with a different tick period. If treat_as_floating_point<Rep>::value is true, then Rep is a floating-point type and implicit conversions are allowed among durations. Otherwise, the implicit convertibility depends on the tick periods of the durations. If Rep is a class type which emulates a floating-point type, the author of Rep can specialize treat_as_floating_point so that duration will treat this Rep as if it were a floating-point type. Otherwise Rep is assumed to be an integral type, or a class emulating an integral type.

Class Template duration_values

The duration template uses the duration_values trait to construct special values of the duration's representation (Rep). This is done because the representation might be a class type with behavior which requires some other implementation to return these special values. In that case, the author of that class type should specialize duration_values to return the indicated values.

Static Member Function zero()

```
static constexpr Rep zero();
t
```

Returns: Rep(0). **Note:** Rep(0) is specified instead of Rep() since Rep() may have some other meaning, such as an uninitialized value.

Remarks: The value returned corresponds to the additive identity.

Static Member Function max()

```
static constexpr Rep max();
h
```

Returns: numeric_limits<Rep>::max().

Remarks: The value returned compares greater than zero().

Static Member Function min()

```
static constexpr Rep min();
```

Returns: numeric_limits<Rep>::lowest().

Remarks: The value returned compares less than or equal to zero().



common_type Specialization

```
template <class Rep1, class Period1, class Rep2, class Period2>
struct common_type<chrono::duration<Rep1, Period1>, chrono::duration<Rep2, Period2> >
{
    typedef chrono::duration<typename common_type<Rep1, Rep2>::type, see bellow> type;
};
alues
```

The period of the duration indicated by this specialization of common_type is the greatest common divisor of Period1 and Period2. This can be computed by forming a ratio of the greatest common divisor of Period1::num and Period2::num, and the least common multiple of Period1::den and Period2::den.

Note: The typedef type is the <u>duration</u> with the largest tick period possible where both <u>duration</u> arguments will convert to it without requiring a division operation. The representation of this type is intended to be able to hold any value resulting from this conversion, with the possible exception of round-off error when floating-point <u>durations</u> are involved (but not truncation error).

Class Template duration<>

A duration measures time between two points in time (time_point). A duration has a representation which holds a count of ticks, and a tick period. The tick period is the amount of time which occurs from one tick to another in units of a second. It is expressed as a rational constant using ratio.



```
namespace boost { namespace chrono {
        template <class Rep, class Period>
        class duration {
        public:
            typedef Rep rep;
            typedef Period period;
        private:
            rep rep_; // exposition only
        public:
            constexpr duration();
            template <class Rep2>
            constexpr explicit duration(const Rep2& r);
            template <class Rep2, class Period2>
            constexpr duration(const duration<Rep2, Period2>& d);
            duration& operator=(const duration&) = default;
            constexpr rep count() const;
            constexpr duration operator+();
            constexpr duration operator-();
            duration& operator++();
            duration operator++(int);
            duration& operator--();
            duration operator -- (int);
            duration& operator+=(const duration& d);
            duration& operator-=(const duration& d);
            duration& operator*=(const rep& rhs);
            duration& operator/=(const rep& rhs);
            duration& operator%=(const rep& rhs);
            duration& operator%=(const duration& rhs);
            static constexpr duration zero();
            static constexpr duration min();
            static constexpr duration max();
        };
le="identifier">Rep2</phrase><phrase role=</pre>
```

Rep must be an arithmetic type, or a class emulating an arithmetic type, compile diagnostic otherwise. If duration is instantiated with the type of Rep being a duration, compile diagnostic is issued.

Period must be an instantiation of ratio, compile diagnostic otherwise.

Period::num must be positive, compile diagnostic otherwise.

Examples:

- duration<long, ratio<60> > holds a count of minutes using a long.
- duration<long long, milli> holds a count of milliseconds using a long long.
- duration<double, ratio<1, 30> > holds a count using a double with a tick period of 1/30 second (a tick frequency of 30 Hz).



The following members of duration do not throw an exception unless the indicated operations on the representations throw an exception.

Constructor duration(const Rep2&)

```
template <class Rep2>
  constexpr explicit duration(const Rep2& r);
n#
```

Remarks: Rep2 is implicitly convertible to rep, and

- treat_as_floating_point<rep>::value is true, or
- !treat_as_floating_point<rep>::value && !treat_as_floating_point<Rep2>::value is true.

If these constraints are not met, this constructor will not participate in overload resolution. **Note:** This requirement prevents construction of an integral-based duration with a floating-point representation. Such a construction could easily lead to confusion about the value of the duration.

Example:

```
duration<int, milli> d(3.5); // do not compile
  duration<int, milli> d(3); // ok
se
```

Effects: Constructs an object of type duration.

PostConditions: count() == static_cast<rep>(r).

Constructor duration(const duration&)

```
template <class Rep2, class Period2>
constexpr duration(const duration<Rep2, Period2>& d);
```

Remarks: treat_as_floating_point<rep>::value,orratio_divide<Period2, period>::type::den == 1,else this constructor will not participate in overload resolution. **note** This requirement prevents implicit truncation error when converting between integral-based durations. Such a construction could easily lead to confusion about the value of the duration.

Example:

```
duration<int, milli> ms(3);
  duration<int, micro> us = ms; // ok
  duration<int, milli> ms2 = us; // do not compile
=#s
```

Effects: Constructs an object of type duration, constructing rep_from duration_cast<duration>(d).count().

Member Function count() const

```
constexpr rep count() const;
h
```



Returns: rep_.

Member Function operator+() const

```
constexpr duration operator+() const;
#
```

Returns: *this.

Member Function operator-() const

```
constexpr duration operator-() const;
#
```

Returns: duration(-rep_).

Member Function operator++()

```
duration& operator++();
```

Effects: ++rep_.

Returns: *this.

Member Function operator++(int)

```
duration operator++(int);
p
```

Returns: duration(rep_++).

Member Function operator--()

```
duration& operator--();
;
```

Effects: --rep_.

Returns: *this.

Member Function operator--(int)

```
duration operator--(int);
```

Returns: duration(rep_--).



Member Function operator+=(const duration&)

```
duration& operator+=(const duration& d);
#
```

Effects: rep_ += d.count().

Returns: *this.

Member Function operator == (const duration&)

```
duration& operator-=(const duration& d);
#
```

Effects: rep_ -= d.count().

Returns: *this.

Member Function operator%=(const duration&)

```
duration& operator%=(const duration& d);
#
```

Effects: rep_ %= d.count().

Returns: *this.

Member Function operator*=(const rep&)

```
duration& operator*=(const rep& rhs);
#
```

Effects: rep_ *= rhs.

Returns: *this.

Member Function operator/=(const rep&)

```
duration& operator/=(const rep& rhs);
#
```

Effects: rep_ /= rhs.

Returns: *this.

Member Function operator%=(const rep&)

```
duration& operator%=(const rep& rhs);
#
```

Effects: rep_ %= rhs.



Returns: *this.

Static Member Function zero()

```
static constexpr duration zero();
>
```

Returns: duration(duration_values<rep>::zero()).

Static Member Function min()

```
static constexpr duration min();
s
```

Returns: duration(duration_values<rep>::min()).

Static Member Function max()

```
static constexpr duration max();
s
```

Returns: duration(duration_values<rep>::max()).

duration Non-Member Arithmetic

Non-Member Function operator+(duration, duration)

```
template <class Rep1, class Period1, class Rep2, class Period2>
  typename common_type<duration<Rep1, Period1>, duration<Rep2, Period2> >::type
  operator+(const duration<Rep1, Period1>& lhs, const duration<Rep2, Period2>& rhs);
hra
```

Returns: CD(lhs) += rhs where CD is the type of the return value.

Non-Member Function operator-(duration, duration)

```
template <class Rep1, class Period1, class Rep2, class Period2>
  typename common_type<duration<Rep1, Period1>, duration<Rep2, Period2> >::type
  operator-(const duration<Rep1, Period1>& lhs, const duration<Rep2, Period2>& rhs);
hra
```

Returns: CD(lhs) -= rhs where CD is the type of the return value.

```
template <class Rep1, class Period, class Rep2>
duration<typename common_type<Rep1, Rep2>::type, Period>
operator*(const duration<Rep1, Period>& d, const Rep2& s);
se 

J
```

Requires: Let CR represent the common_type of Rep1 and Rep2. This function will not participate in overload resolution unless both Rep1 and Rep2 are implicitly convertible to CR.



Returns: duration<CR, Period>(d) *= s.

Non-Member Function operator*(Rep1,duration)

```
template <class Rep1, class Period, class Rep2>
  duration<typename common_type<Rep1, Rep2>::type, Period>
  operator*(const Rep1& s, const duration<Rep2, Period>& d);
ase
```

Requires: Let CR represent the common_type of Rep1 and Rep2. This function will not participate in overload resolution unless both Rep1 and Rep2 are implicitly convertible to CR.

Returns: d * s.

Non-Member Function operator/(duration, Rep2)

```
template <class Rep1, class Period, class Rep2>
  duration<typename common_type<Rep1, Rep2>::type, Period>
  operator/(const duration<Rep1, Period>& d, const Rep2& s);
/ph
```

Requires: Let CR represent the common_type of Rep1 and Rep2. This function will not participate in overload resolution unless both Rep1 and Rep2 are implicitly convertible to CR, and Rep2 is not an instantiation of duration.

Returns: duration<CR, Period>(d) /= s.

Non-Member Function operator/(duration,duration)

```
template <class Rep1, class Period1, class Rep2, class Period2>
  typename common_type<Rep1, Rep2>::type
  operator/(const duration<Rep1, Period1>& lhs, const duration<Rep2, Period2>& rhs);
e=#
```

Returns: Let CD represent the common_type of the two duration arguments. Returns CD(lhs).count() / CD(rhs).count().

Non-Member Function operator/(Rep1,duration)

Included only if BOOST_CHRONO_EXTENSIONS is defined.

This overloading could be used to get the frequency of an event counted by Rep1.

```
template <class Rep1, class Rep2, class Period>
  double operator/(const Rep1& s, const duration<Rep2, Period>& d);
de
```

Remarks: Let CR represent the common_type of Rep1 and Rep2. This function will not participate in overload resolution unless both Rep1 and Rep2 are implicitly convertible to CR, and Rep1 is not an instantiation of duration.

Returns: CR(s)/duration<CR, Period>(d).count().



Non-Member Function operator%(duration,Rep2)

```
template <class Rep1, class Period, class Rep2>
duration<typename common_type<Rep1, Rep2>::type, Period>
operator%(const duration<Rep1, Period>& d, const Rep2& s);
Rep
```

Remarks This function will not participate in overload resolution unless Rep2 must be implicitly convertible to CR(Rep1, Rep2) and Rep2 must not be an instantiation of duration.

Returns: duration<CR(Rep1,Rep2), Period>(d) %= s.

Non-Member Function operator%(duration,duration)

Remarks This function will not participate in overload resolution unless

Returns: CD(lhs) %= CD(rhs)

duration Non-Member Comparaisons

Non-Member Function operator==(duration,duration)

Returns: Let CD represent the common_type of the two duration arguments. Returns CD(lhs).count() == CD(rhs).count()

Non-Member Function operator!=(duration,duration)

Returns: !(lhs == rhs).

Non-Member Function operator<(duration,duration)

Returns: Let CD represent the common_type of the two duration arguments. Returns CD(lhs).count() < CD(rhs).count()



Non-Member Function operator<=(duration,duration)

Returns: !(rhs < lhs).

Non-Member Function operator>(duration, duration)

Returns: rhs < lhs.

Non-Member Function operator>=(duration,duration)

Returns: !(lhs < rhs).

Non-Member Function duration_cast(duration)

```
template <class ToDuration, class Rep, class Period>
  ToDuration duration_cast(const duration<Rep, Period>& d);
c
```

Requires: This function will not participate in overload resolution unless ToDuration is an instantiation of duration.

Returns: Forms CF which is a ratio resulting from ratio_divide<Period, typename ToDuration::period>::type. Let CR be the common_type of ToDuration::rep, Rep, and intmax_t.

- If CF::num == 1 and CF::den == 1, then returns ToDuration(static_cast<typename ToDuration::rep>(d.count()))
- else if CF::num != 1 and CF::den == 1, then returns ToDuration(static_cast<typename ToDuration::rep>(static_cast<CR>(d.count()) * static_cast<CR>(CF::num)))
- else if CF::num == 1 and CF::den != 1, then returns ToDuration(static_cast<typename ToDuration::rep>(static_cast<CR>(d.count()) / static_cast<CR>(CF::den)))
- else returns ToDuration(static_cast<typename ToDuration::rep>(static_cast<CR>(d.count()) * static_cast<CR>(CF::num) / static_cast<CR>(CF::den)))

Remarks: This function does not rely on any implicit conversions. All conversions must be accomplished through static_cast. The implementation avoids all multiplications or divisions when it is known at compile-time that it can be avoided because one or more arguments are 1. All intermediate computations are carried out in the widest possible representation and only converted to the destination representation at the final step.



duration typedefs

Clock Requirements

A clock represents a bundle consisting of a duration, a time_point, and a function now() to get the current time_point. A clock must meet the requirements in the following Table.

In this table C1 and C2 denote clock types. t1 and t2 are values returned from C1::now() where the call returning t1 happens before the call returning t2 and both of these calls happen before C1::time_point::max().

Table 1. Clock Requirements

| expression | return type | operational semantics | |
|----------------|--|--|--|
| C1::rep | An arithmetic type or class emulating an arithmetic type. | The representation type of the duration and time_point. | |
| C1::period | ratio | The tick period of the clock in seconds. | |
| C1::duration | <pre>chrono::duration<c1::rep, c1::period=""></c1::rep,></pre> | The duration type of the clock. | |
| C1::time_point | <pre>chrono::time_point<cl></cl></pre> | The time_point type of the clock. Different clocks are permitted to share a time_point definition if it is valid to compare their time_points by comparing their respective durations. C1 and C2 must refer to the same epoch. | |
| C1::is_steady | constexpr bool | true if t1 <= t2 is always true, else false. Note : A clock that can be adjusted backwards is not steady | |
| C1::now() | C1::time_point | Returns a time_point representing the current point in time. | |

Models of Clock:

- system_clock
- steady_clock
- high_resolution_clock
- process_real_cpu_clock
- process_user_cpu_clock
- process_system_cpu_clock
- thread_clock



Header <boost/chrono/time_point.hpp>

This file contains time_point specific classes and non-member functions.

```
namespace boost {
 namespace chrono {
    template <class Clock, class Duration = typename Clock::duration> class time_point;
  template <class Clock, class Duration1, class Duration2>
 struct common_type<time_point<Clock, Duration1>,
                     time_point<Clock, Duration2> >;
 namespace chrono {
    // time_point arithmetic
    template <class Clock, class Duration1, class Rep2, class Period2>
    time_point<Clock, typename common_type<Duration1, duration<Rep2, Period2> >::type>
   operator+(const time_point<Clock, Duration1>& lhs, const duration<Rep2, Period2>& rhs);
    template <class Rep1, class Period1, class Clock, class Duration2>
    time_point<Clock, typename common_type<duration<Rep1, Period1>, Duration2>::type>
   operator+(const duration<Rep1, Period1>& lhs, const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Rep2, class Period2>
    time_point<Clock, typename common_type<Duration1, duration<Rep2, Period2> >::type>
   operator-(const time_point<Clock, Duration1>& lhs, const duration<Rep2, Period2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    typename common_type<Duration1, Duration2>::type
    operator-(const time_point<Clock, Duration1>& lhs, const time_point<Clock,
            Duration2>& rhs);
    // time point comparisons
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator == (const time_point < Clock, Duration1 > & lhs,
                    const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator!=(const time_point<Clock, Duration1>& lhs,
                    const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator< (const time_point<Clock, Duration1>& lhs,
                    const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator <= (const time_point < Clock, Duration 1 > & lhs,
                    const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator> (const time_point<Clock, Duration1>& lhs,
                    const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator>=(const time_point<Clock, Duration1>& lhs,
                    const time_point<Clock, Duration2>& rhs);
    // time_point_cast
    template <class ToDuration, class Clock, class Duration>
```



```
constexpr time_point<Clock, ToDuration> time_point_cast(const time_point<Clock, DuraJ
tion>& t);

}
are a <link linkend=#boost_chrono.reference.cpp0x.time_p</pre>
```

common_type specialization

```
template <class Clock, class Duration1, class Duration2>
    struct common_type<chrono::time_point<Clock, Duration1>, chrono::time_point<Clock, Duration2> >
    {
        typedef chrono::time_point<Clock, typename common_type<Duration1, Duration2>::type> type;
    };
ier#>
```

The common_type of two time_points is a time_point with the same clock (both have the same clock), and the common_type of the two durations.

Class template time_point<>

A time_point represents a point in time with respect to a specific clock.

```
template <class Clock, class Duration>
    class time_point {
    public:
        typedef Clock
                                           clock;
        typedef Duration
                                           duration;
        typedef typename duration::rep
                                           rep;
        typedef typename duration::period period;
    private:
        duration d_; // exposition only
    public:
        constexpr time_point();
        constexpr explicit time_point(const duration& d);
        // conversions
        template <class Duration2>
        time_point(const time_point<clock, Duration2>& t);
        // observer
        constexpr duration time_since_epoch() const;
        // arithmetic
        time_point& operator+=(const duration& d);
        time_point& operator-=(const duration& d);
        // special values
        static constexpr time_point min();
        static constexpr time_point max();
h############pecial#>()</phrase
```

Clock must meet the Clock requirements.



Duration must be an instantiation of duration, compile diagnostic otherwise.

Constructor time_point()

```
constexpr time_point();
a
```

Effects: Constructs an object of time_point, initializing d_ with duration::zero(). This time_point represents the epoch.

Constructor time_point(const duration&)

```
constexpr time_point(const duration& d);
#
```

Effects: Constructs an object of time_point, initializing d_ with d. This time_point represents the epoch + d.

Copy Constructor time_point(const time_point&)

```
template <class Duration2> time_point(const time_point<clock, Duration2>& t);
h
```

Requires: This function will not participate in overload resolution unless Duration2 is implicitly convertible to duration.

Effects: Constructs an object of time_point, initializing d_ with t.time_since_epoch().

Member Function time_since_epoch() const

```
constexpr duration time_since_epoch() const;
a
```

Returns: d_.

Member Function operator+=

```
time_point& operator+=(const duration& d);
>
```

Effects: d_ += d.

Returns: *this.

Member Function operator -=

```
time_point& operator-=(const duration& d);
>
```

Effects: d_ -= d

Returns: *this.



Static Member Function min

```
static constexpr time_point min();
s
```

Returns: time_point(duration::min()).

Static Member Function max

```
static constexpr time_point max();
s
```

Returns: time_point(duration::max()).

time_point non-member arithmetic

Non-Member Function operator+(time_point,duration)

Returns: CT(lhs) += rhs where CT is the type of the return value.

Non-Member Function operator+(duration,time_point)

Returns: rhs + lhs.

Non-Member Function operator-(time_point,duration)

Returns: lhs + (-rhs).



Non-Member Function operator-(time_point,time_point)

Returns: lhs.time_since_epoch() - rhs.time_since_epoch().

time_point non-member comparisons

Non-Member Function operator == (time_point, time_point)

Returns: lhs.time_since_epoch() == rhs.time_since_epoch().

Non-Member Function operator!=(time_point,time_point)

template <class Clock, class Duration1, class Duration2> bool operator!=(const time_point<Clock, Duration1>& lhs, const time_point<Clock, Duration2>& rhs);

Returns: !(lhs == rhs).

Non-Member Function operator<(time_point,time_point)

Returns: lhs.time_since_epoch() < rhs.time_since_epoch().

Non-Member Function operator<=(time_point,time_point)

Returns: !(rhs < lhs).

Non-Member Function operator>(time_point,time_point)

template <class Clock, class Duration1, class Duration2> bool operator>(const time_point<Clock, Duration1>& lhs, const time_point<Clock, Duration2>& rhs);

Returns: rhs < lhs.



Non-Member Function operator>=(time_point,time_point)

Returns: !(lhs < rhs).

Non-Member Function time_point_cast(time_point)

```
template <class ToDuration, class Clock, class Duration>
   time_point<Clock, ToDuration> time_point_cast(const time_point<Clock, Duration>& t);
in
```

Requires: This function will not participate in overload resolution unless ToDuration is an instantiation of duration.

Returns: time_point<Clock, ToDuration>(duration_cast<ToDuration>(t.time_since_epoch())).

Header <boost/chrono/system_clocks.hpp>

This file contains the standard clock classes.

```
namespace boost {
    namespace chrono {

        // Clocks
        class system_clock;
        class steady_clock;
        class high_resolution_clock;

    }
}
>#rhs);
r#
```

Class system_clock

The system_clock class provides a means of obtaining the current wall-clock time from the system-wide real-time clock. The current time can be obtained by calling system_clock::now(). Instances of system_clock::time_point can be converted to and from time_t with the system_clock::to_time_t() and system_clock::to_time_point() functions. If system clock is not steady, a subsequent call to system_clock::now() may return an earlier time than a previous call (e.g. if the operating system clock is manually adjusted, or synchronized with an external clock).

The current implementation of system_clock is related an epoch (midnight UTC of January 1, 1970), but this is not in the contract. You need to use the static function static

```
std::time_t to_time_t(const time_point& t);
#
```

which returns a time_t type that is based on midnight UTC of January 1, 1970.



```
class system_clock {
    public:
        typedef see bellow
                                    duration;
        typedef duration::rep
                                                     rep;
        typedef duration::period
                                                     period;
        typedef chrono::time_point<system_clock>
                                                     time_point;
        static constexpr bool is_steady =
                                                      false;
        static time_point now();
                                                           // throws on error
        static time_point now(system::error_code & ec); // never throws
        // Map to C API
        static std::time_t to_time_t(const time_point& t);
        static time_point from_time_t(std::time_t t);
    };
d to and from t
```

system_clock satisfy the Clock requirements:

- system_clock::duration::min() < system_clock::duration::zero() is true.
- The nested duration typedef has a resolution that depends on the one provided by the platform.

Static Member Function to_time_t(time_point)

time_t to_time_t(const time_point& t);

Returns: A time_t such that the time_t and t represent the same point in time, truncated to the courser of the precisions among time_t and t.

Static Member Function from_time_t(time_t)

```
time_point from_time_t(time_t t);
#
```

Returns: A time_point such that the time_point and t represent the same point in time, truncated to the coarser of the precisions among time_point and t.

Macro boost_chrono_has_clock_steady

Defined if the platform support steady clocks.

Class steady_clock

steady_clock satisfy the Clock requirements.

steady_clock class provides access to the system-wide steady clock. The current time can be obtained by calling
steady_clock::now(). There is no fixed relationship between values returned by steady_clock::now() and wall-clock time.



```
#ifdef BOOST_HAS_CLOCK_STEADY
       class steady_clock {
       public:
            typedef nanoseconds
                                                         duration;
           typedef duration::rep
                                                         rep;
           typedef duration::period
                                                        period;
           typedef chrono::time_point<steady_clock> time_point;
           static constexpr bool is_steady =
           static time_point now();
                                                              // throws on error
            static time_point now(system::error\_code \& ec); // never throws
    #endif
se></code></l
```

Class high_resolution_clock

high_resolution_clock satisfy the Clock requirements.

```
#ifdef BOOST_CHRONO_HAS_CLOCK_STEADY
    typedef steady_clock high_resolution_clock; // as permitted by [time.clock.hires]
#else
    typedef system_clock high_resolution_clock; // as permitted by [time.clock.hires]
#endif
ident
```

Header <boost/chrono/typeof/boost/chrono/chrono.hpp>

Register duration<> and time_point<> class templates to **Boost.Typeof**.



Chrono I/O

Header <boost/chrono/chrono_io.hpp>

```
namespace boost {
    namespace chrono {
        template <class CharT>
        class duration_punct;
        template <class Clock, class CharT>
        struct clock_string;
        template <class CharT, class Traits>
            std::basic_ostream<CharT, Traits>&
            duration_short(std::basic_ostream<CharT, Traits>& os);
        template <class CharT, class Traits>
            std::basic_ostream<CharT, Traits>&
            duration_long(std::basic_ostream<CharT, Traits>& os);
        template <class CharT, class Traits, class Rep, class Period>
            std::basic_ostream<CharT, Traits>&
            operator<<(std::basic_ostream<CharT, Traits>& os, const duration<Rep, Period>& d);
        template <class CharT, class Traits, class Rep, class Period>
            std::basic_istream<CharT, Traits>&
            \verb|operator|>> (\verb|std::basic_istream|<| Chart, Traits> \& is, duration|<| Rep, Period> \& d)|
        template <class CharT, class Traits, class Clock, class Duration>
            std::basic_ostream<CharT, Traits>&
            operator<<(std::basic_ostream<CharT, Traits>& os,
                   const time_point<Clock, Duration>& tp);
        template <class CharT, class Traits, class Clock, class Duration>
            std::basic_istream<CharT, Traits>&
            operator>>(std::basic_istream<CharT, Traits>& is,
                   time_point<Clock, Duration>& tp);
role="preprocessor">#ifdef</phrase> <</pre>
```

Template Class duration_punct<>

The duration unit names can be customized through the facet: duration_punct. duration unit names come in two varieties: long and short. The default constructed duration_punct provides names in the long format. These names are English descriptions. Other languages are supported by constructing a duration_punct with the proper spellings for "hours", "minutes" and "seconds", and their abbreviations (for the short format).



```
template <class CharT>
        class duration_punct
            : public std::locale::facet
        public:
            typedef std::basic_string<CharT> string_type;
            enum {use_long, use_short};
            static std::locale::id id;
            explicit duration_punct(int use = use_long);
            duration_punct(int use,
                const string_type& long_seconds, const string_type& long_minutes,
                const string_type& long_hours, const string_type& short_seconds,
                const string_type& short_minutes, const string_type& short_hours);
            duration_punct(int use, const duration_punct& d);
            template <class Period> string_type short_name() const;
            template <class Period> string_type long_name() const;
            template <class Period> string_type name() const;
            bool is_short_name() const;
            bool is_long_name() const;
        };
eyword#>const</phrase> #</
```

Template Class clock_string<>

```
template <class Clock, class CharT>
  struct clock_string;
as
```

This template must be specialized for specific clocks. The specialization must define the following functions

```
static std::basic_string<CharT> name();
static std::basic_string<CharT> since();
##
```

clock_string<>::name() return the clock name, which usually corresponds to the class name. clock_string<>::since()
return the textual format of the clock epoch.

clock_string<system_clock> Specialization

```
template <class CharT>
struct clock_string<system_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
#>()
```

clock_string<>::name() returns "system_clock".clock_string<>::since() returns "since Jan 1, 1970"



clock_string<steady_clock> Specialization

```
#ifdef BOOST_CHRONO_HAS_CLOCK_STEADY

template <class CharT>
struct clock_string<steady_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
#endif
ss name.
```

clock_string<>::name() returns "steady_clock".clock_string<>::since() returns "since boot"

clock_string<thread_clock> Specialization

```
#if defined(BOOST_CHRONO_HAS_THREAD_CLOCK)
template <class CharT>
struct clock_string<thread_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
#endif
me.
#cod
```

clock_string<>::name() returns "thread_clock".clock_string<>::since() returns "since thread start-up"

clock_stringcpu_clock> Specialization

```
template <class CharT>
struct clock_stringprocess_real_cpu_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
se>#k>
```

clock_string<>::name() returns "process_real_cpu_clock".clock_string<>::since() returns "since process start-up"

clock_stringcpu_clock Specialization

```
template <class CharT>
struct clock_stringprocess_user_cpu_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
se>#k>
```

clock_string<>::name() returns "process_user_cpu_clock".clock_string<>::since() returns " since process start-up"



clock_stringcpu_clock Specialization

```
template <class CharT>
struct clock_stringprocess_system_cpu_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
>#k>#u
```

clock_string<>::name() returns "process_system_cpu_clock".clock_string<>::since() returns "since process start-up"

clock_stringcpu_clock> Specialization

```
template <class CharT>
struct clock_stringprocess_cpu_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
};
```

clock_string<>::name() returns "process_cpu_clock".clock_string<>::since() returns "since process start-up"

I/O Manipulators

The short or long format can be easily chosen by streaming a duration_short or duration_long manipulator respectively.

```
template <class CharT, class Traits>
    std::basic_ostream<CharT, Traits>&
    duration_short(std::basic_ostream<CharT, Traits>& os);
dur
```

Effects: Set the duration_punct facet to stream durations and time_points as abbreviations.

Returns: the output stream

```
template <class CharT, class Traits>
    std::basic_ostream<CharT, Traits>&
    duration_long(std::basic_ostream<CharT, Traits>& os);
ion
```

Effects: Set the duration_punct facet to stream durations and time_points as long text.

Returns: the output stream

I/O Streams Operations

Any duration can be streamed out to a basic_ostream. The run-time value of the duration is formatted according to the rules and current format settings for duration::rep. This is followed by a single space and then the compile-time unit name of the duration. This unit name is built on the string returned from ratio_string<> and the data used to construct the duration_punct which was inserted into the stream's locale. If a duration_punct has not been inserted into the stream's locale, a default constructed duration_punct will be added to the stream's locale.



A time_point is formatted by outputting its internal duration followed by a string that describes the time_point::clock epoch. This string will vary for each distinct clock, and for each implementation of the supplied clocks.

```
template <class CharT, class Traits, class Rep, class Period>
    std::basic_ostream<CharT, Traits>&
    operator<<(std::basic_ostream<CharT, Traits>& os, const duration<Rep, Period>& d);
e>#
```

Effects: outputs the duration as an abrevieated or long text format depending on the state of the duration_punct facet.

Returns: the output stream

```
template <class CharT, class Traits, class Rep, class Period>
    std::basic_istream<CharT, Traits>&
    operator>>(std::basic_istream<CharT, Traits>& is, duration<Rep, Period>& d)
>& J
```

Effects: reads a duration from the input stream. If a format error is found, the input stream state will be set to failbit.

Returns: the input stream

```
template <class CharT, class Traits, class Clock, class Duration>
    std::basic_ostream<CharT, Traits>&
    operator<<(std::basic_ostream<CharT, Traits>& os,
        const time_point<Clock, Duration>& tp);
stre
```

Effects: outputs the time_point as an abrevieated or long text format depending on the state of the duration_punct facet.

Returns: the output stream

Effects: reads a time_point from the input stream. If a format error is found, the input stream state will be set to failbit.

Returns: the input stream

Other Clocks

Header <boost/chrono/process_cpu_clocks.hpp>

Knowing how long a program takes to execute is useful in both test and production environments. It is also helpful if such timing information is broken down into real (wall clock) time, CPU time spent by the user, and CPU time spent by the operating system servicing user requests.

Process clocks don't include the time spent by the child process.



```
namespace boost { namespace chrono {
        class process_real_cpu_clock;
        class process_user_cpu_clock;
        class process_system_cpu_clock;
        class process_cpu_clock;
        struct process_cpu_clock::times;
        template <class CharT, class Traits>
        std::basic_ostream<CharT, Traits>&
        operator<<(std::basic_ostream<CharT, Traits>& os,
                process_cpu_clock::times const& rhs);
        template <class CharT, class Traits>
        std::basic_istream<CharT, Traits>&
        operator>>(std::basic_istream<CharT, Traits>& is,
                process_cpu_clock::times const& rhs);
        template <>
        struct duration_valuescpu_clock::times>;
   {\tt namespace std}\ \{
        template <>
        class numeric_limits<boost::chrono::process_cpu_clock::times>;
> string_type name() cons
```

Class process_real_cpu_clock

process_real_cpu_clock satisfy the Clock requirements.

process_real_cpu_clock class provides access to the real process wall-clock steady clock, i.e. the real CPU-time clock of the calling process. The process relative current time can be obtained by calling process_real_cpu_clock::now().

Class process_user_cpu_clock

process_user_cpu_clock satisfy the Clock requirements.

process_user_cpu_clock class provides access to the user CPU-time steady clock of the calling process. The process relative user current time can be obtained by calling process_user_cpu_clock::now().



Class process_system_cpu_clock

process_system_cpu_clock satisfy the Clock requirements.

process_system_cpu_clock class provides access to the system CPU-time steady clock of the calling process. The process relative system current time can be obtained by calling process_system_cpu_clock::now().

Class process_cpu_clock

process_cpu_clock can be considered as a tuplecpu_clock, process_user_cpu_clock, process_system_cpu_clock.

process_cpu_clock provides a thin wrapper around the operating system's process time API. For POSIX-like systems, that's the times() function, while for Windows, it's the GetProcessTimes() function.

The process relative real, user and system current time can be obtained at once by calling process_clocks::now().

```
class process_cpu_clock
   public:
       struct times ;
       typedef duration<times, nano>
                                                         duration;
        typedef duration::rep
                                                         rep;
        typedef duration::period
                                                         period;
       typedef chrono::time_pointprocess_cpu_clock> time_point;
       static constexpr bool is_steady =
                                                         true;
       static time_point now( system::error_code & ec = system::throws );
   };
       };
( )
```



Class process_cpu_clock::times

This class is the representation of the process_cpu_clock::duration class. As such it needs to implements the arithmetic operators.

```
struct times : arithmetic<times,</pre>
       multiplicative<times, process_real_cpu_clock::rep,
       less_than_comparable<times> > >
       process_real_cpu_clock::rep
                                              // real (i.e wall clock) time
                                    real;
       process_user_cpu_clock::rep user;
                                              // user cpu time
       process_system_cpu_clock::rep system; // system cpu time
       times();
       times(
          process_real_cpu_clock::rep r,
           process_user_cpu_clock::rep u,
           process_system_cpu_clock::rep s);
       bool operator==(times const& rhs);
       times operator+=(times const& rhs);
       times operator -= (times const& rhs);
       times operator*=(times const& rhs);
       times operator/=(times const& rhs);
       bool operator<(times const & rhs) const;
   };
#########ais_sh
```

process_cpu_clock::times Input/Output

Effect: Output each part separated by ';' and sourrounded by '{', '}'. **Throws**: None.

Effect: overrides the value of rhs if the input stream has the format "{r;u;s}". Otherwise, set the input stream state as failbit | eofbit. **Throws**: None.



duration_values Specialization for times

```
template <>
struct duration_valuescpu_clock::times>
{
    static process_cpu_clock::times zero();
    static process_cpu_clock::times max();
    static process_cpu_clock::times min();
};
ne.#met
```

The times specific functions zero(), max() and min() uses the relative functions on the representation of each component.

numeric_limits Specialization for times

 $The \ \texttt{times} \ specialization \ functions \ \texttt{min(), max()} \ and \ \texttt{lowest()} \ uses \ the \ relative \ functions \ on \ the \ representation \ of \ each \ component.$

Notes

- min() returns the tuple of mins.
- max() returns the tuple of maxs.
- lowest() returns the tuple of lowests.
- digits is the sum of (binary) digits.
- digits10 is the sum of digits10s.

Header <boost/chrono/thread_clock.hpp>

Knowing the time a thread takes to execute is useful in both test and production environments.



```
#define BOOST_CHRONO_HAS_THREAD_CLOCK
#define BOOST_CHRONO_THREAD_CLOCK_IS_STEADY
namespace boost { namespace chrono {
    class thread_clock;
}
}
cpu_clo
```

Macro boost_chrono_has_thread_clock

This macro is defined if the platform supports thread clocks.

Macro boost_chrono_thread_clock_is_steady

This macro is defined if the platform has a thread clock. Its value is true if it is steady and false otherwise.

Class thread clock

thread_clock satisfy the Clock requirements.

thread_clock class provides access to the real thread wall-clock, i.e. the real CPU-time clock of the calling thread. The thread relative current time can be obtained by calling thread_clock::now().

Appendices

Appendix A: History

Version 1.0.0, January 6, 2011

- Moved chrono to trunk taking in account the review remarks.
- Documentation revision.

Features:

- Boost_Chrono is now a configurable header-only library version (that also allows the user to choose if the windows.h file is included or not).
- Added clock_string<> traits.
- Define chrono-io for all the clocks.
- Add input of process_times representation.



Implementation:

- Use of detail/win files to avoid the use of windows.h file.
- Completed the error_code handling.
- Works now with BOOST_SYSTEM_NO_DEPRECATED.

Fixes:

- Fix some warnings.
- Fix original errors on Mac
- Dont fix the link with boost_system to static.

Test:

- Added test on process and thread clocks.
- · Moved to lightweight_test.hpp.
- Able to test multiple configurations.

Doc:

Removed some not useful parts as the history, the test and the tickets.

Version 0.6.0, September 22, 2010

Features:

· Added experimental chrono_io.

Fixes:

- Fix duration values min implementation.
- Fix some warnings

Test:

Adapted test from libc++/chrono

Version 0.5.0, September 10, 2010

Features:

• Stopwatches, Ratio and CommonType have been moved to separated libraries: Boost.Stopwatches, Boost.Ratio and Boost.TypeTraits.

Version 0.4.7, September 1, 2010

New Features:

Added __lightweightstopwatch_.

Version 0.4.6, August 28, 2010

New Features:



- Implementation of common_type without using Boost.TypeOf.
- Added __stopwatch_accumulator_timeformatter_class.

Old Features:

• Type reporter removed from Stopwatches as well as the get_reporter metafunction.

Bug Fixes

- process_cpu_clock is now a valid model of Clock that can be used with __stopclocksaccumulator_.
- eliminate or suppress a lot of warnings appearing with with warnings=all -Wextra
- · improve the error code handling

Version 0.4.5, July 6, 2010 Documentation update

Documentation

- Overview rewriting
- Added missing thread_clock reference.
- How to implement a thread_clock tutorial removed.
- References section renamed to External Resources.
- Added links to source examples.
- · Added links between Models and Concepts.
- Added macros descriptions.
- Cleanup.

Bug Fixes

- Valgrind fixes: "Conditional jump or move depends on uninitialised value(s)"
- Take care of Boost.System break on version 1.44
- gcc.4.4 "warning: suggest parentheses around '&&' within '||' " removal.

Version 0.4.4, February 22, 2010 Warning fixes

Bug Fixes

- scoped_suspend warning removal
- error_code management completed

Version 0.4.3, June 18, 2010 Missing file fixe

Bug Fixes

boost/thread/detail/cv_status.hpp file was not committed.

Version 0.4.2, June 18, 2010 Packaging fixe

Boost.Conversion library, used by Boost.Thread porting to Boost.Chrono was not packaged.



Version 0.4.1, June 17, 2010 Added thread clock implementation on Windows

New Features:

- Added thread_clock implementation on Windows.
- Added Boost.Thread using Boost.Chrono.

Version 0.4, February 28, 2010 New thread clock and Suspendible clock

New Features:

- <u>SuspendibleClock</u> concept + template class _suspendible<u>clock</u> .
- Added scope_suspend which do suspend/resume if the Clock is a model of <u>SuspendibleClock</u> concept, and nothing otherwise.
- thread_clock support on platforms providing it natively.
- Added support for wide character for __stopwatchreporter_, stopclock, and stopclock_accumulator.
- digital_time renamed t24_hours.

Perf

Added performances measures.

Bug Fixes

Bug on timeval_demo.

```
time_point t(duration(xtime(0))); // this was taken as a function declaration
  gettimeofday((timeval*)&t, 0);
  return t;
pcl
```

time_point t(duration(xtime(0))); // this was taken as a function declaration gettimeofday((timeval*)&t, 0); return t; by

```
timeval tv;
gettimeofday(&tv, 0);
xtime xt( tv.tv_sec, tv.tv_usec);
return time_point(duration(xt));
0);
```

Bug on run_timer_test (add a global variable to avoid optimization that removes completely the code to be measured

Version 0.3.2, January 25, 2010 New frequency, lifetime and percentage stopwatch_accumulator features

Features:

- Added overloading for operator/(Integer/Duration)
- Added frequency, lifetime and percentage to the default stopwatch_accumulator_formatter.

Bug Fixes * Specific formatters didn't work completly. * Replace duration(0) by duration::zero() on template classes. * suspend doesn't works: partial_ not initialized neither taken in account by the elapsed function.



Version 0.3.1, January 20, 2010 New support for wide characters

Features:

- · Support for wide characters on formatters and stopclocks
- added chrono.hpp and stopwatches.hpp at the boost level

Version 0.3.0, January 17, 2010 New stopwatch/stopclock feature + Bug fixes

Features:

- · Added independent process cpu clocks for real, user, system process CPU time
- Added global process cpu clock for real, user, system process CPU time
- Added digital_time (looking for a better name)
- Added new <u>Stopwatch</u> concept measuring elapsed time between different points in time associated to the operations start, stop, suspend and resume.
- Added <u>stopwatch</u> is a model <u>Stopwatch</u> measuring the elapsed time between the start and the stop operations.
- Added __stopwatchaccumulator_ is a model _<u>Stopwatch_</u> allowing to accumulate several time samples and gives the average,
 ...
- Added scoped helper classes allowing to pairwise start'stop' operations, 'suspend' resume and resume/suspend a <u>Stopwatch</u>.
- Added new stopwatch <u>Formatter</u> concept
 - Added stopwatch formatter "%ds\n"
 - Added stopwatch accumulator formatter "%c times, sum%ss, min%ms, max%Ms, mean%as\n"
 - Added time formatter "real %rs, cpu %cs (%p%), user %us, system %ss\n"
 - Added digital_time formatter "%d days(s) %h:%m:%s.%n\n"
- __stopwatch<u>reporter</u> is a convenient generic class reporting elapsed time for the Stopwatch concept.
- Added stopclock<Clock> shortcut stopwatch_reporter<stopwatch<Clock>>
- Added <u>scopedstopclock</u> which trace at the constuctor and destructor.
- Added typeof registration for classes duration and time_point
- The old classes process_times, process_clock, process_timer, timer and run_timer are deprecated as the preceding additions are more generic. However for backward compatibility they preserved until inclusion of the library in Boost. Next follows the equivalences:
 - timer<> ~ stopwatch<>
 - process_timer ~ stopwatch<process_cpu_clock>
 - run_timer ~ stopclock<>

Bug Fixes

• Try to correct warning "C4251: 'boost::chrono::run_timer::m_format' : class 'std::basic_string<_Elem,_Traits,_Ax>' needs to have dll-interface to be used by clients of class 'boost::chrono::run_timer''', by don't including inlines functions using the std::string m_format.



Version 0.2.1, December 13, 2009 Bug fixes

Bug Fixes

- Replace INTMAX_C by BOOST_INTMAX_C until boost/cstdint.hpp ensures INTMAX_C is always defined.
- Define __BOOST_CHRONO_HAS_CLOCKSTEADY when BOOST_CHRONO_WINDOWS_API
- Commenting invalid operator declarations
- Take care of Boost min/max recommendations
- Complete qualification when defining nested typedef duration on clocks to avoid the following compile error:

```
./boost/chrono/chrono.hpp:945: error: declaration of 'typedef class boost::chrono::duradtion<long long int, boost::_ratio<111, 1000000011> > boost::chrono::system_clock::duration'./boost/chrono/chrono.hpp:458: error: changes meaning of 'duration' from 'class dboost::chrono::duration<long long int, boost::__ratio<111, 1000000011> >' es
```

- cleanup of simulated...
- warning removal on posix/process_clock.cpp.
- disable VC++ foolishness.
- Update Jamfiles to manage with dll.
- removal of conversion warning in test_duration.
- manage with MSVC reporting a warning instead of an error when there is an integral constant overflow.
- Use STATIC_ASSERT specific macro to solve the compile failing issue.
- Qualify with boost::detailboost::chrono::detail to avoid ambiguities with MSVC.

Documentation:

More updated documentation.

Version 0.2.0, December 8, 2009 + Features + Bug fixes + Updated documentation

Features:

- Added ratio construction and assignment from an equivalent ratio (LWG 1281. CopyConstruction and Assignment between ratios having the same normalized form)
- Added nested ratio typedef type (LWG 1281. CopyConstruction and Assignment between ratios having the same normalized form)
- Added __BOOST_CHRONO_HAS_CLOCK<u>STEADY</u> macro to state if steady_clock is provided on this platform.
- Added durationoperator% (LGW 934. duration is missing operator%)
- Added constexpr when constexpr should be used.
- Complete durationoperator* and operator/.



Implementation:

- Use INTMAC_C to name intmax_t constants instead of LL.
- Separate chrono.cpp on # files win/chrono.cpp, mac/chrono.cpp and posix/chrono.cpp to make easier the maintenance on different platforms.
- Separate process_clock.cpp on # files win/process_clock.cpp, mac/process_clock.cpp and posix/process_clock.cpp to make easier the maintenace on different platforms.
- Added the error_code prototype for steady_clock::now for mac/chrono.cpp.
- Fully implement mac/chrono.cpp with error handling.
- Take care on POSIX systems when CLOCK_STEADY is not defined.

Documentation:

The documentation is written now using quick-book using as base N2661 - A Foundation to Sleep On.

Bug Fixes

- operator/ was ambiguous: Disambiguate duration operator/.
- CLOCK_STEADY is not defined with cygwin/gcc 3.4: Disable code when __BOOST_CHRONO_HAS_CLOCK<u>STEADY</u> is not defined.
- result of metafunctions ratio_multiply and ratio_divide were not normalized ratios: Use of the nested ratio typedef type on ratio arithmetic operations.
- Copy constructor from similar duration masked the defaulted operations: Added duration defaulted implementations

Version 0.1.0, April 29, 2009 Beman's boostified version Chrono

Features:

- The C++0x Standard Library's common_type.
- The C++0x Standard Library's compile-time rational arithmetic.
- The C++0x Standard Library's time utilities, including:
 - Class template duration
 - Class template time_point
 - Clocks:
 - system_clock
 - steady_clock
 - high_resolution_clock
- Class template timer, with typedefs:
 - system_timer
 - steady_timer
 - high_resolution_timer



- Process clocks and timers:
 - process_clock, capturing real, user-CPU, and system-CPU times.
 - process_timer, capturing elapsed real, user-CPU, and system-CPU times.
 - run_timer, convenient reporting of process_timer results.

]

Appendix B: Rationale

See N2661 - A Foundation to Sleep On which is very informative and provides motivation for key design decisions. This section contains some extracts from this document.

Is it possible for the user to pass a duration to a function with the units being ambiguous?

No. No matter which option the author of f chooses above, the following client code will not compile:

```
f(3); // Will not compile, 3 is not implicitly convertible to any __duration >
```

Why duration needs operator%

This operator is convenient for computing where in a time frame a given duration lies. A motivating example is converting a duration into a "broken-down" time duration such as hours::minutes::seconds:

Appendix C: Implementation Notes

Which APIs have been chosen to implement each clock on each platform?

The following table presents a resume of which API is uused for each clock on each platform



Table 2. Clock API correspondence

| Clock | Windows Platform | Posix Platform | Mac Platform |
|-------------------------------|---|---------------------------------|---|
| system_clock | GetSystemTimeAsFileTime | clock_gettime(CLOCK_RE-ALTIME) | gettimeofday |
| steady_clock | QueryPerformanceCounter and QueryPerformanceFrequency | clock_gettime(CLOCK_STEADY) | mach_timebase_info,mach_absolute_time |
| p r o - cess_real_cpu_clock | GetProcessTimes | times | times |
| process_sys- tem_cpu_clock | GetProcessTimes | times | times |
| p r o - cess_user_cpu_clock | GetProcessTimes | times | times |
| process_cpu_clock | GetProcessTimes | times | times |
| thread_clock | GetThreadTimes | _ | c l o c k _ g e t - time(pthread_getcpuclockid) |

Appendix D: FAQ

Why does process_cpu_clock sometimes give more cpu seconds than real seconds?

Ask your operating system supplier. The results have been inspected with a debugger, and both for Windows and Linux, that's what the OS appears to be reporting at times.

Are integer overflows in the duration arithmetic detected and reported?

Boost.Ratio avoids all kind of overflow that could result of arithmetic operation and that can be simplified. The typedefs durations don't detect overflow. You will need a representation that handles with.

Which clocks should be used to benchmarking?

Each clock has his own features. It depends on what do you need to benchmark. Most of the time, you could be interested in using a thread clock, but if you need to measure code subject to synchronization a process clock would be better. If you have a multi-process application, a system-wide clock could be needed.

Which clocks should be used for watching?

For trace purposes, it is probably best to use a system-wide clock.

Appendix E: Acknowledgements

The library's code was derived from Howard Hinnant's time2_demo prototype. Many thanks to Howard for making his code available under the Boost license. The original code was modified by Beman Dawes to conform to Boost conventions.

time2_demo contained this comment:

Much thanks to Andrei Alexandrescu, Walter Brown, Peter Dimov, Jeff Garland, Terry Golubiewski, Daniel Krugler, Anthony Williams.



The file <boost/chrono_io.hpp> has been adapted from the experimental header <chrono_io> from Howard Hinnant. Thanks for all Howard.

Howard Hinnant, who is the real author of the library, has provided valuable feedback and suggestions during the development of the library. In particular, The chrono_io_io.hpp source has been adapted from the experimental header <chrono_io> from Howard Hinnant.

The acceptance review of Boost.Ratio took place between November 5th and 15th 2010. Many thanks to Anthony Williams, the review manager, and to all the reviewers: David Deakins, John Bytheway, Roland Bock and Paul A. Bristow.

Thanks to Ronald Bock, Andrew Chinoff, Paul A. Bristow and John Bytheway for his help polishing the documentation.

Thanks to Tom Tan for reporting some compiler issues with MSVC V10 beta and MinGW-gcc-4.4.0 and for the many pushing for an homogeneous process_cpu_clock clock.

Thanks to Ronald Bock for reporting Valgind issues and for the many suggestions he made concerning the documentation.

Appendix F: Future plans

For later releases

Add chrono utilities as defined By Howard Hinnant in here.

