Technical guide

Forwarding Shipment Module Mapping Guide

Universal XML

29 July 2025

Contents

Terms of Use **4**

1. Introduction **5**

1.1 DataSource / DataTarget Type – ForwardingShipment 5

2. Universal Events **6**

2.1 Data export 6

2.1.1 Context Elements 6

2.2 Data import 8

2.2.1 Matching and special update logic 8

3. Universal Shipment **9**

3.1 Data export 9

3.2 Data import 10

3.2.1 Matching and special update logic 10

3.3 Collection mappings 12

3.4 Element mappings 13

3.4.1 Shipment 13

3.4.2 LocalProcessing 18

3.4.3 OrderNumberCollection 21

3.4.4 AdditionalAddressInfoCollection 21

3.4.5 AdditionalReferenceCollection 22

3.4.6 ContainerCollection 22

3.5 Links from containers to PackingLines 33

3.5.1 DateCollection 35

3.5.2 NoteCollection 35

© 2025 WiseTech Global

3.5.3 OrganizationAddressCollection 36
3.5.4 PackingLineCollection 40
3.5.5 PackingLine > UNDGCollection 43
3.5.6 TransportLegCollection 44
3.5.7 PreCarriageShipmentCollection 47
3.5.8 PostCarriageShipmentCollection 52
3.5.9 GatewayInfoCollection 56
4. Sample files 57
4.1 Universal Shipment 57

© 2025 WiseTech Global

Date	Version	Description of Change	Work Item
30 Jul 2024	1.01	CO2eDescriptiveStatus added	
14 Oct 2024	1.02	Total Loading Meters added	
11 Dec 2024	1.03	CO2	WI00790019
04 Jun 2025	1.04	GreenhouseGasCollection and GreenhouseGas added ContainerPenaltyCollection added Formatting to headings to include in TOC	WI00885977 WI00872011
29 July 2025	1.05	Gateway details added	WI00844550

© 2025 WiseTech Global

Terms of Use

WiseTech Global (WTG) grants you access to this Forwarding Shipment Module Mapping Guide for the following purpose(s):

a. Development of interfaces between CargoWise and your In-House Systems /Middleware; and
b. Development of interfaces between CargoWise and your Clients' Systems via your Middleware,

(collectively, the "Permitted Purpose")

Any person within your organization who accesses this Forwarding Shipment Module Mapping Guide (irrespective of how it is accessed) may only do so only for the Permitted Purpose. All intellectual property rights in this Forwarding Shipment Module Mapping Guide are owned by WTG and are the sole and absolute property of WTG, throughout the world.

Neither you, nor any person within your organization who accesses this Forwarding Shipment Module Mapping Guide is permitted to copy or distribute, forward or publicly display the contents of this Forwarding Shipment Module Mapping Guide (or any part of it) to any third party without first obtaining the written consent of WTG.

© 2025 WiseTech Global

1. Introduction

The Forwarding Shipment module allows freight forwarders to receive detailed shipment or shipping instruction from their respective customers, which confirms an earlier booking or creates new or updates an existing shipment with detailed house bill level data. The module supports both, full container loads and loose freight for all Transport modes, providing tracking, documentation, and possible consolidation as part of its interface.

Before starting, you should already be familiar with:

- eAdaptor Developers Guide
- Forwarding learning material and courses found on WiseTech Academy website.

1.1 DataSource / DataTarget Type – ForwardingShipment

A Universal Shipment targeted for import into this module becomes a forwarding shipment. If a matching shipment is found in the recipient system, this shipment will be updated.

If a Universal Shipment XML is targeted for import into this module, but a shipment was already consolidated in the Forwarding module (attached to a consol), then the respective shipment will be updated.

If a Universal Shipment XML contains consol information and shipment details matching an existing shipment, CargoWise will create or find a matching consolidation and attach this shipment to the consolidation subheading.

A Universal Event targeted for import into this module will update the forwarding shipment. If a matching shipment is found in the recipient system, this shipment will be updated.

© 2025 WiseTech Global

2. Universal Events

2.1 Data export

When you export a Universal Event from forwarding shipment, the following information will be extracted and included in ContextCollection of the xml.

2.1.1 Context Elements

Context type	Value mapped from	Notes
MAWBNumber/MBOLNumber	Consol's Details tab > MAWB / BOL field	HAWBNumber for air only and MBOLNumber for other transport modes
MAWBOriginIATAAirportCode	The IATA code of the consol's load port	Air only
MAWBDestinationIATAAirportCode	The IATA code of the consol's discharge port	Air only
MBOLOriginUNLOCO	Consol's Details tab > Load Port field	
MBOLDestinationUNLOCO	Consol's Details tab > Discharge Port field	
CarriersBookingReference	Consol's Details tab > Carrier Bkg. Ref field	
AgentsReference	Consol's Details tab > Agents Reference field	
CarrierCode	The SCAC code of consol's carrier	

© 2025 WiseTech Global

Context type	Value mapped from	Notes
Reference Numbers	Consol's, Details > Numbers tab	Each type of reference number and description serve as their own context type and description
HAWBNumber/HBOLNumber	Shipment's Basic Registration tab > House Bill field	HAWBNumber for air only and HBOLNumber for other transport modes
HAWBOriginIATAAirportCode	The IATA code of the origin UNLOCO	Air only
HAWBDestinationIATAAirportCode	The IATA code of the destination UNLOCO	Air only
HBOLOriginUNLOCO	Shipment's Basic Registration tab > Origin field	
HBOLDestinationUNLOCO	Shipment's Basic Registration tab > Destination field	
ShippersReference	Shipment's Pickup tab > Shipper's Ref field	
Order Numbers	Shipment's Details tab > Job Management Links section > Order Refs field	Each order's job number and order refs serve as context type and description
InterimReceipt	Shipment's Pickup tab > Interim Receipt field	

© 2025 WiseTech Global

Context type	Value mapped from	Notes
Reference Numbers	Shipment's Additional Details tab > Reference Numbers field	Each type of reference number and description serve as their own context type and description

2.2 Data import

2.2.1 Matching and special update logic

- **Context Key Matching** – are relatively unique references that CargoWise matches on, like shipment numbers, and consolidation numbers. They can all be used to help match incoming data to existing jobs and entities within CargoWise. This is the first matching strategy the system will use when importing a Universal Event XML. You can see from the XML snippet below, DataContext contains DataTargetCollection describing the importing target. A DataTarget contains both type and key to indicate the type of the target this event is importing to and the job number of the parent. The system will look for the data target and try to load the event parent with this information.

```
<Event>
  <DataContext>
    <DataTargetCollection>
      <DataTarget>
        <Type>ForwardingShipment</Type>
        <Key>S00001011</Key>
      </DataTarget>
    </DataTargetCollection>zz
```

- **Combination Key Match** – if context key was not defined in Universal Event or job with this shipment number not found, a combination key match will be conducted to find the best matching forwarding shipment. Reference matches included at this level are the house bill, shipper's reference, all order numbers, the interim receipt number, CFS reference, and then all additional references matching to the **Reference Numbers** grid under the **Additional Detail** tab on the forwarding Shipment record. The system will find the shipment that matches the most of these fields. If multiple shipments are best matched, shipment's origin and destination will be used as the fallback reference. If only one shipment has the best matches, it will be loaded. If multiple shipments are best matched, the shipment with latest time will be loaded.

© 2025 WiseTech Global

3. Universal Shipment

3.1 Data export

When a forwarding shipment is exported, the Universal Shipment XML usually looks like it's been exported from the forwarding consolidation. Where the forwarding shipment is linked to a forwarding consolidation, the top-level Universal Shipment exported will represent the forwarding consolidation. All parent forwarding shipments will then be included to provide the parent structure down to the forwarding shipment being exported, but no sibling forwarding shipments will be included.

This means that you always have the same structure in place when you export from a forwarding shipment or a forwarding consolidation, but if you export a forwarding shipment you get a filtered view only containing data relevant to that forwarding shipment.

If the forwarding shipment is not linked to a forwarding consolidation, the top-level Universal Shipment is mapped from the forwarding shipment itself. In this form, the Universal Shipment looks more like a booking, with limited routing and no container information.

In both forms, all child and related forwarding shipments are mapped to Universal Shipments in the SubShipmentCollection, and those include their child and related forwarding shipments all the way down.

Collections are populated in the following manner:

- **ContainerCollection** - containers are exported on the top-level Universal Shipment, and only when it is mapped from a forwarding consol. In CargoWise you cannot have a container against a forwarding shipment, only a forwarding consol.
- **PackingLineCollection** – populated from the **Packing** tab of the forwarding shipment. Containers from the forwarding consol Universal Shipment may be referenced by elements in the PackingLineCollection on any Universal Shipment mapped from a forwarding shipment. This means that the ContainerCollection is only present once at the top-level, but can be referenced by PackingLineCollections at all levels
- **UNDGCollection** – contains all the UNDG linked to pack line at the **Packing** tab.
- **OrganizationAddressCollection** - the **Basic Registration** tab of the forwarding shipment, the consignor, consignee, and local client organizations plus any organizations from the **Addresses** tab within the forwarding shipment are populated.
- **NoteCollection** – all notes from the **Notes** tab are included.
- AdditionalReferenceCollection – all references from the **Reference Numbers** grid under the **Additional Detail** tab within the forwarding shipment are mapped.
- **DateCollection** - the dates exported from the forwarding shipment at the time of publication of this document were booking confirmed, received, departure, arrival, shipped on board, and bill issued.
- **EntryNumberCollection** – all entry numbers linked to the forwarding shipment are mapped.

© 2025 WiseTech Global

Entry number is populated from **Brokerage > Declaration > Numbers** tab on the shipment.

- **TransportLegCollection** – on a Universal Shipment mapped from a forwarding shipment, this includes all transport legs that are not exported in any parent Universal Shipment. This means that where transport legs are exported at the forwarding consol level, they will not be repeated at the forwarding shipment level. If there is no parent Universal Shipment, all legs present will be included in the mapping. This means that to get a complete picture of all legs applicable to a given shipment, you must include all legs from parent Universal Shipments as well.
- **LocalProcessing** – populated from **Pickup > Details and Delivery > Details** tab of the shipment.
- **SubShipmentCollection** – contains directly related forwarding sub-shipments. Sub-shipments can have their own sub-shipments in their SubShipmentCollections and so on. For HVLV shipments, it will populate from its consignments.
- **RelatedShipmentCollection** – contains all orders linked to forwarding shipment at the **Basic Registration** tab.
- **PreCarriageShipmentCollection** – contains pickup instructions and confirmations of forwarding shipment.
- **PostCarriageShipmentCollection** – contains delivery instructions and confirmations of forwarding shipment.

3.2 Data import

Where an incoming Universal Shipment has a data target element with a type of ForwardingShipment, the Universal Data Buss will try to match to an existing forwarding shipment using the matching system described below.

System only will update the existing shipment, when the following Registry item is enabled: **eServices > Universal XML > Automatic Update on Import > Update Shipment During Automatic Import**.

3.2.1 Matching and special update logic

- **Context Key Matching** – context Keys are relatively unique references that CargoWise matches on, like shipment numbers, and consolidation numbers. They can all be used to help match incoming data to existing jobs and entities within CargoWise. This is the first matching strategy the system will use when importing a Universal Shipment XML. As you can see from the XML snippet below, DataContext contains DataTargetCollection describing the importing target. A DataTarget contains both type and key to indicate the target shipment to be imported. The system will use the key in DataTarget, which is the shipment number of the shipment, to try to load the shipment.

© 2025 WiseTech Global

```
<UniversalShipment xmlns="http://www.cargowise.com/Schemas/Universal/2011/11"
version="1.1">
  <Shipment>
    <DataContext>
      <DataTargetCollection>
        <DataTarget>
          <Type>ForwardingShipment</Type>
          <Key>S00001001</Key>
        </DataTarget>
      </DataTargetCollection>
```

- **Combined Reference and Party ID Matching** – when the Registry item: **eServices > Universal XML > Use Combined Reference and Party ID Matching** is enabled; the system will try to match with reference and party ID. The system has a list of pre-defined criteria specifying which reference and organization will be used for matching. Each criteria has three score, the match score for matching both reference and party, the partial score for matching only reference, the conflict score is for the case where reference is provided but it is different from the given job. All the matched scores will be sum to a total and compared in order to get the best match.

All the criteria of forwarding shipment:

Reference element	Party	Match	Partial	Conflict
BookingConfirmationReference	Consignor	90	30	0
BookingConfirmationReference	Consignee	90	30	0
InterimReceiptNumber	Consignor	90	30	0
WayBillNumber	SendingForwarder	180	30	-180

Note: for the criteria to take effect, the **Reference** field must be longer than six characters. Unmatched organization will also be taken into considerations if enabled in the registry.

- **Module Specific Business Rules** – if context key matching and combined reference and party ID matching do not find any matched shipment, the system will then try to match SubShipments by using WayBillNumber, when WayBillType is House WayBill.

© 2025 WiseTech Global

- **Combination Key Match** – reference matches included at this level are the house bill, shipper's reference (from the BookingConfirmationReference element), all order numbers, the interim receipt number, CFS reference, and then all additional references matching to the **Reference Numbers** grid of the **Additional Detail** tab within the forwarding Shipment record. If there are multiple matches, the system will fallback to OriginUNLOCO and DestinationUNLOCO to match the shipment. Reference match will perform only when **eServices > Universal XML > Use Combined Reference and Party ID Matching** registry item is disabled.

3.3 Collection mappings

Collections are mapped in the following manner:

- **RelatedShipmentCollection** – used to store shipment information that is attached to the master shipment. It uses the same logic as described under 3.2.1
- **LocalProcessing > OrderNumberCollection** – matched on order reference. It will also remove any order reference that was not in XML.
- **LocalProcessing > AdditionalServiceCollection** – matched on service code.
- ***AdditionalReferenceCollection** – matched on type if the type of reference need to be unique in the collection, otherwise match on ReferenceNumber as well.
- ***ContainerCollection** – matched on container number, fallback to match on container type.
- **DateCollection** – matched on type. Unknown types are discarded.
- **EntryNumberCollection** – matched on type and CountryOfIssue. EntryNumbers are always brought in ignoring the EntryIsSystemGenerated flag. System generated entry numbers will not be updated, if they already exist in CargoWise and are read only. If there is no pre-existing system generated entry number, a new entry number row will be added with the IsSytemGenerated flag set to false.
- ***NoteCollection** – matched on description and NoteContext.Code (NoteContext.Code is combination of module, direction, and freight from the **Notes** tab on the forwarding shipment)
- **OrganizationAddressCollection** – matched on organization code and address code, fallback to match by address similarity, if still not found and no other address information exist, match by custom registration number, and finally fallback to unmatched organization in the registry if enabled.
- ***PackingLineCollection** – matched on existing pack lines using pack quantity, pack type, reference number, export reference, goods description and marks & numbers. If reference number or export reference number is matched, goods description will not be used for matching and can be updated.
- ***TransportLegCollection** – matched on port of loading and port of discharge.
- **SubShipmentCollection** – matched on house bill. Universal Shipments in the SubShipmentCollection are then brought in using the same matching and updating process outlined above.

© 2025 WiseTech Global

- **PreCarriageShipmentCollection** – matched on forwarding shipment **Pickup** tab.
- **PostCarriageShipmentCollection** – matched on forwarding shipment **Delivery** tab.

*Collections that support collection content attributes.

3.4 Element mappings

3.4.1 Shipment

Elements in the shipment will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from	Notes
ActualChargeable	Basic Registration tab > Chargeable field	
AdditionalTerms	Basic Registration tab > Additional Terms field	
AviationSecurityInspectionType	Basic Registration tab > Inspection field	Export only if transport mode is air and inspection code is not unknown (UNK). Import only if AviationSecurityInspectionType is not unknown (UNK)
BookingConfirmationReference	Pickup tab > Shipper's Ref field	
ContainerMode	Basic Registration tab Container field	
FreightRate	Basic Registration tab > Spot Rate field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
FreightRateCurrency	Basic Registration tab > Spot Rate field	
GatewayServiceLevel	Additional Details tab > Gateways > G/W Service	
GoodsDescription	Basic Registration tab > Description field	
GoodsValue	Basic Registration tab > Goods Value field	
GoodsValueCurrency	Basic Registration tab > Goods Value field	
GreenhouseGasEmission	**Basic Registration** > CO2e field	**FOR EXPORT ONLY:** <CO2e>, <CO2eUnit>, <CO2eDescriptiveStatus> **INTERNAL ONLY:** CO2eDistanceInKm>, <CO2ePerTEU>, <CO2ePerTonne>, <CO2eStatus>, <GreenhouseGasCollection>, <GreenhouseGas>
HBLAWBChargesDisplay	Basic Registration tab > Charges Apply field	
HBLContainerPackModeOverride	Basic Registration tab > Shipment Type field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
InsuranceValue	Basic Registration tab > Insurance Value field	
InsuranceValueCurrency	Basic Registration tab > Insurance Value field	
InterimReceiptNumber	Pickup tab > Interim Receipt field	
LloydsIMO		Export only if shipment has a transport leg
NoCopyBills	Basic Registration tab > Copy Bills field	
NoOriginalBills	Basic Registration tab > Originals field	
OuterPacks	Basic Registration tab > Packs field	
OuterPacksPackageType	Basic Registration tab > Packs field	
PortOfDestination	Basic Registration tab > Destination field	
PortOfDischarge	Additional Details tab > Consolidation Details grid	Export only, if shipment is linked to consolidation
PortOfFirstArrival	Additional Details tab > Consolidation Details grid	Export only, if shipment is linked to consolidation

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
PortOfLoading	Additional Details tab > Consolidation Details grid	Export only, if shipment is linked to consolidation
PortOfOrigin	Basic Registration tab > Origin field	
ReleaseType	Basic Registration tab > Release Type field	
ServiceLevel	Basic Registration tab > Service Level field	
ShipmentIncoTerm	Basic Registration tab > Incoterm field	
ShipmentType	Basic Registration tab > Shipment Type field	
ShippedOnBoard	Basic Registration tab > Shipment Type field	
ShipperCODAmount	Basic Registration tab > Shipper COD field	
ShipperCODPayMethod	Basic Registration > Shipper COD field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
TEU	Consol > Containers tab > Container Type > TEU Count field	Internal Use only – This tag also contains sub tag **ContainerEmptyWeightPer TEU** taken from **Container Type ref file > Tare Weight** field
TotalLoadingMeters	Basic Registration tab > Loading Meters field	
TotalNoOfPacks	Basic Registration tab > Inners field	
TotalNoOfPacksPackageType	Basic Registration tab > Inners field	
TotalVolume	Basic Registration tab > Vol field	
TotalVolumeUnit	Basic Registration tab > Vol field	
TotalWeight	Basic Registration tab > Weight field	
TotalWeightUnit	Basic Registration tab > Weight field	
TransportMode	Basic Registration tab > Transport field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
VesselName	Routing tab > Vessel field	Export only if shipment has transport leg
VoyageFlightNo	Routing tab > Voyage / Flight field	Export only if shipment has transport leg
WayBillNumber	Basic Registration tab > House Bill field	

3.4.2 LocalProcessing

Elements in the LocalProcessing will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from
DeliveryCartageAdvised	Delivery tab > Port Trn. Advised field
DeliveryLabourCharge	Delivery tab > Delivery Labour section > Charge field
DeliveryLabourTime	Delivery tab > Delivery Labour section > Time field
DemurrageOnDeliveryCharge	Delivery tab > Delivery Demurrage section > Charge field
DemurrageOnDeliveryTime	Delivery tab > Delivery Demurrage section > Time field
DemurrageOnPickupCharge	Delivery tab > Pickup Demurrage section > Charge field
DemurrageOnPickupTime	Delivery tab > Pickup Demurrage section > Time field

© 2025 WiseTech Global

Element name (XML)	Value mapped from
EstimatedDelivery	Delivery tab > Estimated Delivery field
EstimatedPickup	Pickup tab > Estimated Pickup field
ExportStatement	Basic Registration tab > Exporter Statement field
FCLDeliveryEquipmentNeeded	Delivery tab > Drop Mode field
FCLPickupEquipmentNeeded	Pickup tab > Drop Mode field
LCLAirStorageCharge	Delivery tab > Storage Charge > Charge field
LCLAirStorageDaysOrHours	Delivery tab > Storage Charge section > Time field
LCLDatesOverrideConsol	Delivery tab > Override Available and Storage Consolidation Dates field
PickupCartageAdvised	Pickup tab > Port Trn. Advised field
PickupCartageCompleted	Pickup tab > Actual Pickup field
PickupLabourCharge	Pickup tab > Pickup Labour section > Charge field
PickupLabourTime	Pickup tab > Pickup Labour section > Time field
PrintOptionForPackagesOnAWB	Basic Registration tab > Air Waybill Dims field

3.4.2.1 LocalProcessing > AdditionalServiceCollection

Elements in the AdditionalServiceCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

© 2025 WiseTech Global

Element name (XML)	Value mapped from
Booked	Additional Details tab > Service grid > Date Booked field
Completed	Additional Details tab > Service grid > Completed field
Contractor	Additional Details tab > Service grid > Contractor field
Duration	Additional Details tab > Service grid > Duration field
Location	Additional Details tab > Service grid > Service Loc. Address field
References	Additional Details tab > Service grid > Reference field
ServiceCode	Additional Details tab > Service grid > Type field
ServiceCount	Additional Details tab > Service grid > Count field
ServiceNote	Additional Details tab > Service grid > Notes field

© 2025 WiseTech Global

3.4.3 OrderNumberCollection

Elements in the OrderNumberCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from
OrderReference	Details tab > Job Management Links section > Order Refs field
Sequence	Set by system

The OrderNumberCollection will not be imported when there are orders attached to the shipment in CargoWise.

3.4.4 AdditionalAddressInfoCollection

Elements in the AdditionalAddressInfoCollection will be mapped to various Transport Mode fields on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from
AddressType	Can have below values: ConsignorPickupDeliveryAddress – Shipment > Pickup > Pickup From > Pickup By DepartureCFSAddress – Shipment > Pickup > CFS / Transit Warehouse > CFS Departure By ConsigneePickupDeliveryAddress – Shipment > Delivery > Deliver To > Delivery By ArrivalCFSAddress – Shipment > Delivery > CFS / Transit Warehouse > CFS Arrival By
TransportMode	Mapped as per above fields

© 2025 WiseTech Global

3.4.5 AdditionalReferenceCollection

Elements in the AdditionalReferenceCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from
Type	Additional Details tab > Reference Numbers grid > Type field
CountryOfIssue	Additional Details tab > Reference Numbers grid > Country/Region of Issue field
ReferenceNumber	Additional Details tab > Reference Numbers grid > Reference Number field
ContextInformation	Additional Details tab > Reference Numbers grid > Additional Information field
IssueDate	Additional Details tab > Reference Numbers grid > Issue Date field

3.4.6 ContainerCollection

Elements in the ContainerCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from
ContainerCount	Details tab > Containers grid > Container Count field
ContainerNumber	Details tab > Containers grid > Container # field
ContainerType	Details tab > Containers grid > Container Type field

© 2025 WiseTech Global

Element name (XML)	Value mapped from
DeliveryMode	Details tab > Containers grid > Delivery Mode field
FCL_LCL_AIR	Details tab > Containers grid > Container Mode field
Seal	Details tab > Containers grid > Seal/Rate Class field
SealPartyType	Details tab > Containers grid > Sealed By field
SecondSeal	Details tab > Containers grid > Second Seal Number field
SecondSealPartyType	Details tab > Containers grid > Second Sealed By field
TareWeight	Details tab > Containers grid > TareWeight field
TempRecorderSerialNo	Details tab > Containers grid > Temp Recorders Serial Number field
ThirdSeal	Details tab > Containers grid > Third Seal Number field
ThirdSealPartyType	Details tab > Containers grid > Third Sealed By field
TrainWagonNumber	Details tab > Containers grid > Train Wagon Number field
VolumeCapacity	Details tab > Containers grid > Vol. Capacity field
WeightCapacity	Details tab > Containers grid > Wgt. Capacity field

© 2025 WiseTech Global

3.4.6.1 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty

Element Name (XML)	Value Mapped From	Notes
Duration	Shipment > Pickup / Delivery > Container Penalties > Penalty Duration Period	DateTime (Deprecated and to be obsoleted and replaced by DurationAmount in future releases.)
DurationAmount	Shipment > Pickup / Delivery > Container Penalties > Penalty Duration Period	Numeric
FirstFreeDay	Shipment > Pickup / Delivery > Container Penalties > First Free Day	DateTime (This is a calculated field.)
FreeTime	Shipment > Pickup / Delivery > Container Penalties > Free Time Period	DateTime (Deprecated and to be obsoleted and replaced by FreeTimeAmount in future releases.)
FreeTimeAmount	Shipment > Pickup / Delivery > Container Penalties > Free Time Period	Numeric
LastFreeDay	Shipment > Pickup / Delivery > Container Penalties > Last Free Day	DateTime (This is a calculated field.)

© 2025 WiseTech Global

Element Name (XML)	Value Mapped From	Notes
PerUnitCost	Shipment > Pickup / Delivery > Container Penalties > Override Sell per Unit	Numeric (Deprecated and to be obsoleted and replaced by PerUnitSell in future releases.)
PerUnitSell	Shipment > Pickup / Delivery > Container Penalties > Override Sell per Unit	Numeric
TimeUnit	Shipment > Pickup / Delivery > Container Penalties > Unit of Period	String
TotalCost	Shipment > Pickup / Delivery > Container Penalties > Override Total Sell	Numeric (Deprecated and to be obsoleted and replaced by TotalSell in future releases.)
TotalSell	Shipment > Pickup / Delivery > Container Penalties > Override Total Sell	Numeric

3.4.6.2 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Creditor

Element Name (XML)	Value Mapped From	Notes
AddressType	'Creditor'	String
Address1	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Address 1	String

© 2025 WiseTech Global

Element Name (XML)	Value Mapped From	Notes
Address2	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Address 2	String
AddressOverride	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Override Additional Address Information	Boolean
AddressShortCode	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Address > Address Short Code	String
City	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > City	String
Country	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Country	
CompanyName	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Address > Address Details > Company Name	String
Email	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Email	String
Fax	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Fax	String
GovRegNum	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Registration Number field	String
OrganizationCategory	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Organisation Category	String

© 2025 WiseTech Global

Element Name (XML)	Value Mapped From	Notes
OrganizationCode	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Organisation Code	String
Phone	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Phone	String
Port	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > UNLOCO	
Postcode	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Postcode	Numeric
ScreeningStatus	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Screening Status	
State	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > State	String

3.4.6.3 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Creditor / GovRegNumType

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Registration Type (Code)	String
Description	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Registration Type (Description)	String

© 2025 WiseTech Global

3.4.6.4 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Creditor / Country

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Country/Region's Country/Region > ISO Code	String
Name	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Country/Region's Country/Region > Country/Region Name	String

3.4.6.5 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Creditor / Port

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > UNLOCO Code	String
Name	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > UNLOCO's UNLOCO > Port Name	String

© 2025 WiseTech Global

3.4.6.6 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Creditor / ScreeningStatus

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Details > Screening Status (Code)	String
Description	Shipment > Pickup / Delivery > Container Penalties > Creditor Org's Organisation > Details > Details > Screening Status (Description)	String

3.4.6.7 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Creditor / RegistrationNumberCollection / RegistrationNumber

Element Name (XML)	Value Mapped From	Notes
Value	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Config > Registration Numbers/ Codes > Registration Number / Code	String

© 2025 WiseTech Global

3.4.6.8 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Creditor / RegistrationNumberCollection / RegistrationNumber / Type

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Config > Registration Numbers/ Codes > Type (Code)	String
Description	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Config > Registration Numbers/ Codes > Type (Description)	String

3.4.6.9 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Creditor / RegistrationNumberCollection / RegistrationNumber / CountryOfIssue

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Config > Registration Numbers/ Codes > Country/Region Of Issue	String
Name	Shipment > Pickup / Delivery > Container Penalties > Creditor's Organisation > Details > Config > Registration Numbers/ Codes > Country/Region Of Issue's Country/Region > Name	String

© 2025 WiseTech Global

3.4.6.10 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / CreditorType

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Creditor Type (Code)	String
Description	Shipment > Pickup / Delivery > Container Penalties > Creditor Type (Description)	String

3.4.6.11 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Currency

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Currency	String
Description	Shipment > Pickup / Delivery > Container Penalties > Currency's Currency > Description	String

© 2025 WiseTech Global

3.4.6.12 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / Location

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Location	String
Name	Shipment > Pickup / Delivery > Container Penalties > Location's UNLOCO > Port Name	String

3.4.6.13 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / PenaltyType

Element Name (XML)	Value Mapped From	Notes
Code	Shipment > Pickup / Delivery > Container Penalties > Penalty Type	String
Description	Shipment > Pickup / Delivery > Container Penalties > Penalty Description	String

© 2025 WiseTech Global

3.4.6.14 ContainerCollection / ContainerPenaltyCollection / ContainerPenalty / ProcessType

Element Name (XML)	Value Mapped From	Notes
Code	'PIC' for Shipment > Pickup > Container Penalties 'DLV' for Shipment > Delivery Container Penalties	String
Description	'PIC' for Shipment > Pickup > Container Penalties 'DLV' for Shipment > Delivery Container Penalties	String

3.5 Links from containers to PackingLines

The ContainerCollection will be imported or exported when the shipment is linked to the consolidation in CargoWise.

To import the container number in the shipment packing line, each container under the UXML's ContainerCollection at the consol level must have a <Link> element and an assigned number.

As shown below for ContainerNumber TCLU9384055, Link 1:

```
<ContainerCollection Content="Complete">
  <Container>
    <ContainerNumber>TCLU9384055</ContainerNumber>
    <ContainerType>
      <Code>20GP</Code>
      <Category>
        <Code>DRY</Code>
        <Description>Dry Storage</Description>
      </Category>
      <Description>Twenty foot general purpose</Description>
      <ISOCode>22G0</ISOCode>
    </ContainerType>
    <DeliveryMode>CY/CY</DeliveryMode>
    <FCL_LCL_AIR>
      <Code>FCL</Code>
      <Description>Full Container Load</Description>
    </FCL_LCL_AIR>
    <GoodsWeight>14560</GoodsWeight>
    <GrossWeight>16560</GrossWeight>
    <Link>1</Link>
    <TareWeight>2000</TareWeight>
    <WeightUnit>
      <Code>KG</Code>
      <Description>Kilograms</Description>
    </WeightUnit>
  </Container>
</ContainerCollection>
```


© 2025 WiseTech Global

That link number must then be applied to the corresponding pack line under the sub shipment level against the <ContainerLink> element, as shown here:


```xml
<PackingLineCollection Content="Complete">
  <PackingLine>
    <Commodity>
      <Code>GEN</Code>
      <Description>GENERAL</Description>
    </Commodity>
    <ContainerLink>1</ContainerLink>
    <ContainerNumber>TCLU9384055</ContainerNumber>
    <ContainerPackingOrder>1</ContainerPackingOrder>
    <CountryOfOrigin>
      <Code>AU</Code>
      <Name>Australia</Name>
    </CountryOfOrigin>
    <GoodsDescription>GOODS DESCRIPTION</GoodsDescription>
    <HarmonisedCode>9380404988</HarmonisedCode>
    <Link>1</Link>
    <PackQty>22</PackQty>
    <PackType>
      <Code>PLT</Code>
      <Description>Pallet</Description>
    </PackType>
    <Volume>14.59</Volume>
    <VolumeUnit>
      <Code>M3</Code>
      <Description>Cubic Metres</Description>
    </VolumeUnit>
    <Weight>14560</Weight>
    <WeightUnit>
      <Code>KG</Code>
      <Description>Kilograms</Description>
    </WeightUnit>
    <Width>0.500</Width>
  </PackingLine>
</PackingLineCollection>
```


If you would like to generate a working example and see how the XML is structured, open up an existing consol (the container needs to have allocated packlines), then click on the **Actions** menu and select **Send Universal XML> UniversalShipment**.

The file created will display how the ContainerLink and Link elements are used.

For further information on Link Elements, please review the section in the eAdaptor – Developer's Guide.

© 2025 WiseTech Global

3.5.1 DateCollection

Elements in the DateCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from
Arrival	Basic Registration tab > ETA field
BillIssued	Basic Registration tab > Issue Date field
Departure	Basic Registration tab > ETD field
ShippedOnBoard	Basic Registration tab > On Board field

3.5.2 NoteCollection

Elements in the NoteCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from
Description	Notes tab > Description field
IsCustomDescription	Notes tab > Custom field
NoteText	Notes tab > Note field
NoteContext	Notes tab > Module/Direction/Freight field
Visibility	Notes tab > Visibility field
VisibleCompany	Notes tab > Company field

© 2025 WiseTech Global

3.5.3 OrganizationAddressCollection

Elements in the OrganizationAddressCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped f	Notes
ArrivalCFSAddress	Delivery tab > CFS field	
AssuredPartyDocumentaryAddress	Addresses tab > Address grid > Assured Party Documentary Address field	
BuyerDocumentaryAddress	Addresses tab > Address grid > Buyer Documentary Address field	
ClaimsPayableByDocumentaryAddress	Addresses tab > Address grid > Claims Payable By Documentary Address field	
ConsigneeDocumentaryAddress	Basic Registration tab > Consignee field	Inbound: if ConsigneeDocumentaryAddress is not found, fallback to ConsigneeAddress

© 2025 WiseTech Global

Element name (XML)	Value mapped f	Notes
ConsigneePickupDeliveryAddress	Addresses tab > Address grid > Consignee Pickup/Delivery Address field	
ConsignorDocumentaryAddress	Basic Registration tab > Consignor field	
ConsignorPickupDeliveryAddress	Addresses tab > Address grid > Consignor Pickup/Delivery Address field	
ControllingAgent	Addresses tab > Address grid > Controlling Agent field	
ControllingCustomer	Addresses tab > Address grid > Controlling Customer Address field	AddressType schema version 2011_11 will use ShipmentControllingParty schema version 2011_12 will use ControllingCustomer
DeliveryAgent	Delivery tab > Delivery Agent field	

© 2025 WiseTech Global

Element name (XML)	Value mapped f	Notes
DeliveryLocalCartage	Delivery tab > Delivery Transport Company field	Outbound: DeliveryLocalCartage Inbound: if DeliveryLocalCartage is not found, fallback to LocalCartageDeliverToAddress
DepartureCFSAddress	Pickup tab > CFS field	
ExportBroker	Pickup > Details tab > Export Broker field	
GeoLocation	Generated value	Internal Use only – <Latitude>, <Longitude>
HouseBillIssuingParty	Addresses tab > Address grid > House Bill Issuing Party field	
ImportBroker	Delivery > Details tab > Import Broker field	
InsuredByDocumentaryAddress	Addresses tab > Address grid > Insured By Documentary Address field	

© 2025 WiseTech Global

Element name (XML)	Value mapped f	Notes
LocalClient	Basic Registration tab > Local Client field	
Manufacturer	Addresses tab > Address grid > Goods Manufacturer Address field	
NotifyParty	Addresses tab > Address grid > Notify Party field	
NotifyParty2	Addresses tab > Address grid > Notify Party 2 field	
NotifyParty3	Addresses tab > Address grid > Notify Party 3 field	
OverseasAgent	Billing tab > Overseas Agent field	
PickupAgent	Addresses tab > Address grid > Pickup Agent field	

© 2025 WiseTech Global

Element name (XML)	Value mapped f	Notes
PickupLocalCartage	Pickup tab > Pickup Transport Company field	Outbound: PickupLocalCartage Inbound: if PickupLocalCartage is not found, fallback to TransportCompanyDocumentary Address or LocalCartagePickupFromAddress Fallback will occur when xml element is not found
SurveyReportPartyDocumentaryAddress	Addresses tab > Address grid > Survey Report Obtained From Documentary Address field	

3.5.4 PackingLineCollection

Elements in the PackingLineCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from
Commodity	Packing tab > Commodity field
ContainerPackingOrder	Packing tab > Pack Lines grid > Packing Order field
CountryOfOrigin	Packing tab > Origin field
DetailedDescription	Packing tab > Pack Lines grid > Detailed Description field
EndItemNo	Packing tab > Pack Lines grid > EndItemNo field

© 2025 WiseTech Global

Element name (XML)	Value mapped from
ExportReferenceNumber	Packing tab > Pack Lines grid > Export Ref Number field
GoodsDescription	Packing tab > Goods Description field
HarmonisedCode	Packing tab > HarmonisedCode field
Height	Packing tab > Height field
ImportReferenceNumber	Packing tab > Pack Lines grid > Import Ref Number field
ItemNo	Packing tab > Pack Lines grid > Item No field
Length	Packing tab > Length field
LengthUnit	Packing > Height > Packing tab > Pack Lines grid > UD field
LinePrice	Packing tab > Line Price field
LoadingMeters	Packing tab > Pack Lines grid > LoadingMeters field
MarksAndNos	Packing tab > Marks & Numbers field
OutturnComment	Packing tab > Outturn section > Outturned Comment section > Packing tab > Pack Lines grid > Outturned Comments field
OutturnDamagedQty	Packing tab > Outturn section > Outturned Comment section > Packing tab > Pack Lines grid > Damaged Packages field
OutturnedLength	Packing tab > Outturn section > Length field

© 2025 WiseTech Global

Element name (XML)	Value mapped from
OutturnedVolume	Packing tab > Outturn section > Outturned Volume > Packing tab > Pack Lines grid > Outturned Volume field
OutturnedWeight	Packing tab > Outturn section > Outturned Weight field
OutturnedWidth	Packing tab > Outturn section > Outturned Width field
OutturnPillagedQty	Packing tab > Outturn section > Pillaged > Packing tab > Pack Lines grid > Pillaged field
OutturnQty	Packing tab > Outturn section > Packs field
PackQty	Packing tab > Packs field
PackType	Packing tab > Packages field
ReferenceNumber	Packing tab > Ref Number field
Volume	Packing tab > Volume field
VolumeUnit	Packing > Volume > Packing tab > Pack Lines grid > UV field
Weight	Packing tab > Weight field
WeightUnit	Packing > Weight > Packing tab > Pack Lines grid > UW field
Width	Packing tab > Width field

* The PackingLineCollection will not be imported when the shipment type is co-load master

© 2025 WiseTech Global

or blind co-load master or assembly master.

3.5.5 PackingLine > UNDGCollection

Elements in the UNDGCollectionCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from	Notes
Contact	Packing tab > DG Contact > Packing tab > Pack Lines grid > DG Contact field	
FlashPoint	Packing tab > Flash Point > Packing tab > Pack Lines grid > Flash Point field	
IMOClass	Packing tab > DG Class > Packing tab > Pack Lines grid > DG Class field	IMOClass will be imported only UNDGCode is blank in CargoWise
MarinePollutant	Packing tab > Pack Lines grid > Marine Pollutant field	
TechnicalName	Packing tab > Pack Lines grid > Technical Name field	
UNDGCode	Packing tab > DG Substance > Packing tab > Pack Lines grid > DG Subs field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
Volume	Packing tab > Pack Lines grid > DG Volume field	
VolumUQ	Packing tab > Pack Lines grid > DG UV field	
Weight	Packing tab > Pack Lines grid > DG Weight field	
WeightUQ	Packing tab > Pack Lines grid > DG UW field	

3.5.6 TransportLegCollection

Elements in the TransportLegCollection will be mapped to various user controls on forwarding shipment form. Please see the table below:

Element name (XML)	Value mapped from	Notes
ActualArrival	Routing tab > ATA field	
ActualDeparture	Routing tab > ATD field	
ArrivalAt	Routing tab > Arrival At field	
Carrier	Routing tab > Carrier field	
CarrierBookingReference	Routing tab > Carrier Reference field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
CarrierServiceLevel	Routing tab > Carrier Service Level field	
Creditor	Routing tab > Creditor field	
DepartureFrom	Routing tab > Dep. From field	
DocumentCutOff	Routing tab > Docs Due field	
EstimatedArrival	Routing tab > ETA field	
EstimatedDeparture	Routing tab > ETD field	
FCLAvailability	Routing tab > FCL Availability field	
FCLCutOff	Routing tab > FCL Cut Off field	
FCLReceivalCommences	Routing tab > FCL Receival field	
FCLStorage	Routing tab > FCL Storage field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
GreenhouseGasEmission	**Routing** tab > CO2e field	**FOR EXPORT ONLY:** <CO2e>, <CO2eUnit>, <CO2eDescriptiveStatus> **INTERNAL ONLY:** CO2eDistanceInKm>, <CO2ePerTEU>, <CO2ePerTonne>, <CO2eStatus>, <GreenhouseGasCollection>, <GreenhouseGas>
IsCargoOnly	Routing tab > Is Cargo Only field	
LegNotes	Routing tab > Leg Notes field	
LegOrder	Routing tab > Leg Order field	
PortOfDischarge	Routing tab > Discharge Port field	
TransportMode	Routing tab > Transport Mode field	
TransportType	Routing tab > Transport Type field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
VesselLloydsIMO	Routing tab > Vessel Name field	System will look up the vessel name based on VesselLloydsIMO
VGMCutOff	Routing tab > VGM Cut Off field	
VoyageFlightNo	Routing tab > Voyage / Flight field	Label will change based on transport mode

When importing, the transport leg will not update if the sailing schedule already archived and sailing data has not changed. (LCLAvailableDate, LCLCutOff, LCLReceivalCommences, LCLStorageDate, EstimatedDeparture, ActualDeparture, EstimatedArrival, ActualArrival, DepartureFrom, ArrivalAt)

3.5.7 PreCarriageShipmentCollection

3.5.7.1 PreCarriageShipmentCollection – FCL Container Mode

Elements in the PreCarriageShipmentCollection will be mapped to various user controls on forwarding shipment **Pickup** tab. This part is applied to FCL container mode. Please see the table below:

Element name (XML)	Value mapped from	Notes
Instruction.Type	Code – PIC > Description - Pickup	Fixed value
Instruction.Address	Pickup > Confirmations tab > Address field	Only present when **Change** and **Override** boxes are ticked.

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
Instruction.DropMode	Pickup > Confirmations tab > Drop Mode field	
Instruction.Equipment	Pickup > Confirmations tab > Vehicle Registration field	
Instruction.ServiceInstruction	Pickup > Confirmations tab > Notes field	
InstructionContainerLink.ContainerLink	Unique (per XML) ID for Container Element	Relation to container
Confirmation.DateDescription	'PIC'	Pickup confirmation
Confirmation.EstimatedDate	Pickup > Confirmations tab > Estimated field	
Confirmation.RequiredToDate	Pickup > Confirmations tab > Requested By field	
Confirmation.ActualDate	Pickup > Confirmations tab > Picked Up At field	
Confirmation.ReceivedBy	Pickup > Confirmations tab > Goods Signed By field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
Confirmation.Distance	Pickup > Confirmations tab > Driving Distance field	Distance value
Confirmation.DistanceUnit	Pickup > Confirmations tab > Driving Distance field	Distance unit KM or MI.

* The PreCarriageShipmentCollection only supports export and will not be imported.

3.5.7.2 PreCarriageShipmentCollection – Non-FCL Container Modes

Elements in the PreCarriageShipmentCollection will be mapped to various user controls on forwarding shipment **Pickup** tab. This part is applied to Non-FCL Container Modes.

Please see the table below:

Element name (XML)	Value mapped from	Notes
Instruction.Type	Code – PIC > Description - Pickup	Fixed value
Instruction.Address	Pickup > Confirmations tab > Address field	Only present when **Change** and **Override** boxes are ticked.
Instruction.DropMode	Pickup > Confirmations tab > Drop Mode field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
Instruction.Equipment	Pickup > Confirmations tab > Vehicle Registration field	
Instruction.ServiceInstruction	Pickup > Confirmations tab > Notes field	Pickup instructions
InstructionPackingLineLink .PackingLineLink	Unique (per XML) ID for Packing Line	Relation to packing line
InstructionPackingLineLink .Quantity	Pickup > Confirmations tab > Packs Delivered field	From **Packages** grid
Confirmation.DateDescription	'PIC'	Pickup confirmation
Confirmation.EstimatedDate	Pickup > Confirmations tab > Estimated field	
Confirmation.RequiredToDate	Pickup > Confirmations tab > Requested By field	
Confirmation.ActualDate	Pickup > Confirmations tab > Picked Up At field	

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
Confirmation.ReceivedBy	Pickup > Confirmations tab > Goods Signed By field	
Confirmation.Distance	Pickup > Confirmations tab > Driving Distance field	Distance value
Confirmation.DistanceUnit	Pickup > Confirmations tab > Driving Distance field	Distance unit KM or MI.

* The PreCarriageShipmentCollection only supports export and will not be imported.

© 2025 WiseTech Global

3.5.8 PostCarriageShipmentCollection

3.5.8.1 PostCarriageShipmentCollection – FCL or BCN Container Mode

Elements in the PostCarriageShipmentCollection will be mapped to various user controls on forwarding shipment Delivery tab. This part is applied to FCL container mode with various transport mode, or BCN container mode with SEA transport mode. Please see the table below:

Element name (XML)	Value mapped from	Notes
Instruction.Type	Code – DLV > Description - Delivery	Fixed value
Instruction.Address	Delivery > Confirmations tab > Address field	Only present when **Change** and **Override** boxes are ticked.
Instruction.DropMode	Delivery > Confirmations tab > Drop Mode field	
Instruction.Equipment	Delivery > Confirmations tab > Vehicle Registration field	
Instruction.ServiceInstruction	Delivery > Confirmations tab > Notes field	
InstructionContainerLink.ContainerLink	Unique (per XML) ID for Container Element	Relation to container
Confirmation.DateDescription	'DLV'	Delivery confirmation

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
Confirmation.EstimatedDate	Delivery > Confirmations tab > Estimated field	
Confirmation.RequiredToDate	Delivery > Confirmations tab > Requested By field	
Confirmation.ActualDate	Delivery > Confirmations tab > Actual field	
Confirmation.ReceivedBy	Delivery > Confirmations tab > Goods Signed By field	
Confirmation.Distance	Delivery > Confirmations tab > Driving Distance field	Distance value

* The PostCarriageShipmentCollection only supports export and will not be imported.

© 2025 WiseTech Global

3.5.8.2 PostCarriageShipmentCollection – Other Container Modes

Elements in the PostCarriageShipmentCollection will be mapped to various user controls on forwarding shipment Delivery tab. This part is applied to other container modes other than FCL with various transport mode or BCN with SEA transport mode. Please see the table below:

Element name (XML)	Value mapped from	Notes
Instruction.Type	**Code** – DLV > **Description** - Delivery	Fixed value
Instruction.Address	Delivery > Confirmations tab > Address field	Only present when **Change** and **Override** boxes are ticked.
Instruction.DropMode	Delivery > Confirmations tab > Drop Mode field	
Instruction.Equipment	Delivery > Confirmations tab > Vehicle Registration field	
Instruction.ServiceInstruction	Delivery > Confirmations tab > Notes field	Pickup instructions
InstructionPackingLineLink .PackingLineLink	Unique (per XML) ID for Packing Line	Relation to packing line
InstructionPackingLineLink .Quantity	Delivery > Confirmations tab > Packs Delivered field	From **Packages** grid

© 2025 WiseTech Global

Element name (XML)	Value mapped from	Notes
Confirmation.DateDescription	'DLV'	Delivery confirmation
Confirmation.EstimatedDate	Delivery > Confirmations tab > Estimated field	
Confirmation.RequiredToDate	Delivery > Confirmations tab > Requested By field	
Confirmation.ActualDate	Delivery > Confirmations tab > Actual field	
Confirmation.ReceivedBy	Delivery > Confirmations tab > Goods Signed By field	
Confirmation.Distance	Delivery > Confirmations tab > Driving Distance field	Distance value
Confirmation.DistanceUnit	Delivery > Confirmations tab > Driving Distance field	Distance unit KM or MI.

* The PostCarriageShipmentCollection only supports export and will not be imported.

© 2025 WiseTech Global

3.5.9 GatewayInfoCollection

Elements in GatewayInfoCollection are mapped to the Gateways grid in Forwarding Shipment Additional Detail tab.

Forwarder	Selected forwarder address from Additional Detail > Gateway grid > Code & Address	The full name and address details are defaulted from the selected Forwarder's code and address.
Order	Additional Detail > Gateway Grid > Order	This is a read-only field and can only be changed with the directional buttons to the right of the grid.

© 2025 WiseTech Global

4. Sample files

Refer to the eAdaptor Sample Interfaces Pack under **WiseTech Academy > CargoWise > Technical Guides**.

4.1 Universal Shipment

- **UniversalShipment_ForwardingShipment_DataTarget_SEA_NoConsol.xml** – creates a standalone SEA shipment in CargoWise.
- **UniversalShipment_ForwardingShipment_DataTarget_SEA_WithConsol.xml** – creates a SEA shipment and a consolidation in CargoWise and attaches the shipment to the consolidation.
- **UniversalShipment_ForwardingShipment_DataTarget_AIR_NoConsol.xml** – creates a standalone AIR shipment in CargoWise.
- **UniversalShipment_ForwardingShipment_DataTarget_AIR_WithConsol.xml** – creates an AIR shipment and a consolidation in CargoWise and attached the shipment to the consolidation. Contains GreenhouseGasEmission example.
- **UniversalShipment_ForwardingShipment_DataTarget_SEA_FCL_WithConsol.xml** – exported sample showing PreCarriageShipmentCollection and PostCarriageShipmentCollection from a SEA FCL shipment.
- **UniversalShipment_ForwardingShipment_DataTarget_AIR_LSE_WithConsol.xml** – exported sample showing PreCarriageShipmentCollection and PostCarriageShipmentCollection from an AIR LSE shipment. Contains GreenhouseGasEmission example.
- **Universal Event**
- **UniversalEvent_BKD_HBOLNumber_Context.xml** – this UniversalEvent does not have a data target, it will use the HBOLNumber to match and link to a shipment when importing into CargoWise.
- **UniversalEvent_FLO_ForwardingShipment_DataTarget.xml** – this UniversalEvent uses the data target to match the shipment when imported into CargoWise.
- **UniversalShipment_ForwardingShipment_ContainerPenalty.xml** – Contains ContainerPenalty example.

Support: Press the **F1** key from anywhere within CargoWise to raise an eRequest.

© 2025 WiseTech Global