



Title

rdrandinf — Randomization Inference for RD Designs under Local Randomization.

Syntax

```
rdrandinf outvar runvar [if] [in] [, cutoff(#) wl(#) wr(#) statistic(stat_name)
p(#) vce(hc1|hc2|hc3) evalr(#) evalr(#) kernel(kerneltype) fuzzy(fuzzy_var
[fuzzy_stat]) nulltau(#) d(#) dscale(#) ci(level [tlist]) interfci(#)
bernoulli(varname) reps(#) seed(#) covariates(varlist) obsmin(#) wmin(#) #)
wobs(#) wstep(#) wasymmetric wmasspoints nwindows(#) rdwstat(stat_name)
dropmissing approximate rdwreps(#) level(#) plot graph_options(graphopts)
obsstep(#) firststage quietly ]
```

Description

rdrandinf implements randomization inference and related methods for regression discontinuity (RD) designs, employing observations in a specified or data-driven selected window around the cutoff where local randomization is assumed to hold. See [Cattaneo, Frandsen and Titiunik \(2015\)](#) and [Cattaneo, Titiunik and Vazquez-Bare \(2017\)](#) for an introduction to this methodology.

A detailed introduction to this command is given in [Cattaneo, Titiunik and Vazquez-Bare \(2016\)](#).

Companion R and Python packages are also available [here](#).

Companion functions are [rdwinselect](#), [rdsensitivity](#) and [rdrbounds](#).

Related R, Python, and Stata packages useful for inference in RD designs are described in the following website:

<https://rdpackages.github.io/>

With **p()** greater than zero, mean contrasts and fuzzy Anderson-Rubin and TSLS/Wald tests use normal inference from the full polynomial regression, with HC3 standard errors by default. No randomization p-value is computed. HC3 does not guarantee finite-sample size control, and TSLS/Wald requires a sufficiently strong first stage. TSLS uses structural residuals and projected-regressor leverage. Fuzzy Anderson-Rubin confidence sets require an explicit grid in **ci()**. For **ksmirnov**, **ranksum**, **all**, or **interfci**, positive **p** becomes **p(0)** with a final warning. At **p(0)**, existing inference methods and variance defaults are retained; TSLS honors **nulltau()** and the requested CI level.

Options

cutoff(#) specifies the RD cutoff for the running variable *runvar*. Default is **cutoff(0)**.

_____ Window selection _____

wl(#) specifies the left limit of the window. Default is the minimum value of the running variable.

wr(#) specifies the right limit of the window. Default is the maximum value of the running variable.

_____ Statistic _____

statistic(stat_name) specifies the statistic to be used. Options are:
diffmeans for difference in means statistic. This is the default option.
ksmirnov for Kolmogorov-Smirnov statistic.
ranksum for Wilcoxon-Mann-Whitney studentized statistic.
all for all three statistics.
The option **ttest** is equivalent to **diffmeans** and included for backward compatibility.

p(#) specifies the order of the polynomial for outcome adjustment model. Default is **p(0)** (constant treatment effect model).

vce(hc1/hc2/hc3) selects the heteroskedasticity-consistent variance estimator for **p()** greater than zero. Default is **vce(hc3)**. Ignored when **p(0)**.

evall(#) specifies the point at the left of the cutoff at which the adjusted outcome is evaluated. Default is the cutoff value.

evalr(#) specifies the point at the right of the cutoff at which the adjusted outcome is evaluated. Default is the cutoff value.

kernel(kerneltype) specifies the type of kernel to use as a weighting scheme. Allowed kernel types are **uniform** (uniform kernel), **triangular** (triangular kernel), and **epan** (Epanechnikov kernel). Default is **kernel(uniform)**.

fuzzy(fuzzy_var [fuzzy_stat]) specifies the endogenous treatment variable in a fuzzy design. Options for the fuzzy statistic are:
itt for the intention-to-treat (ITT) statistic (this is the default option),
tsls for the two-stage least squares (TSLs) statistic (asymptotic approximation only).

firststage shows output from the first-step regression when using TSLs.

Inference

nulltau(#) sets the value of the treatment effect under the null hypothesis. Default is **nulltau(0)**.

d(#) specifies the effect size for asymptotic power calculation. Default is 0.5 times the standard deviation of the outcome variable for the control group.

dscale(#) specifies the fraction of the standard deviation of the outcome variable for the control group used as the alternative hypothesis for asymptotic power calculation. Default is **dscale(.5)**.

ci(alpha [tlist]) calculates a confidence interval for the treatment effect. *alpha* specifies the significance level (typically 0.05 or 0.01); *tlist* specifies a treatment-effect grid. TSLs uses normal intervals. Polynomial sharp-design mean contrasts use normal intervals unless a grid is supplied. Other cases invert tests over a grid; polynomial fuzzy Anderson-Rubin requires an explicit grid. At **p(0)**, test inversion uses **rd sensitivity**. Use a sufficiently wide grid to avoid truncating the confidence set.

interfci(#) sets the significance level (alpha) for Rosenbaum's confidence interval under arbitrary interference between units.

bernoulli(varname) specifies that the randomization mechanism is Bernoulli trials (instead of fixed margins randomization). The probability of treatment for each unit must be provided in the variable **varname**.

reps(#) specifies the number of replications. Default is **reps(1000)**.

seed(#) sets the seed for the permutation test. With this option, the user can manually set the desired seed, or can enter the value -1 to use the system seed. Default is **seed(666)**.

Options for rdwinselect

When the window around the cutoff is not specified, **rdrandinf** can select the window automatically using the companion command **rdwinselect**. The following options are available:

covariates(varlist) specifies the covariates used by the companion command **rdwinselect**.

obsmin(#) specifies the minimum number of observations above and below the cutoff in the smallest window used by the companion command **rdwinselect**. Default is **obsmin(10)**.

wmin(# #) specifies the initial window to be used (if **obsmin(#)** is not specified). Can be a single number to specify the length of the (symmetric) initial window, or two numbers to specify the left and right limits of the initial window. Specifying both **wmin(#)** and **obsmin(#)** returns an error.

wobs(#) specifies the number of observations to be added at each side of the cutoff at each step. Default is **wobs(5)**.

wstep(#) specifies the increment in window length (if **obsstep(#)** is not specified) by the companion command rdwinselect. Specifying both **wobs(#)** and **wstep(#)** returns an error.

wasymmetric allows for asymmetric windows around the cutoff (when **wobs(#)** is specified).

wmasspoints specifies that the running variable is discrete and each masspoint should be used as a window.

nwindows(#) specifies the number of windows to be used by the companion command rdwinselect. Default is **nwindows(10)**.

dropmissing drops rows with missing values in covariates when calculating windows.

rdwstat(#) specifies the statistic to be used by the companion command rdwinselect (see help file for options). Default option is **rdwstat(diffmeans)**.

approximate specifies that covariate balance tests should use a large-sample approximation instead of finite-sample exact randomization inference methods.

rdwreps(#) specifies the number of replications to be used by the companion command rdwinselect. Default is **rdwreps(1000)**.

level(#) specifies the minimum accepted value of the p-value from the covariate balance tests to be used by the companion command rdwinselect. Default is **level(.15)**.

plot draws a scatter plot of the minimum p-value from the covariate balance test against window length implemented by the companion command rdwinselect.

graph_options(*graphopts*) specifies graph options for the plot generated by the companion command rdwinselect.

quietly suppresses output from the companion command rdwinselect.

obsstep(#) specifies the minimum number of observations to be added on each side of the cutoff by the companion command rdwinselect. This option is deprecated and only included for backward compatibility.

Example: Cattaneo, Frandsen and Titiunik (2015) Incumbency Data

Setup

```
. use rdlocrand_senate.dta, clear
```

Randomization inference with user-specified window and default options

```
. rdrandinf demvoteshfor2 demmv, cutoff(0) wl(-.75) wr(.75)
```

Randomization inference with all statistics

```
. rdrandinf demvoteshfor2 demmv, cutoff(0) wl(-.75) wr(.75) stat(all)
```

Randomization inference with triangular weights

```
. rdrandinf demvoteshfor2 demmv, cutoff(0) wl(-.75) wr(.75) kernel(triangular)
```

Randomization inference on the Kolmogorov-Smirnov statistic with rdwinselect window options

```
. rdrandinf demvoteshfor2 demmv, cutoff(0) statistic(ksmirnov)
covariates(dopen population demvoteshlag1) wmin(.5) wstep(.125)
```

Randomization inference with linear adjustment

```
. rdrandinf demvoteshfor2 demmv, cutoff(0) wl(-.75) wr(.75) p(1)
```

Randomization inference under Bernoulli trials with .5 probability of treatment

```
. gen probs=.5
. rdrandinf demvoteshfor2 demmv, cutoff(0) wl(-.75) wr(.75) bernoulli(probs)
```

Confidence interval under interference

```
. rdrandinf demvoteshfor2 demmv, cutoff(0) wl(-.75) wr(.75) interfci(.05)
```

Confidence interval for the treatment effect

```
. rdrandinf demvoteshfor2 demmv, wl(-.75) wr(.75) ci(.05 3(1)20)
```

Linear adjustment with effects evaluated at the mean of the running variable

```
. qui sum demmv if abs(demmv)<=.75 & demmv>=0 & demmv!=. & demvoteshfor2!=.
. local mt=r(mean)
. qui sum demmv if abs(demmv)<=.75 & demmv<0 & demmv!=. & demvoteshfor2!=.
. local mc=r(mean)
. rdrandinf demvoteshfor2 demmv, wl(-.75) wr(.75) p(1) eval(`mc') evalr(`mt')
```

Saved results

rdrandinf saves the following in **r()**:

Scalars

r(p_requested)	requested polynomial degree
r(p)	order of polynomial in adjusted model
r(se)	standard error when the effective polynomial degree is positive
r(wl)	left end of window used
r(wr)	right end of window used
r(N)	sample size in used window
r(N_left)	sample size in used window to the left of the cutoff
r(N_right)	sample size in used window to the right of the cutoff
r(obs_stat)	observed statistic
r(randpval)	randomization p-value; missing when the effective polynomial degree is positive
r(asy_pval)	asymptotic p-value
r(int_lb)	lower limit of confidence interval under interference (if interfci option is specified)
r(int_ub)	upper limit of confidence interval under interference (if interfci option is specified)

Locals

r(vce)	HC estimator when the effective polynomial degree is positive
r(seed)	seed used in permutations

Matrices

r(obs_stat)	matrix of observed statistics (when all is specified)
r(asy_pval)	matrix of asymptotic p-values (when all is specified)
r(p_val)	matrix of p-values (when all is specified)
r(CI)	confidence interval matrix (if ci option is specified)

References

- Cattaneo, M. D., Frandsen, B., and R. Titiunik. 2015. [Randomization Inference in the Regression Discontinuity Design: An Application to Party Advantages in the U.S. Senate.](#) *Journal of Causal Inference* 3(1): 1-24.
- Cattaneo, M.D., Titiunik, R. and G. Vazquez-Bare. 2016. [Inference in Regression Discontinuity Designs under Local Randomization.](#) *Stata Journal* 16(2): 331-367.
- Cattaneo, M. D., Titiunik, R. and G. Vazquez-Bare. 2017. [Comparing Inference Approaches for RD Designs: A Reexamination of the Effect of Head Start on Child Mortality.](#) *Journal of Policy Analysis and Management* 36(3): 643-681.

Authors

Matias D. Cattaneo, Princeton University, Princeton, NJ.
matias.d.cattaneo@gmail.com.

Rocio Titiunik, Princeton University, Princeton, NJ. rocio.titiunik@gmail.com.

Gonzalo Vazquez-Bare, UC Santa Barbara, Santa Barbara, CA.
gvazquezbare@gmail.com.