

ASTROHARMONY

Chord progressions, shaped by feeling.

VST3 plugin · Standalone application · Windows

User Manual · Version 1.0

Astrotone Audio · 2026

info@astrotoneaudio.com

Contents

§	Section	Page
1.	Welcome	4
2.	Installing & Activating	5
3.	Using AstroHarmony in Your DAW	6
4.	The Workspace at a Glance	8
5.	Choosing a Mood	9
6.	Scale, Mode & Extensions	10
7.	Diatonic & Suspended Chords	11
8.	Suggested Chords	12
9.	Building a Progression	13
10.	Progression Voicing Styles	14
11.	Per-Chord Editing & Slash Bass	15
12.	Piano View	16
13.	Instruments	17
14.	Playback Pitch (Transpose)	18
15.	Projects: Save, Load, Duplicate	19
16.	MIDI Export & Drag-Out	20
17.	Settings	21
18.	Keyboard & Mouse Shortcuts	22
19.	Troubleshooting	23
20.	License Terms (Summary)	25
21.	Support & Contact	26

1. Welcome

AstroHarmony is a chord-progression workbench for composers and producers who want to start from a **feeling** rather than a music-theory grid. Pick a mood, audition harmonies that already fit, drop them onto the timeline, dress them with a voicing style, and play it back in your DAW or export to MIDI.

This release ships in two interchangeable formats:

- **VST3 plugin** — loads inside any modern DAW (FL Studio, Studio One, Reaper, Cubase, Ableton Live, Bitwig). Audio is routed straight to the host's mixer.
- **Standalone application** — a self-contained app for ideation away from the DAW. Same engine, same UI, same projects.

Both formats use the same audio engine, share the same project library on disk, and accept the same licence key.

Built for three audiences

- **Film composers** — cinematic, modal and chromatic-median moves at hand.
- **Game composers** — adaptive harmonic moods per scene, character or level.
- **Beat producers** — lush jazz, neo-soul and gospel voicings without the theory homework.

Everything runs offline once activated. There is no cloud account, no telemetry, and no DAW lock-in — chords leave the app as standard MIDI events that any modern DAW will record or import.

What ships in the box

Component	Detail
Moods	Epic, Dark, Hopeful, Sad, Tension, Mystery, Fantasy, Adventure, Love, Horror
Voicing styles	Standard, Cinematic, Jazz Shell, Piano Spread, Neo Soul, Gospel, Voice Leading, Open Voicing, Quartal, Quintal, Cluster
Instruments	Grand Piano, Strings, Flute, Trumpet — bundled, no separate download
Theory engine	Diatonic and modal chord generation in every common Western mode, plus Harmonic / Melodic Minor and exotic modes
MIDI export	One-click .mid download <i>and</i> drag-out from the EXPORT button straight onto a DAW track

2. Installing & Activating

System requirements

Requirement	Detail
Operating system	Windows 10 version 1809 (October 2018 Update) or later, or Windows 11. 64-bit only.
WebView2 Runtime	Required for the user interface. Ships with Windows 11 and current Windows 10 builds; the installer fetches it from Microsoft if missing.
DAW (for the VST3)	Any VST3-compatible host: FL Studio 20.7+, Studio One 5+, Reaper 6+, Cubase 12+, Ableton Live 11+, Bitwig Studio 4+.
Disk space	About 80 MB after install (binaries + bundled samples).

Running the installer

Double-click `AstroHarmony_Setup_1.0.0.exe`. Windows SmartScreen may show a blue warning because the installer is not yet code-signed — click **More info** → **Run anyway**. When EV code signing is added in a future build, the warning will disappear.

The installer walks you through five screens:

- **License Agreement** — the full EULA. You must click **I accept** to continue. This screen is the legal point at which you activate the EU 14-day right-of-withdrawal waiver for installed copies (Article 16(m) of EU Directive 2011/83/EU).
- **Select Components** — tick what you want: VST3 plugin, Standalone application, or both. The default is “Full installation”.
- **Select Install Location** — where the Standalone goes. The default is `C:\Program Files\Astrotone Audio\AstroHarmony`. The VST3 path is fixed by Steinberg’s spec (see below) and is not configurable.
- **Ready to Install** — final confirmation.
- **Installing** — if WebView2 Runtime is missing, the installer downloads ~1.8 MB from Microsoft and installs it silently before finishing.

Where files land

File	Path
VST3 plugin	<code>C:\Program Files\Common Files\VST3\AstroHarmony.vst3</code>
Standalone app	<code>C:\Program Files\Astrotone Audio\AstroHarmony\AstroHarmony.exe</code>
License agreement	<code>C:\Program Files\Astrotone Audio\AstroHarmony\LICENSE.txt</code>
Your projects	<code>%APPDATA%\AstroHarmony\sessions\</code>
Your licence key	<code>%APPDATA%\AstroHarmony\license.txt</code>

The two paths under %APPDATA%\AstroHarmony are **never touched by the uninstaller**. Reinstalling or upgrading preserves your projects and your activation.

First launch — activation

On first launch (Standalone) or first instance in a DAW (VST3), the app opens on an **Activation** screen. Paste the licence key you received with your purchase (format: XXXX-XXXX-XXXX-XXXX) and click **Activate**. Validation happens locally against a bundled hash list — no internet connection is required and no data is sent.

The key is case-insensitive and accepts spaces. ab12 cd34 ef56 gh78 is treated the same as AB12-CD34-EF56-GH78.

Once activated, the key persists in %APPDATA%\AstroHarmony\license.txt. Both the Standalone and the VST3 read from the same file, so activating one format unlocks the other automatically. Your purchase allows install on up to **three (3) devices**.

3. Using AstroHarmony in Your DAW

AstroHarmony is an **instrument plugin** (not an effect). It produces audio — the chord progression you built — and sends it to a stereo bus in your DAW.

Finding the plugin

After install, ask your DAW to re-scan plugins. AstroHarmony appears under **Vendor: Astrotone Audio, Category: Instrument / Synth / Sampler**.

FL Studio

- Open **Options** → **Manage plugins**.
- Click **Find more plugins** — FL re-scans C:\Program Files\Common Files\VST3\.
- AstroHarmony shows up in the “Recently installed” pane. Click the star to favourite it; right-click → **Add to channel rack** drops it onto the project.

Studio One

Studio One auto-scans on launch. AstroHarmony appears under **Instruments** → **Astrotone Audio**. Drag it onto a track or into empty space in the arrange view to create a new instrument track.

Reaper

- **Options** → **Preferences** → **Plug-ins** → **VST**.
- Confirm C:\Program Files\Common Files\VST3 is in the VST3 paths.
- Click **Re-scan**. AstroHarmony appears as **VST3i: AstroHarmony (Astrotone Audio)**.

Ableton Live

- **Preferences** → **Plug-Ins**. Make sure **Use VST3 Plug-In System Folders** is on.
- Click **Rescan**. The plugin appears under **Plug-Ins** → **VST3** → **Astrotone Audio** in the browser.

4. The Workspace at a Glance

The window is split into three columns and two bars.

Area	What it does
Top bar	Project menu, save / undo / redo, instrument picker, transport (play / stop / loop), tempo, settings.
Mood column (left)	Pick the emotional palette — the rest of the UI reshapes around it.
Centre column	Active progression timeline, suggested chords, scale picker, diatonic and suspended chord rows.
Right panel	Progression voicing style, chord-notes piano view, slash-bass selector.
Bottom bar	Playback pitch shift (-12 to +12 semitones), CLEAR, and EXPORT MIDI.

The divider between the centre and the right panel is draggable. Wider right panel → bigger piano. Narrower right panel → more room for chord buttons. The position is remembered between launches.

When loaded as a VST3, the plugin window can be resized by dragging its bottom-right corner. The UI scales fluidly; the splitter position and zoom level are saved with the DAW project.

5. Choosing a Mood

Each mood ships with three things wired in:

- **Preferred modes** — the scale dropdown auto-snaps to whichever fits the mood best.
- **Suggested chord transitions** — the “Suggested Next Chords” row is built from move templates specific to the mood (Epic loves chromatic mediants, Sad leans on modal interchange, Mystery favours diminished pivots, etc.).
- **Preferred root** — some moods (Epic, Adventure) sound best in flat keys; switching mood may transpose you there.

Clicking a mood while a progression is already on the timeline does *not* destroy what you wrote — only the **suggestions** are re-computed. Your existing chords keep playing as they are.

The ten moods

Mood	Character
Epic	Powerful, grand, heroic — Ionian / Mixolydian / Aeolian.
Dark	Mysterious, ominous — Aeolian / Phrygian / Locrian / Harmonic Minor.
Hopeful	Uplifting, inspiring — bright Ionian + Lydian colour.
Sad	Melancholic, emotional — Aeolian / Dorian / Phrygian.
Tension	Suspenseful, intense — Harmonic Minor, Phrygian Dominant, Diminished.
Mystery	Curious, uncertain — Phrygian, Locrian, Phrygian Major.
Fantasy	Magical, otherworldly — modal mixture with Lydian sparkle.
Adventure	Bold, exciting, dynamic — quartal & pentatonic colour.
Love	Romantic, warm — major / Lydian / Dorian with extensions.
Horror	Dark, scary, eerie — Phrygian, Locrian, exotic minors.

6. Scale, Mode & Extensions

Picking a tonic

The left dropdown holds the tonic note (A, A#, B...G#). The right dropdown holds the mode. The two are independent — you can run D# Locrian or B Lydian if your project asks for it.

Mode families available

Family	Members
Major modes	Ionian, Dorian, Phrygian, Lydian, Mixolydian, Aeolian, Locrian
Harmonic minor	Harmonic Minor, Locrian #6, Ionian #5, Dorian #4, Phrygian Dominant, Lydian #2, Altered Dim (Ultralocrian)
Melodic minor	Melodic Minor, Dorian b2, Lydian Augmented, Lydian Dominant, Mixolydian b6, Locrian #2, Super Locrian (Altered)
Phrygian Major	Aka “Spanish Phrygian” — major third on a Phrygian frame.

Extensions tabs

Above the diatonic rows is a tab strip: **Triad / 6&7 / 9 / 11 / 13**. These select how many notes the chord buttons will generate.

Notes per chord	Example I-chord in C major
3	C E G
4	C E G B (CΔ7) or C E G A (C6)
5	C E G B D (CΔ9)
6, avoid-4 stripped on major-3rd chords	Dm9 + G → Dm11
7, avoid-4 stripped	CΔ13 spread across the row

Major-3rd chords drop the natural 11 automatically — the b9 clash between major 3rd and perfect 11 ruins every voicing. Lydian #11 keeps the colour, and minor chords keep the natural 11 because it sits a clean M9 above the b3.

7. Diatonic & Suspended Chords

Below the scale picker is the chord grid. Each column is a scale degree (I, II, III, IV, V, VI, VII), each row is a chord flavour.

Rows

- **Diatonic Chords** — the seven chords that belong to the current mode at the selected extension level.
- **sus2** — suspended-second variant of every degree, where the third has been replaced by a major second.
- **sus4** — suspended-fourth variant of every degree.

Each pill has two halves. Click the **name** to preview the chord on the piano view without adding it. Click the **+** on the right to drop the chord onto the timeline.

Empty slots

A dashed-outline slot in a row means “the scale doesn’t support a clean version of this chord here” (e.g. sus2 on a degree whose second is a tritone). This is intentional — the app refuses to give you a flat-fifth sus2 because it doesn’t voice well.

8. Suggested Chords

Between the timeline and the scale picker is the **Suggested Next Chords** row. It rebuilds itself each time you change mood, key, extension or the last chord on the timeline.

Each suggestion carries a label (“Heroic Mediant”, “Cinematic Descent”, “Sudden Sorrow”...) describing the harmonic move it makes, plus the Roman numeral of the resulting chord in the current key. Some suggestions come from a *secondary* mode — they show a small ↑ arrow with the borrowed scale’s name.

Borrowed chords

When a suggestion borrows from another mode (for example Dbm/C# ↑ Db Dorian), the chord is shown with its original spelling and a slash bass. The piano view still shows every pitch correctly — double accidentals (Cb, Fb, B#, G##, etc.) are normalised so the keys light up no matter how the chord is spelled.

Suggestions tend to fit best when the current mode matches one of the “X prefers:” chips below the mode dropdown. Picking an exotic mode outside that list (e.g. Epic + Locrian #2) will still produce suggestions — just expect a few chords to live outside the strict scale.

9. Building a Progression

Drop chords onto the timeline by clicking the **+** on either a diatonic pill or a suggestion card. The new chord lands at the end of the progression and is automatically selected so the right-panel controls follow it.

Reordering and resizing

- **Drag** a chord card sideways to reorder it. Colours follow the card so it stays visually distinct after a reorder.
- **Drag the right edge** of a chord card to change how many bars it lasts (snaps to half-bar).
- **×** in the top-right corner of a card removes it.
- **CLEAR** button above the timeline empties the whole progression in one click — no confirm dialog. If you tap it by accident, hit **Ctrl+Z**.

Undo / Redo

Every add / remove / reorder / voicing change pushes onto an unlimited history stack. Use **Ctrl+Z** / **Ctrl+Shift+Z** or the **<** and **>** arrows in the top bar.

10. Progression Voicing Styles

Above the piano view in the right panel is the **Progression Style** dropdown. Picking a style applies the same voicing flavour to every chord on the timeline. Each style ships with four variants — use the < / > arrows under **Selected** to cycle them.

Style	Character
Standard	Inversion-driven triads with optional drop-2.
Cinematic	Modern film-score wide spread: deep bass + mid-high colour tones.
Jazz Shell	Root + 3rd + 7th + colour tone — the classic comping shape.
Piano Spread	Left-hand root + 5th, right-hand 3-7-9 cluster (classical pianist).
Neo Soul	Rootless extensions, Robert Glasper feel.
Gospel	Bass + dense right-hand cluster; great for church-key pads.
Voice Leading	Smoothest path from the previous chord — minimal motion in the upper voices.
Open Voicing	Wide intervals, classical orchestral spread.
Quartal	Stacked fourths; modal jazz colour.
Quintal	Stacked fifths; bright sus-flavoured.
Cluster	Tight close-position, modern dissonance.

The reshuffle button (the circular arrow next to the dropdown) keeps the same style but re-rolls every chord's variant. Hit it a few times if you want to taste the full range of a style without manually stepping through variants.

11. Per-Chord Editing & Slash Bass

Selecting a chord card (click anywhere on it) wires the right panel to that chord.

Variant arrows

< / > next to **Selected** in the right panel cycles through the four variants of the current voicing style for the selected chord only — the rest of the progression is untouched.

Bass Note row

Each chord has a slash bass selector at the bottom of the right panel. Click any chromatic note to set it as the bass; click again to clear back to the chord root. The piano view marks the active bass in dusty rose so you can see at a glance where it sits.

Slash bass changes the lowest sounded note and the MIDI export — both during playback. The chord notes themselves are not rewritten, so analysing the progression after the fact still shows the original Roman numeral.

12. Piano View

The piano view in the right panel shows two distinct things depending on the mode toggle in its top-right corner:

Mode	What lights up
SCALE	Every note that belongs to the current scale across all six octaves.
CHORD	Only the notes of the currently selected chord, voiced exactly as it will play.

Colours

- **Dusty rose** — the bass note (lowest sounding pitch class of the chord).
- **Dusty teal** — the rest of the chord tones at their voiced positions.
- **Empty** (white / dark) — not part of the current chord or scale.

*Heads-up: the piano view shows the **theory pitches**, not the **playback pitches**. If you have the playback pitch shift slider at +5, the audio plays five semitones higher but the piano keeps showing the original chord. This is by design — the visual harmony stays consistent with the chord card labels.*

13. Instruments

In the top bar (just left of the play button) is a pill showing the current instrument’s icon and name. Click it to open the picker. Instruments are grouped by family (Keys, Strings, Woodwinds, Brass).

Range played	Character
A0 – C8	Bright, sustained, every chord tone audible — the de
G2 – B4	Soft attack, long sustain — cinematic pads.
C4 – C7	Pure-tone single voice; renders chords as parallel lin
F#3 – F#5	Brassy attack — great for heroic / Epic-mood sketch

Switching instruments is instant — samples are bundled with the plugin and loaded on demand. The first chord after a switch may have a few milliseconds of extra latency while the new instrument warms up.

All four instruments are designed for clean MIDI export. The note ranges above are what plays back inside AstroHarmony — once you export to MIDI and route the file to your own sampler, every pitch in the progression is preserved at its true register.

14. Playback Pitch (Transpose)

The bottom bar carries a **PITCH** control with a slider, two step buttons (– / +) and a numeric readout. Range: –12 to +12 semitones.

Pitch shift is **playback-only**. It changes what comes out of the speakers and what lands in the exported MIDI file — nothing else.

Stays the same	Changes
Chord names on the timeline	Audio playback
Notes on the piano view	MIDI export pitch
Suggested chords	
Diatonic / suspended chord rows	
Scale picker / mode picker	
Double-click anywhere on the pitch slider to snap it back to 0. Useful when you've been auditioning a key change and want to compare against the original.	

15. Projects: Save, Load, Duplicate

The top-left **Projects**  menu manages all your sessions, stored as JSON files in %APPDATA%\AstroHarmony\sessions\. Standalone and VST3 share the same folder — a project saved in Standalone shows up in the DAW the next time you open the plugin window.

Saving

- **Save** button (next to Projects) overwrites the active session.
- **Save current as new...** at the bottom of the Projects menu opens a dialog asking for a name, then snapshots everything into a fresh session.

Per-session menu

Hover any session row in the Projects menu and three icons appear:

- **Rename** in place.
- **Duplicate** (the copy is suffixed “(copy)”).
- **Delete** — opens a small in-app confirmation modal styled to match the rest of the UI. Press **Enter** to confirm, **Esc** to cancel.

Sessions remember **everything**: progression, mood, scale, voicing style and per-chord variants, instrument, playback pitch, tempo, loop state, and piano-view mode.

Starter projects

Fresh installs ship with three example sessions that you can edit, duplicate or delete freely:

Name	Style
Sad01	A Aeolian · Piano Spread · 100 BPM · Piano
Epic01	D# Ionian · Cinematic · 219 BPM · Trumpet
Love01	F Ionian · Neo Soul · 219 BPM · Flute

The session folder is left alone by the uninstaller. Reinstalling, upgrading to a future version, or moving the install location all keep your projects intact.

16. MIDI Export & Drag-Out

AstroHarmony offers two ways to get a progression out as MIDI. Both produce identical Standard MIDI Files (Type 0).

Method 1: Click EXPORT MIDI

Click the **EXPORT MIDI** button in the bottom right corner. A Save dialog opens; pick a folder and filename. The file is written and the dialog closes — that's it. Use this when you want a long-lived .mid file you can keep, version, or send to a collaborator.

Method 2: Drag the EXPORT MIDI button onto a DAW track

Press and hold the **EXPORT MIDI** button, then drag — the cursor switches to a drag-and-drop icon. Release the mouse over an empty area of an instrument track in your DAW. AstroHarmony writes the file to %TEMP%\AstroHarmony\ and hands it to the DAW as an OS-level file drag. Your DAW imports it as if you had dragged a .mid file from File Explorer.

The drag is triggered after 5 pixels of mouse movement. A normal click (no movement) still opens the Save dialog. So both workflows live on the same button without one stealing from the other.

What's in the file

- **Track name** — the project's name (e.g. "Sad01").
- **Tempo meta-event** — the BPM displayed in the top bar.
- **Time signature** — 4/4 with quarter-note pulse.
- **Note events** — one note-on per voiced pitch at the start of each chord, one note-off at the end of its bar count.
- **Transpose offset** — applied to every note so the file matches what you heard.

Filename

The default filename is the project name "slugified" — lowercased, spaces → dashes, special characters stripped. So a project called *Epic Hero 01* downloads as epic-hero-01.mid. Untitled projects fall back to untitled.mid.

17. Settings

The gear icon (⚙️) on the far right of the top bar opens a small About popover. It shows:

- **AstroHarmony** — product name and tagline (“Chord-progression composer.”).
- **Build** — the version string of the plugin you are running. Include this in any bug report.
- **Copyright** — © 2026 Astrotone Audio.

Full sample credits and open-source-library attribution are reproduced in `LICENSE.txt`, shown during install and available afterwards from the Start Menu (**AstroHarmony** → **License Agreement**) or directly from the install folder.

Closing the popover: click outside it, hit Escape, or click the × in its top-right corner.

Standalone-only: audio device settings

When running the Standalone, an extra **Options** menu in the top menu bar exposes the host's audio device settings — output device, sample rate, buffer size, MIDI input device. These are JUCE's standard standalone-host controls. The VST3 version inherits these settings from your DAW and exposes none of its own.

18. Keyboard & Mouse Shortcuts

Action	Shortcut
Undo last edit	Ctrl+Z
Redo last edit	Ctrl+Shift+Z
Save current session	Click the Save button in the top bar
Close any popover / modal	Esc
Confirm rename / save-as / delete	Enter
Reorder chord cards	Drag horizontally
Resize chord bars	Drag the right edge of a card
Reset pitch slider	Double-click on the slider
Cycle voicing variants (selected chord)	< / > in the right panel
Export MIDI to disk	Click EXPORT MIDI
Drag MIDI into DAW	Press & drag EXPORT MIDI onto a track

19. Troubleshooting

Windows SmartScreen blocks the installer

The installer is not yet EV-code-signed. Click **More info** → **Run anyway**. The block will disappear automatically once enough users have installed the same file (Microsoft tracks installer reputation per hash).

The activation screen keeps reappearing

Your local key cache (%APPDATA%\AstroHarmony\license.txt) was cleared. Paste your licence key again — the same key works on the same machine forever (up to 3 devices per purchase).

Plugin doesn't appear in my DAW after install

- Confirm the file exists at C:\Program Files\Common Files\VST3\AstroHarmony.vst3.
- In your DAW's plugin preferences, force a full re-scan (FL: **Options** → **Manage plugins** → **Find more plugins**).
- Some DAWs cache plugin metadata. If you rebuilt or reinstalled with a different version, delete the stale entry from the DAW's plugin list before rescanning.

FL Studio shows AstroHarmony as an effect, not an instrument

FL Studio decides plugin type from the VST3 metadata. AstroHarmony is declared as **Instrument | Synth | Sampler**, but FL sometimes mis-classifies on the first scan after a new install. Fix: in **Manage plugins**, find AstroHarmony, right-click → **Set as Generator**. FL remembers the choice for future projects.

FL Studio says “Vendor: unknown”

Same root cause — cached metadata from an older build. Delete the AstroHarmony entry from **Manage plugins**, then **Find more plugins** to force a fresh scan. The vendor should read **Astrotone Audio**.

Clicks when changing chords quickly

DAWs with very small audio buffer sizes (under 256 samples) can produce click artefacts on rapid chord changes. The plugin uses a 3 ms fade on same-note retriggers to suppress this, but extreme low-latency settings may still leak through.

- Raise the audio buffer in your DAW's ASIO settings to **256** or **512** samples.
- If you need low latency for live performance, switch to a softer-attack instrument (Strings, Flute).
- Standalone running on Windows' default WASAPI driver has its own buffer; raise it under **Options** → **Audio/MIDI Settings**.

Plugin window is blank / shows a white box

The user interface is rendered by Microsoft Edge WebView2. If the Runtime is missing, the host area appears blank. Re-run the installer — it will detect the missing Runtime and offer to install it. Alternatively, install it manually from Microsoft (search *WebView2 Runtime download*).

“Plug-in scan failed” on a clean Windows install

Usually means the WebView2 Runtime is missing. Install it (see previous tip) and re-scan. If the scan still fails, check that the .vst3 bundle is the full folder including the `Contents\x86_64-win` subfolder and not just the inner binary — some file-copy tools strip the bundle structure.

Chord is missing some notes on the piano view

Earlier builds had trouble with double-accidental spellings (G##, Dbb) and unicode sharps. This release normalises every spelling before the piano renderer sees it, so all chord tones should light up. If you spot a missing note, please send the chord name and the mode to support.

MIDI export sounds wrong in my DAW

Two common causes: **(1)** your DAW track is loaded with an instrument whose range doesn't cover the exported pitches (common with brass libraries that won't play below E2); **(2)** you exported with the playback pitch slider not at zero and you didn't realise — the file is correctly transposed but in a different key from what the timeline labels.

Drag-out from EXPORT MIDI doesn't land on the track

AstroHarmony hands the file to your DAW as an OS-level file drop. If the DAW's arrange view doesn't accept it, drop instead onto the DAW's File Browser pane and drag from there. The .mid file is always also written to `%TEMP%\AstroHarmony\` so you can pick it up manually if all else fails.

20. License Terms (Summary)

AstroHarmony is licensed, not sold. The full End User License Agreement is shown during installation, must be accepted to proceed, and is also installed as `LICENSE.txt` in the application folder.

What you can do

- Install on up to **three (3) devices** you own.
- Use the plugin and/or the Standalone for any lawful purpose, including **commercial** work (film, game, music release, beat sales).
- Keep full ownership of every chord progression, MIDI export and audio bounce you produce. The Licensor claims nothing in your output.

What you may not do

- Resell, redistribute or sublicense the software itself.
- Reverse-engineer or modify the binary.
- Share your licence key with anyone else.
- Extract, repackage or redistribute the bundled audio samples as a sample library.

Refund & right of withdrawal (EU / UK)

EU and UK consumers have a statutory 14-day right of withdrawal under EU Directive 2011/83/EU. **Activating** the Software on any device within that window starts the “immediate performance” clause — per Article 16(m), the right of withdrawal ends at that moment. **Unactivated** copies remain refundable within the 14-day window upon written request to info@astrotoneaudio.com.

Privacy

The Software does not collect or transmit personal data. Everything lives locally: projects in `%APPDATA%\AstroHarmony\sessions\`, licence key in `%APPDATA%\AstroHarmony\license.txt`. No telemetry, no analytics, no “phone home” after activation.

Governing law

The EULA is governed by the laws of the Republic of Lithuania. Disputes are heard by the competent courts of Lithuania, except where mandatory consumer-protection law of your country of residence provides otherwise.

VST is a trademark of Steinberg Media Technologies GmbH, registered in Europe and other countries.

21. Support & Contact

All questions, refund requests, bug reports and licence enquiries go to a single inbox:

info@astrotoneaudio.com

When emailing about a bug, please include:

- Your Windows version (10 or 11, and the build number from winver).
- Your DAW and its version (or “Standalone” if you ran the app directly).
- The plugin build, visible under the gear icon → **About** → **Build**.
- A short description of the steps that triggered the issue.
- If relevant, the project file (drag-export it as MIDI and attach the .mid).

Thank you for using AstroHarmony.

— Astrotone Audio