DNA Sequence Reads Compression

User Guide

Release 2.0

March 31, 2014

Contents

Co	ontent	3	ii
1	Intro	duction	1
	1.1	What is DSRC?	1
	1.2	Main features	1
	1.3	Compression factor and speed	1
	1.4	Contact and support	2
2	Quic		3
	2.1	Download	3
	2.2	Building	3
	2.3	Program usage	4
3	DSR	C integration	6
	3.1	Python API	6
	3.2	Python examples	9
	3.3	C++ API	12
	2 /	Culovamplas	15

Introduction

1.1 WHAT IS DSRC?

DNA Sequence Reads Compression is an application designed for loosless and lossy compression of DNA sequencing reads stored in FASTQ format. The first release (0.x) of DSRC was accompanied by the research paper:

• S. Deorowicz and S. Grabowski: *Compression of DNA sequence reads in FASTQ format*, Bioinformatics (2011).

The newest release is described in:

• Ł. Roguski and S. Deorowicz: DSRC 2—Industry-oriented compression of FASTQ files (under review).

1.2 Main features

The main features of DSRC are:

- Effective multithreaded compression of DNA sequencing data stored in FASTQ format.
- Full support for Illumina, ABI SOLiD, and 454/Ion Torrent dataset formats with non-standard (AGCTN) IUPAC base values.
- Support for lossy quality values compression using Illumina binning scheme.
- Support for lossy IDs compression keeping only key fields selected by user.
- Pipes support for easy integration with current pipelines.
- Python and C++ libraries allowing to integrate DSRC archives in own applications.
- Availability for Linux, Windows, and MacOS 64-bit operating systems.
- Open C++ source code under GNU GPL 2 license.

1.3 Compression factor and speed

In terms of lossless compression factor (the ability to reduce the file size), DSRC in is usually 35–60% better than gzip and 15–30% better than bzip2, which are currently the most common tools for storing FASTQ files in a compressed format. DSRC is a multithreaded software and the speed in the fast mode usually reaches the I/O limits (e.g., about $500\,\mathrm{MB/s}$ for 8 threads). The achieved compression ratio and speeds are described in the mentioned research papers.

1.4 CONTACT AND SUPPORT

- Official Web site: http://sun.aei.polsl.pl/dsrc/
- Contact and bug reports: sebastian.deorowicz [at] polsl.pl , lucas.roguski [at] gmail.com

Quickstart

2.1 DOWNLOAD

The compiled binaries, C++ and Python libraries with example of usage can be downloaded from the official Web site: http://sun.aei.polsl.pl/dsrc/

2.2 Building

DSRC compiles on both Windows and Linux platforms.

2.2.1 Linux

To compile DSRC on Linux platform do use provided makefile files in the main directory. The default Makefile will compile DSRC in a static-linking variant using boost::thread¹ library for multithreading functionality, so boost development libraries are required to be present. The Makefile.g++11 will use g++ (≥ 4.8) with implementation of C++11 standard, which provides multithreading functionality without using Boost libraries. To build DSRC binary in the main directory:

make bin

where the resulting dsrc binary file will be placed in bin directory.

To build DSRC C++ library use:

make lib

where the resulting dsrc binary file will be placed in lib directory.

2.2.2 Windows

To compile on Windows platform there are provided project solution files dsrc-vs2k10.sln and dsrc-vs2k12.sln for respectively Microsoft Visual Studio 2010 and 2012 with configurations for building DSRC binary and C++ library. When building DSRC using Microsoft Visual Studio 2010 boost::thread library will be required to provide multithreading functionality, while by using Microsoft Visual Studio 2012 C++11 threads implementation will be used. DSRC can be also compiled using MinGW-W64 (64-bit) using linux makefile files.

¹Boost libraries can be downloaded from http://www.boost.org/

2.2.3 Mac OSX

To compile DSRC on Mac OSX use the provided Makefile.osx file in the main directory. The makefile uses clang compiler with C++11 standard support for multithreading. To build DSRC binary in the main directory:

```
make -f Makefile.osx bin
```

where the resulting dsrc binary file will be placed in bin directory.

To build DSRC C++ library use:

```
make -f Makefile.osx lib
```

where the resulting dsrc binary file will be placed in lib directory.

2.2.4 Python module

To build the DSRC Python module the boost::python, boost::thread and boost::system libraries in development versions are required. The module will be build using the Boost Build bjam tool using Jamroot file located in py folder.

In order to compile Python module, the location of the local boost path needs to be edited in Jamroot file:

After setting the local boost path to compile the pydsrc module just type in the main directory:

```
make pylib
```

which will launch Boost Build tool and place the library in the output pylib directory tree.

2.3 PROGRAM USAGE

DSRC can be run from the command prompt:

```
dsrc <c|d> [options] <input_file_name> <output_file_name>
```

in one of two modes:

c — compression,

d — decompression.

Available compression options are:

```
-d < n > — DNA compression mode: 0–3, default: 0
```

-q < n > — Quality compression mode: 0–2, default: 0

-f<1,...> — keep only those fields no. in ID field string, default: keep all

-b < n > — FASTQ input buffer size in MB, default: 8

- -m < n > Automated compression mode (one of the three preset combination of other parameters): 0–2
- -o < n > Quality offset, 0 for auto selection, default: 0
- -1 use Quality lossy mode (Illumina binning scheme), default: false
- -c calculate and check CRC32 checksum calculation per block (slows the compression about twice), default: false

Available 'automated' compression modes:

```
-m0 — fast mode, equivalent to: -d0 -q0 -b8
```

-m1 — medium mode, equivalent to: -d2 -q2 -b64

-m2 — best mode, equivalent to: -d3 -q2 -b256

Options for both compression and decompression modes:

- -t < n > processing threads number, default: max available hardware threads
- -s use stdin/stdout for reading/writing FASTQ data (stderr is used for info/warning messages)

Usage examples:

- Compress SRR001471.fastq file saving DSRC archive to SRR001471.dsrc: dsrc c SRR001471.fastq SRR001471.dsrc
- Compress file in the *fast* mode with CRC32 checking and using 4 threads: dsrc c -m0 -c -t4 SRR001471.fastq SRR001471.dsrc
- Compress file using DNA and Quality compression level 2 and using 512 MB buffer: dsrc c -d2 -q2 -b512 SRR001471.fastq SRR001471.dsrc
- Compress file in the best mode with lossy Quality mode and preserving only 1–4 fields from record IDs:

```
dsrc c -m2 -l -f1,2,3,4 SRR001471.fastq SRR001471.dsrc
```

- Compress in the *best* mode reading FASTQ file read from stdin: cat SRR001471.fastq | dsrc c -m2 -s SRR001471.dsrc
- Decompress SRR001471.dsrc archive saving output FASTQ file to SRR001471.out.fastq: dsrc d SRR001471.dsrc SRR001471.out.fastq
- Decompress archive using 4 threads and streaming FASTQ data to stdout: dsrc d -t4 -s SRR001471.dsrc » SRR001471.out.fastq

DSRC integration

DSRC can be easily integrated with applications written in C++ or Python. We provide C++ and Python libraries with very similar interfaces. Although the methods and members names are almost identical in both cases, for clarity the C++ and Python descriptions are divided into two separate sections.

3.1 PYTHON API

To start using the compressor functionality in Python it's only needed to import pydsrc module (pydsrc.so file) in the project. In order to provide high performance of compression routines the core operations were written in C++ and exported to Python.

3.1.1 FastqRecord

FastqRecord represents a single DNA sequencing read. The ID, sequence, plus, and quality fields are accessible as Python string type.

3.1.2 FastqFile

FastqFile is used for reading and writing FASTQ files in a sequential manner, read by read, where each is of type FastqRecord. Figure 3.1 shows FastqFile available public methods—all methods throw exception on error or failure.

Method Returns **Parameters** Description Open Opens specified file. string filename Creates a new file or overwrites one if Create string filename exists. Close Closes the file. Gets the next record. Returns True on FastqRecord successful read and False on reaching ReadNextRecord boolean record the end of file. FastqRecord Writes the next record. WriteRecord record

Table 3.1: FastqFile public methods

3.1.3 DsrcArchive

DsrcArchive represents DSRC archive file and provides compression and decompression routines. Figure 3.2 shows DsrcArchive available public methods—all methods throw exception on error or failure. Figure 3.3 shows public properties. It's important to note, that properties cannot be set, when DsrcArchive is already in processing mode (compression or decompression routines have been stared).

Table 3.2: DsrcArchive methods

Method	Returns	Parameters	Description
StartCompress		string filename	Creates a new DSRC archive and pre-
Star toompress	_	501111g mename	pares for compression.
WriteNextRecord	_	FastqRecord rec	Writes a new record to file.
FinishCompress			Finalizes the compression of the
			archive and performs cleanup.
StartDecompress	_	string filename	Opens a DSRC archive and prepares
2 car oz c c ampross			for decompression.
			Reads the next decompressed FASTQ
ReadNextRecord	boolean	FastqRecord	record from archive. Returns True on
itedulies ditector a		record	success and False on reaching end of
			archive.
FinishDecompress	_		Finalizes the decompression of the
rinishbecompless			archive and performs cleanup.

Table 3.3: DsrcArchive properties

Property	Type	Description
DnaCompressionLevel	int	DNA compression level: 0–3. Default: 0.
QualityCompressionLevel	int	Quality compression level: 0–2. Default: 0.
FastqBufferSize	int	Size of input FASTQ buffer specified in MB. Default: 8.
LossyCompression	boolean	Lossy quality compression mode indicator. Default: False.
TagFieldFilterMask	int	Mask defining ID fields to keep. Default: 0 (keep all).
QualityOffset	int	Value of Quality offset—typically 33 or 64. Default: auto determined.
Crc32Checking	boolean	CRC32 checksum check during compression indicator. Default: False.
ColorSpace	boo lean	Color space archive type (e.g., ABI SOLiD) indicator. Default: False.
PlusRepetition	boolean	Flag indicating keeping additional information in plus lines. Default: False.

3.1.4 DsrcModule

DsrcModule provides automated and parallel compression routines, working on whole files instead of single records. Figures 3.4 and 3.5 show available public methods and public properties. All methods throw exception on error or failure.

Table 3.4: DsrcModule methods

Method	Returns	Parameters	Description
		string	
Compress	_	fastqFilename,	Compresses the FASTQ file to DSRC
Compress		string	archive.
		dsrcFilename	
	ss —	string	
Docommoga		dsrcFilename,	Decompresses the DSRC archive to file
Decompress		string	in FASTQ format.
		fastqFilename	

Table 3.5: DsrcModule properties

Property	Type	Description
DnaCompressionLevel	int	DNA compression level: 0–3. Default: 0.
QualityCompressionLevel	int	Quality compression level: 0–2. Default: 0.
FastqBufferSize	int	Size of input FASTQ buffer in MB. Default: 8.
LossyCompression	boolean	Lossy Quality compression mode indicator. Default: False.
TagFieldFilterMask	int	Mask defining ID fields to keep. Default: 0 (keep all).
QualityOffset	int	Value of Quality offset, typically 33 or 64. Default: auto determined.
Crc32Checking	boolean	Flag indicating if CRC32 checking is enabled during compression. Default: False.

3.2 PYTHON EXAMPLES

3.2.1 Compressing FASTQ file using automated DsrcModule module

```
import pydsrc

filename_fq = "SRR001471.fastq"
filename_dsrc = "SRR001471.dsrc"

# create and configure DSRC module
module = pydsrc.DsrcModule()
module.LossyCompression = True
module.DnaCompressionLevel = 2
module.QualityCompressionLevel = 2
module.FastqBufferSizeMB = 512
module.ThreadsNumber = 2
module.Compress(filename_fq, filename_dsrc)
```

3.2.2 Decompressing DSRC archive using automated DsrcModule module

```
import pydsrc

filename_dsrc = "SRR001471.dsrc"
filename_fq = "SRR001471.dsrc.fastq"

# create and configure DSRC module
module = pydsrc.DsrcModule()
module.ThreadsNumber = 2

module.Decompress(filename_dsrc, filename_fq)
```

3.2.3 Manual compression using DsrcArchive and FastqFile

```
import pydsrc
   filename_fq = "SRR001471.fastq"
  filename_dsrc = "SRR001471.dsrc"
   fqfile = pydsrc.FastqFile()
   fqfile.Open(filename_fq)
   # create and configure DSRC archive file
   archive = pydsrc.DsrcArchive()
   archive.DnaCompressionLevel = 2
   # lossy compress quality values using use Illumina bining scheme
   archive.LossyCompression = True
   archive.QualityCompressionLevel = 2
16
   archive.FastqBufferSizeMB = 512
   # do not keep extra information in 'plus' field
20 | archive.PlusRepetition = False
   archive.StartCompress(filename_dsrc)
24
   # read all records from FASTQ file and write to DSRC archive
   rc = 0
   rec = pydsrc.FastqRecord()
while fqfile.ReadNextRecord(rec):
       archive.WriteNextRecord(rec)
       rc += 1
   # save archive and close FASTQ file
   archive.FinishCompress()
   fqfile.Close()
36 | print "Success!\nRecords⊔written:⊔%d" % rc
```

3.2.4 Manual decompression using DsrcArchive and FastqFile

```
import pydsrc
filename_dsrc = "SRR001471.dsrc"
filename_fq = "SRR001471.dsrc.fastq"

# open existing DSRC archive file
archive = pydsrc.DsrcArchive()
archive.StartDecompress(filename_dsrc)

# create results FASTQ file
fqfile = pydsrc.FastqFile()
fqfile.Open(filename_fq)

# read all records from DSRC archive and write to FASTQ file
rc = 0
rec = pydsrc.FastqRecord()
while archive.ReadNextRecord(rec):
    fqfile.WriteNextRecord(rec)
    rc += 1

# close (and save) FASTQ file and close DSRC archive
fqfile.Close()
archive.FinishDecompress()
print "Success!\nRecords_uwritten:u%d" % rc
```

3.3 C++ API

To start using DSRC C++ library it's only needed to include Dsrc.h header file and to link application with libdsrc(libdsrc.a file under Linux or libdsrc.lib file under Windows) library.

3.3.1 FastqRecord

FastqRecord stores a single DNA sequencing read information. The IDs, sequence, plus, and quality fields are represented using std::string type.

3.3.2 FastqFile

FastqFile is used to read and write FASTQ records, where each record is of FastqRecord type. Figure 3.6 shows FasqtFile public methods—methods throw std::runtime_error exception on error.

Method Returns **Parameters** Description std::string Opens specified file for reading. Open filename std::string Creates a new file or overwrites if one Create filename exists for writing. Close Closes the file. FastqRecord& Gets the next buffered record. Returns ReadNextRecord bool false when reaching end of file. record FastqRecord WriteNextRecord Writes the next record. record

Table 3.6: FastqFile public methods

3.3.3 DsrcArchive

DsrcArchve provides methods to read from and write to DSRC archive file in a continuous way, read by read, where record is of FastqRecord type. Figure 3.7 shows DsrcArchive public methods, while Figure 3.8 shows public accessors.

3.3.4 DsrcModule

DsrcModule provides automated parallel compression and decompression routines operating on whole files instead of single records. Figure 3.9 shows available public methods, Figure 3.10 shows public accessors.

Table 3.7: DsrcArchive public methods

Method	Returns	Parameters	Description
StartCompress	tartCompress —		Creates a new DSRC archive and prepares for compression.
WriteNextRecord	_	FastqRecord record	Writes a new record to file.
FinishCompress	_	_	Finalizes the compression of the archive and performs cleanup.
StartDecompress	_	std::string	Opens a DSRC archive and prepares for decompression.
ReadNextRecord bool		FastqRecord& record	Reads the next decompressed FASTQ record from archive. Returns false on reaching end-of-file.
FinishDecompress —		_	Finalizes the decompression of the archive and performs cleanup.

 ${\it Table 3.8: DsrcArchive\ public\ accessors}$

Methods	Value type	Description
Get/Set	int	Gets/Sets the level of DNA compression: 0–3. De-
DnaCompressionLevel	1116	fault: 0
Get/Set	int	Gets/Sets the level of quality compression: 0–3.
QualityCompressionLevel	1116	Default: 0.
Get/Set	int	Gets/Sets the size of input FASTQ buffer in MB.
FastqBufferSize	IIIC	Default: 8.
Is/Set	1 7	Gets/Sets the state of lossy quality mode enabled.
LossyCompression	bool	Default: false.
Get/Set	unsigned	Gets/Sets the mask describing ID fields to keep in
TagFieldFilterMask	long	FASTQ record. Default: 0 (keep all fields).
Get/Set QualityOffset	int	Gets/sets the quality values offset—typically 33 or 64. Default: automatic selection.
	bool	Gets/sets CRC32 hash calculations. Default:
Is/Set Crc32Checking		false.
Is/Set PlusRepetition	bool	Gets/sets repetition of ID fields on 'plus' field in
15/ Dec Finshehecicion		FASTQ record.
Is/Set ColorSpace	bool	Gets/sets indicator whether file is encoded in color
is/ bet colorspace	5001	space (e.g., ABI SOLiD type).

Table 3.9: DsrcModule public methods

Method	Returns	Parameters	Description
Compress	bool	std::string fastqFilename,	Compresses the FASTQ file to DSRC
COMPIOSS		std::string dsrcFilename	archive.
Decompress	bool	std::string dsrcFilename, std::string fastqFilename	Decompresses the DSRC archive to file.

Table 3.10: ${\tt DsrcModule}$ public accessors

Methods	Value type	Description
Get/Set	int	Gets/Sets the level of DNA compression: 0–3. De-
DnaCompressionLevel	1116	fault: 0
Get/Set	in+	Gets/Sets the level of quality compression: 0-2.
QualityCompressionLevel	int	Default: 0.
Get/Set	÷ +-	Gets/Sets the size of input FASTQ buffer in MB.
FastqBufferSize	int	Default: 8.
Is/Set	bool	Gets/Sets the state of lossy quality mode enabled.
LossyCompression	DOOT	Default: false.
Get/Set	unsigned	Gets/Sets the mask describing ID fields to keep in
TagFieldFilterMask	long	FASTQ record. Default: 0 (keep all fields).
Get/Set QualityOffset	int	Gets/sets the quality values offset—typically 33 or
des, see quarrey dirset	1110	64. Default: automatic selection.
Is/Set Crc32Checking	bool	Gets/sets CRC32 hash calculations. Default:
15/Det CICSZCHecking		false.

3.4 C++ EXAMPLES

3.4.1 Compressing FASTQ file using automated DsrcModule module

```
#include <string>
   #include <iostream>
   #include "Dsrc.h"
   using namespace dsrc::lib;
   int main(int argc_, char* argv_[])
       if (argc_ != 3)
           return -1;
       const std::string inFastqFile = argv_[0];
12
       const std::string outDsrcFile = argv_[1];
       try
16
           DsrcModule dsrc;
           // compress archive in MED mode (flags: -d2 -q2 -b64)
           dsrc.SetQualityCompressionLevel(2);
           dsrc.SetDnaCompressionLevel(2);
           dsrc.SetFastqBufferSizeMB(64);
           // additionally perform CRC32 checking when compressing
24
           dsrc.SetCrc32Checking(true);
           // set maximum compressing worker threads number
           dsrc.SetThreadsNumber(4);
28
           dsrc.Compress(inFastqFile, outDsrcFile);
       }
       catch (const DsrcException& e)
32
           std::cerr << "Error!" << std::endl;</pre>
           std::cerr << e.what() << std::endl;</pre>
           return -1;
       std::cout << "Success!" << std::endl;</pre>
       return 0;
40
   }
```

3.4.2 Decompressing DSRC archive using automated DsrcModule module

```
#include <string>
#include <iostream>
   #include "Dsrc.h"
   using namespace dsrc::lib;
   int main(int argc_, char* argv_[])
8
       if (argc_ != 3)
           return -1;
       const std::string inDsrcFile = argv_[0];
       const std::string outFastqFile = argv_[1];
       try
16
           DsrcModule dsrc;
            // set maximum decompressing worker threads number
           dsrc.SetThreadsNumber(4);
20
           dsrc.Decompress(inDsrcFile, outFastqFile);
       }
       catch (const DsrcException& e)
24
            std::cerr << "Error!" << std::endl;</pre>
           std::cerr << e.what() << std::endl;</pre>
           return -1;
       std::cerr << "Success!" << std::endl;</pre>
       return 0;
32
   }
```

3.4.3 Manual compression using DsrcArchive and FastqFile

```
#include <string>
   #include <iostream>
   #include "Dsrc.h"
   using namespace dsrc::lib;
   int main(int argc_, char* argv_[])
       if (argc_ != 3)
           return -1;
       const std::string inFastqFile = argv_[0];
12
       const std::string outDsrcFile = argv_[1];
       // 1. Open FASTQ file
       FastqFile fastqFile;
       try
       {
           fastqFile.Open(inFastqFile);
20
       catch (const DsrcException& e)
           std::cerr << "Error!\n" << e.what() << std::endl;
           return -1;
       }
       // 2. Create and configure DSRC archive
       DsrcArchive archive;
28
       try
           // compress quality values using Illumina bining scheme
32
           archive.SetLossyCompression(true);
           archive.SetQualityCompressionLevel(2);
           archive.SetDnaCompressionLevel(2);
           archive.SetFastqBufferSizeMB(512);
36
           // discard repeated TAG information in "+" lines
           archive.SetPlusRepetition(false);
40
           archive.StartCompress(outDsrcFile);
       }
       catch (const DsrcException& e)
44
           fastqFile.Close();
           std::cerr << "Error!\n" << e.what() << std::endl;
48
           return -1;
       // 3. When configured, start compression
       FastqRecord rec;
52
       long int recCount = 0;
       while (fastqFile.ReadNextRecord(rec))
       {
           archive.WriteNextRecord(rec);
56
           recCount++;
```

```
// 4. Finish compression and close FASTQ file
archive.FinishCompress();
fastqFile.Close();

std::cout << "Sucess!\nCompressed_records:" << recCount << std::endl;
return 0;
}
</pre>
```

3.4.4 Manual decompression using DsrcArchive and FastqFile

```
#include <string>
   #include <iostream>
   #include "Dsrc.h"
   using namespace dsrc::lib;
   int main(int argc_, char* argv_[])
       if (argc_ != 3)
           return -1;
12
       const std::string inDsrcFile = argv_[0];
       const std::string outFastqFile = argv_[1];
       // 1. Open DSRC archive
       DsrcArchive archive;
16
       try
       {
           archive.StartDecompress(inDsrcFile);
       }
20
       catch (const DsrcException& e)
           std::cerr << "Error!\n" << e.what() << std::endl;
           return -1;
24
       }
       // 2. Create output FASTQ file
       FastqFile fastqFile;
       try
       {
           fastqFile.Create(outFastqFile);
       }
32
       catch (const DsrcException& e)
       {
           archive.FinishDecompress();
36
           std::cerr << "Error!\n" << e.what() << std::endl;
           return -1;
       }
40
       // 3. Start decompression
       FastqRecord rec;
       long int recCount = 0;
       while (archive.ReadNextRecord(rec))
           fastqFile.WriteNextRecord(rec);
           recCount++;
       }
48
       // 4. Finish decompression and close FASTQ file
       archive.FinishDecompress();
       fastqFile.Close();
       std::cout << "Success!\nDecompressed_records:" << recCount << std::endl;
       return 0;
  }
```