

102 - Create whole document with several related tables

Start with Report 88002 or create a new report from a Header Line template.

Complete the dataset

Add VAT Lines:

- 1. Right click the Header;
- 2. Select Insert Section > DataItem;
- 3. In the properties menu add the Data Item Table. Select table 290, VAT Amount Line;
- 4. In the properties menu add sorting to the Data Item Table View. Sort on the VAT Identifier, VAT Calculation Type, Tax Group Code, Use Tax, and Positive fields;
- 5. In the properties menu Total Fields add the fields VAT %, VAT Base, VAT Amount, and Line Amount:
- 6. In the properties Menu set the Data Item Variable Name to VATAmountLine;
- 7. In the properties menu set Temporary to True;
- 8. Right click the Header;
- 9. Select Insert Section > DataItem;
- 10. In the properties menu add the Data Item Table. Select table 560, VAT Clause;
- 11. In the properties menu add sorting to the Data Item Table View. Sort on the Code field;
- 12. In the properties Menu set the Data Item Variable Name to VATClause;
- 13. In the properties menu set Temporary to True.

Add the code to populate temporary tables.

- 14. Open the report in the Object Designer;
- 15. Add the functions GetVatAmountLines and GetVATClauses from the file IO2 C-AL code to add.txt and the calls to them in the Header OnAfterGetRecord section. This will populate the VAT Amount Line temp table;
- 16. Run the report preview and note the changes.

Add VAT amount lines

- 17. Right click the VATAmountLine DataItem and select Insert Section > Header;
- 18. In the properties menu set Section Name to VATHeader;
- 19. Right click the VATAmountLine DataItem;
- 20. Select Insert Section > Body;
- 21. In the properties menu set Section Name to VATBody;
- 22. Right click the VATAmountLine DataItem;
- 23. Select Insert Section > Footer;
- 24. In the properties menu set Section Name to VATFooter;
- 25. In the VATHeader add a table with the field captions VATIdentifier, VATPct, LineAmount, VATAmount, and VATBase;
- 26. In the VATBody add a table with the fields VATIdentifier, VATPct, LineAmount, VATAmount, and VATBase;
- 27. In the VATFooter add a table with the fields LineAmount, VATAmount, and VATBase;
- 28. Run the report preview and note the changes.





Add a Header and a Footer to the line Data Item.

- 29. Right click the Line DataItem and select Insert Section > Header;
- 30. In the properties menu set Section Name to LineHeader;
- 31. Select the Body1 section;
- 32. In the properties menu set Section Name to LineBody;
- 33. Right click the Line DataItem;
- 34. Select Insert Section > Footer;
- 35. In the properties menu set Section Name to LineFooter;
- 36. Delete the fields in the LineBody section;
- 37. Add a table with the fields No, Description, Quantity, Unit of Measure, and LineAmount to the LineBody section;
- 38. Add a table with the fieldcaptions No, Description, Quantity, Unit of Measure, and LineAmount to the LineHeader section;
- 39. In the LineFooter add the fields CurrReport.StandardCaptions.SubTotal and Header.Amount.

Add the Company Information

- 40. Right click the Header DataItem;
- 41. Select Insert Section > Footer;
- 42. In the properties of the footer rename the Section Name to Footer;
- 43. In the properties of the footer set Print On Every Page and Place In Bottom to Yes;
- 44. Add a textbox the full width of the footer;
- 45. In the Source Expression of this Text Box add:

CompanyInformation.FieldCaptions.PhoneNo + ' : ' + CompanyInformation.PhoneNo;

46. Run the report preview and note the changes.