请参考代码注释,补全mips_detect_memory 函数。在实验中,从外设中获取了硬件可用内存大小memsize,请你用内存大小memsize 完成总物理页数npage 的初始化

```
1
    void mips_detect_memory() {
 2
        /* Step 1: Initialize memsize. */
        memsize = *(volatile u_int *)(KSEG1 | DEV_MP_ADDRESS | DEV_MP_MEMORY);
 3
 4
 5
        /* Step 2: Calculate the corresponding 'npage' value. */
        /* Exercise 2.1: Your code here. */
 6
 7
        npage = memsize >> 12;
                                                    // 一个页面大小是4KB
 8
                      1
 9
10
        printk("Memory size: %lu KiB, number of pages: %lu\n", memsize / 1024,
    npage);
   }
11
12
```

2.2

完成include/queue.h 中空缺的函数LIST_INSERT_AFTER。[将elm 插到已有元素listelm 之后。] 其功能是将一个元素插入到已有元素之后,可以仿照LIST_INSERT_BEFORE 函数来实现。

```
1 /*
 2
    * Insert the element 'elm' *after* 'listelm' which is already in the list. The
    'field'
 3
    * name is the link element as above.
 4
 5
     * Hint:
     * Step 1: assign 'elm.next' from 'listelm.next'.
 6
 7
     * Step 2: if 'listelm.next' is not NULL, then assign 'listelm.next.pre' from a
    proper value.
 8
     * Step 3: assign 'listelm.next' from a proper value.
     * Step 4: assign 'elm.pre' from a proper value.
 9
10
11
    #define LIST_INSERT_AFTER(listelm, elm, field)
        /* Exercise 2.2: Your code here. */
12
13
        do {
14
            LIST_NEXT((elm), field) = LIST_NEXT((listelm), field);
15
            if(LIST_NEXT((listelm), field) != NULL) {
16
                LIST_NEXT((listelm), field)->field.le_prev = &LIST_NEXT((elm),
    field);
               \
```

完成page_init 函数。请按照函数中的注释提示,完成上述三个功能。此外,这里也给出一些提示:

- 1. 使用链表初始化宏LIST_INIT。
- 2. 将freemem 按照BY2PG 进行对齐(使用ROUND 宏为freemem 赋值)。
- 3. 将freemem 以下页面对应的页控制块中的pp_ref 标为1。
- 4. 将其它页面对应的页控制块中的pp_ref 标为0 并使用LIST_INSERT_HEAD 将其插入空闲链表。

```
void page_init(void) {
 1
 2
        /* Step 1: Initialize page_free_list. */
 3
        /* Hint: Use macro `LIST_INIT` defined in include/queue.h. */
        /* Exercise 2.3: Your code here. (1/4) */
 4
 5
        LIST_INIT(&page_free_list);
 6
 7
        /* Step 2: Align `freemem` up to multiple of BY2PG. */
        /* Exercise 2.3: Your code here. (2/4) */
 8
 9
        freemem = ROUND(freemem, BY2PG);
10
11
        /* Step 3: Mark all memory below `freemem` as used (set `pp_ref` to 1) */
        /* Exercise 2.3: Your code here. (3/4) */
12
13
        int used_page = PADDR(freemem) / BY2PG; //[PADDR]:physical address
    [BY2PG]:bytes to per page
14
        int i;
15
        for(i=0; i<used_page; i++) {</pre>
            pages[i].pp_ref = 1;
16
17
        }
18
19
        /* Step 4: Mark the other memory as free. */
20
        /* Exercise 2.3: Your code here. (4/4) */
21
        int j;
22
        for(j=used_page; j<npage; j++) {</pre>
23
            pages[j].pp_ref = 0;
24
            LIST_INSERT_HEAD(&page_free_list, &pages[j], pp_link);
25
        }
26
27
    }
```

page_alloc(struct Page **pp),它的作用是将page_free_list 空闲链表头部页控制块对应的物理页面分配出去,将其从空闲链表中移除,并清空对应的物理页面,最后将pp指向的空间赋值为这个页控制块的地址。

完成page_alloc 函数。在page_init 函数运行完毕后,在MOS 中如果想申请存储空间,都是通过这个函数来申请分配。该函数的逻辑简单来说,可以表述为:

- 1. 如果空闲链表没有可用页了, 返回异常返回值。
- 2. 如果空闲链表有可用的页,取出第一页;初始化后,将该页对应的页控制块的地址放到调用者指定的地方。填空时,你可能需要使用链表宏LIST_EMPTY或函数page2kva

```
1 /* Overview:
    * Allocate a physical page from free memory, and fill this page with zero.
 2
 3
 4
    * Post-Condition:
 5
    * If failed to allocate a new page (out of memory, there's no free page),
    return -E_NO_MEM.
    * Otherwise, set the address of the allocated 'Page' to *pp, and return 0.
 6
 7
 8
    * Note:
    * This does NOT increase the reference count 'pp_ref' of the page - the
 9
    caller must do these if
10
    * necessary (either explicitly or via page_insert).
11
12
     * Hint: Use LIST_FIRST and LIST_REMOVE defined in include/queue.h.
13
     */
    int page_alloc(struct Page **new) {
14
       /* Step 1: Get a page from free memory. If fails, return the error code.*/
15
16
        struct Page *pp;
       /* Exercise 2.4: Your code here. (1/2) */
17
        pp = LIST_FIRST(&page_free_list);
18
19
       if(pp == NULL) {
20
           return -E_NO_MEM;
21
        }
22
23
       LIST_REMOVE(pp, pp_link);
24
25
        /* Step 2: Initialize this page with zero.
        * Hint: use `memset`. */
26
27
        /* Exercise 2.4: Your code here. (2/2) */
        u_long temp = page2kva(pp); //清空对应的物理页面。 [page2kva]:page to kernel
28
    virtual address
        memset((void*)temp, 0, BY2PG); //都是使用虚拟地址
29
30
31
        *new = pp;
32
        return 0;
33 }
```

page_free(struct_Page *pp),它的作用是判断pp指向页控制块对应的物理页面引用次数是否为0,若为0则该物理页面为空闲页面,将其对应的页控制块重新插入到page_free_list。

完成page_free 函数。提示:使用链表宏LIST_INSERT_HEAD,将页结构体插入空闲页结构体链表。

```
1
    /* Overview:
    * Release a page 'pp', mark it as free.
 2
 3
     * Pre-Condition:
 4
    * 'pp->pp_ref' is '0'.
 5
    */
 6
 7
   void page_free(struct Page *pp) {
 8
        assert(pp->pp_ref == 0);
 9
        /* Just insert it into 'page_free_list'. */
        /* Exercise 2.5: Your code here. */
10
        LIST_INSERT_HEAD(&page_free_list, pp, pp_link);
11
12
        return;
13 }
```

2.6

int pgdir_walk(Pde *pgdir, u_long va, int create, Pte **ppte),该函数将一级页表基地址 pgdir 对应的两级页表结构中va 虚拟地址所在的二级页表项的指针存储在ppte 指向的空间上。如果create 不为0 且对应的二级页表不存在,则会使用page_alloc 函数分配一页物理内存用于存放二级页表,如果分配 失败则返回错误码。

完成pgdir_walk 函数。

该函数的作用是:给定一个虚拟地址,在给定的页目录中查找这个虚拟地址对应的物理地址,如果存在这一虚拟地址对应的页表项,则返回这一页表项的地址;如果不存在这一虚拟地址对应的页表项(不存在这一虚拟地址对应的二级页表、即这一虚拟地址对应的页目录项为空或无效),则根据传入的参数进行创建二级页表,或返回空指针。

注意,这里可能会在页目录表项无效且create 为真时,使用page_alloc 创建一个页表,此时应维护申请得到的物理页的pp_ref 字段。

```
1 /* Overview:
    * Given 'pgdir', a pointer to a page directory, 'pgdir_walk' returns a
    pointer to the page table
         entry (with permission PTE_D|PTE_V) for virtual address 'va'.
 3
 4
 5
     * Pre-Condition:
       'pgdir' is a two-level page table structure.
 6
 7
 8
     * Post-Condition:
9
     * If we're out of memory, return -E_NO_MEM.
10
     * Otherwise, we get the page table entry, store
11
        the value of page table entry to *ppte, and return 0, indicating success.
12
     * Hint:
13
```

```
* We use a two-level pointer to store page table entry and return a state
    code to indicate
15
    * whether this function succeeds or not.
     */
16
    static int pgdir_walk(Pde *pgdir, u_long va, int create, Pte **ppte) {
17
18
        Pde *pgdir_entryp;
19
        struct Page *pp;
20
21
        /* Step 1: Get the corresponding page directory entry. */
        /* Exercise 2.6: Your code here. (1/3) */
22
23
        pgdir_entryp = (pgdir + PDX(va)); //PDX(va) 可以获取虚拟地址va 的31-22位
24
25
        /* Step 2: If the corresponding page table is not existent (valid) and
    parameter `create`
26
         * is set, create one. Set the permission bits 'PTE_D | PTE_V' for this new
    page in the
27
         * page directory.
         * If failed to allocate a new page (out of memory), return the error. */
28
29
        /* Exercise 2.6: Your code here. (2/3) */
        if(!((*pgdir_entryp) & PTE_V)) { //不存在这一虚拟地址对应的二级页表
30
31
            if(create) {
32
                if(page\_alloc(\&pp) == -E\_NO\_MEM)  {
33
                    *ppte = NULL;
34
                    return -E_NO_MEM;
35
                }
36
                pp->pp_ref++;
37
                *pgdir_entryp = page2pa(pp) | PTE_D | PTE_V;
38
            } else {
39
                *ppte = NULL;
40
                return 0;
41
            }
42
        }
43
44
        /* Step 3: Assign the kernel virtual address of the page table entry to
    '*ppte'. */
        /* Exercise 2.6: Your code here. (3/3) */
45
46
        Pte *pgtable;
        pgtable = KADDR(PTE_ADDR(*pgdir_entryp)); //[PTE_ADDR]:page table entry
47
    address
        *ppte = pgtable + PTX(va);
48
49
50
        return 0;
51 }
```

int page_insert(Pde *pgdir, u_int asid, struct Page *pp, u_long va, u_int perm), 作用是将一级页表基地址pgdir 对应的两级页表结构中虚拟地址va 映射到页控制块pp 对应的物理页面,并将页表项权限为设置为perm。

完成page_insert 函数 (补全TODO 部分)。

```
1
    int page_insert(Pde *pgdir, u_int asid, struct Page *pp, u_long va, u_int perm)
    {
 2
        Pte *pte;
 3
 4
        /* Step 1: Get corresponding page table entry. */
 5
        pgdir_walk(pgdir, va, 0, &pte);
 6
 7
        if (pte && (*pte & PTE_V)) {
 8
            if (pa2page(*pte) != pp) {
                page_remove(pgdir, asid, va);
 9
            } else {
10
11
                tlb_invalidate(asid, va);
                *pte = page2pa(pp) | perm | PTE_V;
12
13
                return 0;
14
            }
15
        }
16
17
        /* Step 2: Flush TLB with 'tlb_invalidate'. */
        /* Exercise 2.7: Your code here. (1/3) */
18
19
        tlb_invalidate(asid, va); //清空对应在TLB中的缓存
20
        /* Step 3: Re-get or create the page table entry. */
21
        /* If failed to create, return the error. */
22
23
        /* Exercise 2.7: Your code here. (2/3) */
24
        pgdir_walk(pgdir, va, 1, &pte); //获取/创建
25
        if(pte == 0) {
26
            return -E_NO_MEM;
27
        }
28
29
        /* Step 4: Insert the page to the page table entry with 'perm | PTE_V' and
    increase its
30
         * 'pp_ref'. */
        /* Exercise 2.7: Your code here. (3/3) */
31
        *pte = page2pa(pp) | perm | PTE_V;
32
33
        pp->pp_ref += 1;
34
35
        return 0;
36
   }
37
```

完成kern/tlb_asm.S 中的tlb_out 函数。该函数根据传入的参数(TLB 的Key)找到对应的TLB 表项,并将其清空。

具体来说,需要在两个位置插入两条指令,其中一个位置为tlbp,另一个位置为tlbwi。因流水线设计架构原因,tlbp 指令的前后都应各插入一个nop 以解决数据冒险。

我们通过tlb_invalidate 实现删除特定虚拟地址在TLB 中的旧表项,函数的主要逻辑位于 kern/tlb_asm.S 中的tlb_out 中。当tlb_out 被tlb_invalidate 调用时, a0 寄存器中存放着传入的参数, 寄存器值为旧表项的Key(由虚拟页号和ASID 组成)。我们使用mtc0 将Key写入EntryHi,随后使用tlbp 指令,根据EntryHi 中的Key 查找对应的旧表项,将表项的索引存入Index。如果索引值大于等于0(即 TLB 中存在Key 对应的表项),我们向EntryHi 和EntryLo 中写入0,随后使用tlbwi 指令,将EntryHi 和 EntryLo 中的值写入索引指定的表项。此时旧表项的Key 和Data 被清零,实现将其无效化。

```
1
   #include <asm/asm.h>
 2
 3
   LEAF(tlb_out)
 4
   .set noreorder
 5
       mfc0 t0, CP0_ENTRYHI
 6
               a0, CP0_ENTRYHI
       mtc0
 7
       nop
       /* Step 1: Use 'tlbp' to probe TLB entry */
 8
 9
       /* Exercise 2.8: Your code here. (1/2) */
10
                /*使用tlbp 指令,根据EntryHi 中的Key 查找对应的旧表项,将表项的索引存入
    Index
11
12
13
        /* Step 2: Fetch the probe result from CPO.Index */
14
       mfc0
             t1, CP0_INDEX
15
    .set reorder
16
       bltz t1, NO_SUCH_ENTRY
    .set noreorder
17
18
       mtc0 zero, CP0_ENTRYHI
19
       mtc0 zero, CP0_ENTRYLO0
20
        nop
       /* Step 3: Use 'tlbwi' to write CPO.EntryHi/Lo into TLB at CPO.Index */
21
        /* Exercise 2.8: Your code here. (2/2) */
22
23
                /*使用tlbwi 指令,将EntryHi 和EntryLo 中的值写入索引指定的表项。此时旧表项
       tlbwi
    的Key 和Data 被清零
24
25
    .set reorder
26
27
   NO_SUCH_ENTRY:
28
       mtc0 t0, CP0_ENTRYHI
29
       j
               ra
30 END(tlb_out)
```

2.9

完成kern/tlbex.c 中的 do tlb refill 函数。

提示: 尝试在循环中调用'page_lookup'以查找虚拟地址va。 在当前进程页表中对应的页表项'pte'如果'page_lookup'返回'NULL',表明'pte'找不到,使用'passive_alloc'为va 所在的虚拟页面分配物理页面,直至'page_lookup'返回不为'NULL'则退出循环。你可以在调用函数时,使用全局变量cur_pgdir 作为其中一个实参。

```
2
    * Refill TLB.
 3
     */
 4
    Pte _do_tlb_refill(u_long va, u_int asid) {
 5
        Pte *pte;
 6
        /* Hints:
 7
        * Invoke 'page_lookup' repeatedly in a loop to find the page table entry
    'pte' associated
         * with the virtual address 'va' in the current address space 'cur_pgdir'.
 8
 9
         * **While** 'page_lookup' returns 'NULL', indicating that the 'pte' could
10
    not be found,
         * allocate a new page using 'passive_alloc' until 'page_lookup' succeeds.
11
12
         */
13
14
        /* Exercise 2.9: Your code here. */
        while(page_lookup(cur_pgdir, va, &pte) == NULL) {
15
16
            passive_alloc(va, cur_pgdir, asid);
17
            //cur_pgdir是一个在kern/pmap.c 定义的全局变量,其中存储了当前进程一级页表基地址位
    于kseg0 的虚拟地址。
18
19
        }
20
21
        return *pte;
22
    }
23
```

完成kern/tlb_asm.S 中的do_tlb_refill 函数。

```
1
   .data
 2
   tlb_refill_ra:
 3
   .word 0
 4
   .text
 5
    NESTED(do_tlb_refill, 0, zero)
 6
        mfc0
              a0, CP0_BADVADDR
 7
        mfc0
               a1, CPO_ENTRYHI
               a1, a1, 6
 8
        srl
 9
        andi a1, a1, 0b111111
10
        SW
              ra, tlb_refill_ra
               _do_tlb_refill
11
        jal
12
        1w
               ra, tlb_refill_ra
13
                v0, CP0_ENTRYLO0
        mtc0
        // See <IDT R30xx Family Software Reference Manual> Chapter 6-8
14
15
        /* Hint: use 'tlbwr' to write CPO.EntryHi/Lo into a random tlb entry. */
16
17
        /* Exercise 2.10: Your code here. */
18
        t1bwr
19
20
        jr
21
    END(do_tlb_refill)
```