Zeus Emulator Setup

1. On Zeus server:

1) Setup PATH variables if not done already:

i. /emulator; ii. /platform-tools/; iii. /cmdline-tools/tools/bin.

export PATH=\$PATH:sdk_path/platform-tools/

2) Give all permissions to files under /dev/kvm.

sudo chmod 777 /dev/kvm

3) Create an emulator, take down its name.

avdmanager create avd -n name -k "sdk_id"

4) Save the following code to boot emulator.

#!/bin/bash

adb kill-server

adb start-server

emulator -avd \$1 -port 5554 -gpu guest -writable-system -no-snapshot

5) Create a VNC server, take down its id.

vncserver (id is after "... desktop is zeus:")

6) Find ip address, and take it down.

ifconfig (ip address is inet addr for eth0)

2. On your machine:

- 7) Install VNC viewer if not done already.
 - https://www.realvnc.com/en/connect/download/viewer/
- 8) Open VNC viewer, sign up or sign in.
- 9) Open a window for new connection.
 - File->New connection->General
- 10) Set the VNC server to be on Zeus.
 - ip_address:590 + id_in_step_5)
- 11) Double click to connect to the viewer.
 - Connect to ubcprivate before this
- 12) Input VNC password and proceed.

3. In VNC viewer:

- 13) Open a terminal window to run script.
 - Right click->Debian->Applications->Terminal Emulators->LXTerminal
- 14) Run script in step 4) with name in step 3).
 - ./script_path name
- 15) Wait and you should see the emulator!