Variables & Data Structures

Lab Manual, Chapter Five

To write the shortest and fastest possible assembly language programs you need to understand how the CPU references data in memory. The Intel 80x86 processor family provides a wide variety of memory addressing modes that allow efficient access to memory. Unless you master these addressing modes, you will not be able to write the most efficient programs.

The 80386 and later processors support an extended set of memory addressing modes. For those working on '386 (or greater) processors, the task is both simpler and more complex. On the one hand, the greater variety of addressing modes opens even more opportunity for optimization. On the other hand, the additional modes complicate the task of selecting the most appropriate mode.

In this laboratory you will experiment with the PC's memory and study the various 80x86 addressing modes. You will also explore various high level language data types and their implementation in assembly language. To support these experiments, you will learn how to use the Microsoft CodeViewTMdebugger, the 80x86 version of SIM886. Finally, you will begin writing real assembly language programs, assembling and linking them with the MASM 6.x assembler.

5.1 The LEA, LES, ADD, and MUL Instructions

You'll need to use the LEA, LES, ADD, and MUL instructions in this chapter's lab exercises, so it's worthwhile to briefly covering these instructions. A few examples may help demystify their use.

The LEA (load effective address) instruction loads a 16-bit register with the address of some specified memory location. This instruction takes the form:

```
LEA reg<sub>16</sub>, memory
```

Reg₁₆ is one of the 8086's 16-bit general purpose registers and memory represents a memory addressing mode (any **mod-r/m** value where **mod** is not 11). This instruction computes the effective address of the memory operand (that is, the offset into the given segment) and loads that effective address into the specified register.

Suppose BX=100h, BP=200h, SI=10h, and DI=20h. The following examples demonstrate how LEA works:

```
LEA AX, DS:[105h] Loads AX with 105h.

LEA AX, 5[BX][si] Loads AX with BX+SI+5 or 115h.

LEA BX, 5[BX] Loads BX with BX+5 or 105h.

LEA BX, [BX] Simply copies BX back into itself.

LEA AX, [BP][DI] Loads AX with BP+DI or 220h.

LEA AX, 10h[SI] Loads AX with SI+10h or 20h.
```

Given these values for BX, BP, SI, and DI, describe what the following LEA instructions will do:

5.1	LEA BX, [BX][SI]	
5.2	LEA SP, [BP]	
5.3	LEA DX, DS:[1027H]	

5.4	The opcode for the LEA instruction is 8Dh followed by a mod-reg-r/m byte and any neces
	sary displacement bytes. Given this encoding, what are the instruction bytes for LEA AX,
	5[BX][SI] ?

The LES instruction, although it looks like the LEA mnemonic, is a completely different instruction. It loads a 32-bit pointer into the ES register and some other 16-bit register. The syntax for this instruction is

```
LES reg_{16}, memory_{32}
```

The memory $_{32}$ operand means that the LES instruction loads 32 bits from four consecutive bytes in memory (L.O. byte first). The L.O. word goes into the 16-bit register, the H.O. word goes into the ES register. The main use of this instruction is to load memory pointers into ES and some other register (typically BX, SI, or DI) to gain access to the object referenced by the pointer.

As an example, suppose memory locations ds:0 through DS:7 contain 0, 2, 5, 6, 1, 2, 6, 4, respectively. The "LES BX, DS: $[\ 0\]$ " would load BX with 200h (the word starting at location 0) and ES with 605h (the value of the word starting at location two). Likewise, "LES SI, DS: $[\ 4\]$ " would load SI with 201h and ES with 406h.

5.5 Given the above values for DS:0...DS:7, what would "LES DI, DS:[2]" do?

The ADD instruction, as its name implies, adds two values together. It's syntax is almost identical to that of the MOV instruction's. The only major difference (other than using ADD rather than MOV) is that you cannot add a value to a segment register. This instruction adds the source and destination operands together and stores the sum into the destination operand. For example, the "ADD AX, 2" instruction adds two to the value in the AX register and leaves the result in the AX register.

5.6 If the opcode for the ADD instruction is 000000dw (where "d" and "w" have the same meanings as for the MOV instruction), followed by a mod-reg-r/m byte and any necessary displacement bytes, what is the instruction encoding for "ADD AX, BX"?

5.7 If AX contains five and BX contains two, what will the instruction "ADD AX, BX" do?

The 80x86 MUL instruction uses a slightly different syntax than the instructions you've seen thus far. Rather than having two operands, a source and a destination, the MUL instruction has only a single operand – the source operand. The destination for the 80x86 MUL instruction is always the AX register (if the source operand is an eight-bit register or memory location) or the DX:AX register pair (if the operand is 16 bits). These instructions do the following:

MUL ${\rm reg_8/mem_8}$ Multiplies AL by operand, stores the result into AX. MUL ${\rm reg_{16}/mem_{16}}$ Multiplies AX by operand, stores the result into DX:AX

The following questions assume AX = 2, BX=3, CX=4, and DX=5 at the beginning of each question. Please specify the exact and complete results for each of the following:

5.8 MULAX

5.9 MUL BX

 $5.1 \quad BX := BX + SI$

5.2 SP := BP

5.2 Variables in an Assembly Language Program

MASM provides many *assembler directives* specifically for declaring scalar variables. These directives are

DB, BYTE, and SBYTE for declaring byte variables,

- DW, WORD, and SWORD for declaring word variables,
- DD, DWORD, and SDWORD for declaring double word variables,
- REAL4, REAL8, and REAL10 for declaring floating point variables, and
- DF/FWORD, DQ/QSORD, and DT/TBYTE for other data types.

The syntax for each of these directives is identical. Using the BYTE directive as an example:

variable name

byte

?

If you want a word variable rather than a byte variable, you would substitute *word* for *byte* above. Likewise, you would substitute *dword* for *byte* if you wanted a double word variable. For example, to declare a 16-bit signed variable named *CurValue* you could use the declaration:

CurValue

sword

?

The DB, DW, DD, DF, DQ, and DT mnemonics are older, obsolete versions of BYTE, WORD, DWORD, etc. In general, you should use the new, easier to read versions rather than these. BYTE, WORD, and DWORD are for declaring *unsigned* variables. SBYTE, SWORD, and SDWORD let you declare *signed* variables. MASM ignores the signed/unsigned specification, but CodeView uses this information to properly display values during debugging.

5.10 How would you declare an eight-byte floating point variable "R"?

5.11 How would you declare an unsigned 32-bit variable "U"?

The question mark in the operand field tells MASM that you don't want the variable initialized when the program loads into memory. If you want to give the variable an initial value, specify that value in the operand field. As an example, the following initializes the CHR variable to the character 'A':

CHR

byte

`A'

5.12 How would you declare a signed 16-bit variable ("S") and initialize it to the value -129?

5.13 How would you declare a four byte floating point variable "Pf" and initialize it to 3.14159?

Generally, you will place all variables in the data segment of your program. When using the SHELLASM program you will almost always put your variables in the DSEG segment, e.g.,

dseg	segment	para public 'data'
bytevar	byte	?
wordvar	word	?
dwordvar	dword	?
byte2	sbyte	?
word2	sword	?
dseg	ends	

5.3 Declaring Your Own Types with TYPEDEF

The TYPEDEF directive lets you create your own data type directives. The TYPEDEF directive is especially useful for declaring pointer types (see the next section), you can also use this directive to create your own names for common types. For example, if you prefer *integer* to *sword* when declaring integer variables, you could create your own type as follows:

integer typedef sword

To declare a variable, I, of type integer, you would use the declaration:

I integer

You could even initialize I by specifying a value in the operand field:

I integer -13

Likewise, if you prefer "float" to REAL4 or DOUBLE to "REAL8" (i.e., you're a "C" programmer) you can create such types using the declarations:

FLOAT typedef real4
DOUBLE typedef real8

You can declare FLOAT and DOUBLE variables using statements like:

F FLOAT ?
D DOUBLE 3.19

5.14 How would you declare a "char" type which reserves storage for a one-byte character variable?

5.15 Give an example of how to declare a variable "chr" initialized with the character "A" using the above declaration.

5.4 Pointers

A pointer is a memory location (generally 16 or 32 bits) which contains the address of some other object in memory. This text will typically use 32-bit (far) pointers since they mesh well with the UCR Standard Library. Keep in mind, though, that 16-bit (near) pointers are more efficient if you are able to use them..

To declare a far (32-bit) pointer in your program, just use the **dword** directive (or some typedef'd equivalent) and declare the pointer as you would any other variable:

pointer typedef far ptr fptr1 dword ? fptr2 pointer ?

You can initialize a pointer with the address of an object by placing that object's name in the operand field of the declaration:

I word 10
Ptr2I pointer I
Ptr2Ptr2I pointer Ptr2I

5.3 DX := 1027h

The 80x86 family does not let you access objects through memory pointers directly⁸. To access an object referenced by a pointer you must use one of the 80x86's indirect or indexed addressing modes. When dealing with far pointers, you would typically use the ES:[BX], ES:[SI], or ES:[DI] addressing modes to access objects referenced by far pointers.

5.4 8Dh, 40h, 05h

5.16 Suppose you have an integer variable J and you want to create a pointer, PJ, to this variable. How could you declare such a pointer so that it will be properly initialized when loaded into memory

5.5 Load 605h into DI and 201h into ES.

5.17 What 80x86 instruction would you use to load the 32-bit pointer PJ into ES and BX?

5.6 03h, C3h

5.7 Set AX to seven.

5.8 Set DX = 0 & AX = 4

5.5 Arrays in Assembly Language Programs

Assembly language programmers generally implement arrays as a contiguous set of memory locations. In general, this provides the most efficient mechanism for accessing elements of an array. Therefore, this is the technique we will use to implement them.

There are a couple of ways to declare an array in your assembly language program.. The first and easiest way is to use the MASM *dup* operator:

IntArray word 16 dup (?)

The example above reserves 16 words of storage. The name "IntArray" is a word variable whose address just happens to be the very first word of the array (this is the *base address* of the array). Because each element of the array is two bytes long, you must multiply the index by two when attempting to access elements of this array. IntArray[0] refers to the first element of the array, IntArray[2] is the second element, IntArray[4] is the third element, IntArray[6] is the fourth element, and so on. A very common mistake beginners make when writing assembly language programs is that they forget to multiply the index by the size of an array element when computing an index into an array. Because the notation "IntArray[2]" looks just like the notation high level languages use, it's very easy to forget the real computation which must take place. The

Element_Address = Base_Address + Index * Element_Size

Element_Size is the size in bytes of one item in the array. Since the element size of a word array is two bytes, Element_Size is two, hence you must multiply your index by two before adding it to the base address⁹.

Even more confusing is the fact that this multiplicative factor changes with the size of the array elements. If you have an array of bytes, the multiplication factor is one and you can ignore it. For words, the factor is two. The factor is four when accessing double word arrays. If you are manipulating several different data types, keeping the multiplication factors straight can be a problem.

Consider the following array declaration:

complete formula for this computation is

5.12 S SWORD -129

5.11 U DWORD?

5.13 PI real4 3.14159

^{8.} Or should this be *indirectly*?

^{9.} Remember, the notation $\bar{X}YZ[ABC]$ in assembly language means XYZ+ABC. Hence the notation IntArray[2] means "add two to the base address of IntArray."

```
IntArray word 16 dup (?)
```

You can access elements of this array using 80x86 instructions like the following:

```
mov IntArray[4], 0
mov IntArray[8], ax
add ax, IntArray[2]
mul IntArray[0]
lea bx, IntArray[8]
```

(the last instruction loads BX with the offset of the fifth element from IntArray.)

5.18 What instruction would you use to load the last element of IntArray into BX?

5.19 How would you declare an array, RArray, containing 64 single precision (32-bit) floating point variables?

5.20 What instruction would you use to load the offset of RArray[10] into BX?

More often than not, you won't need to access a fixed element of an array as in the above examples. Instead, you'll probably have a value in a variable or in a register which you'll use to specify which element to operate on. You cannot use an operand of the form "IntArray[i]" to select the ith element of the array. Instead, you will have to compute the index into the array using the formula given above. For example, to access the ith element of IntArray, you will need to multiply the index by two (the element size is two). This product plus the base address of the array provides the address of the ith element. Some 80x86 code to accomplish this is

There are two important things to note above. First, this example used the ADD instruction to multiply i's value by two before using it. While it could have used the multiply instruction, the ADD instruction is simpler, faster, and easier to use. You can use sequences of the ADD instruction to easily multiply a value in a register by two, four, eight, or any other power of two. The other thing to notice above is that to access an array element, this code uses the indexed addressing mode. The 80x86 does not provide a memory addressing mode which lets you use an integer variable directly as an index into an array. Instead, you must first load the index value into an appropriate register and use one of the indexed addressing modes.

Note that if you're using an 80386 or later processor and your array element size is two, four, or eight you can use the 80386 *scaled indexed addressing modes* to automatically perform this multiplication for you. Since these are the most common array element sizes, the scaled indexed addressing mode can be very useful. The previous example, using the scaled indexed addressing mode takes only two instructions:

```
mov ebx, i ;"i" must be a dword variable!
mov ax, IntArray[ebx*2]
```

5.21 What statement would you use to declare an array, DArray, of 128 double precision (64-bit) floating point values?

5.22 What sequence of instructions would you use to access DArray[j] (8086 instructions only)?

._____

5.23 What (shorter) sequence of instructions could you use on the 80386 to access DArray[j]?

The MASM *dup* operator simply tells the assembler to duplicate the operand inside the parentheses. You may also specify multiple operands in the operand field and define an array in this fashion. This allows you to *initialize* the elements of the array before the program runs:

IntArray word 0,1,2,3,4,5,6,7 word 8,9,10,11,12,13,14,15

The declaration above sets aside 16 words in memory and initializes them with the values zero through fifteen. You would use the same 80x86 code to access these array elements as before.

Note that there is nothing magic about an array declaration. All you're doing is reserving some storage. When you access an element of an array, the 80x86 simply accesses a memory location at a given offset from the base address you supply. Consider the following variable declarations in the data segment:

I	word	0
J	word	1
K	word	2
L	word	3
M	word	4
N	word	5
0	word	6
P	word	7

Now consider the following sequence of instructions:

```
movbx, Indexaddbx, bxmovI[bx], ax
```

The sequence above is a very typical set of instructions you'd normally use to index into a word array whose base address is "I". However, as you can probably tell, "I" isn't really an array. It's just a word variable. The 80x86 doesn't care though, it will happily index off "I" and return the word at offset "Index*2" beyond "I". It is quite possible that "I" really is an array and the programmer wanted to access elements of "I" using names like "J", "K", etc. More likely than not, however, if you see code like the above in a program, it's an indication that there are problems with that program.

5.24 Suppose INDEX = 4, what variable would the above code access?

5.6 Multidimensional Arrays

The 80x86 hardware is set up to handle one-dimensional arrays with ease. Handling two or more dimensions is a bit more work. While there are a wide variety of ways to map multidimensional structures to the one-dimensional structure of memory, there are two techniques in common use: row-major ordering and column major ordering. We'll use row major ordering most of the time, though column major ordering is useful on occasion. Here we will concentrate on two-dimensional arrays, for a more general discussion, please consult the text.

The row major function that maps two values (indices) to a linear offset is

```
ElementAdrs = BaseAdrs + (ColIndex * RowSize + RowIndex) * ElementSize
For column major ordering the formula is
Element_Adrs = BaseAdrs + (RowIndex * ColSize + ColIndex) * ElementSize
To declare a multidimensional array use multiple dup operators as follows:
```

TwoDArray word 4 dup (4 dup (?))

5.14 typedef byte

5.15 chr char 'A'

5.16 PJ dword J

5.17 LES bx, PJ

The dup operator duplicates everything inside the parentheses. "4 dup (0,1,2,3)" duplicates the four values 0, 1, 2, and 3 four times for a total of 16 values (0, 1, 2, 3, 0, 1, 2, 3, ..., 2, 3). Likewise "4 dup (4 dup (0))" says to duplicate "4 dup (0)" four times, to produce a total of 16 zeros. The array declaration above reserves storage for 16 words. Of course, you could also declare a 4x4 array using the declaration

```
TwoDArray word 16 dup (0)
```

However, the former declaration is a little clearer as to its intent.

To access element TwoDArray[i][j] (row major order) you would use 80x86 code like the following

```
mov bx, i
add bx, bx ;Multiply by row size
add bx, bx ;*4
add bx, j ;+ row index
add bx, bx ;* Element Size (2)
mov ax, TwoDArray[bx]
```

5.25 How would you declare the array equivalent to "a:array [0.15][0.15] of integer;" in assembly language?

5.26	What is the code to load	"a[i][j]"	into ax	(assume column	major	ordering)
------	--------------------------	-----------	---------	----------------	-------	-----------

5.7 Structures

An array is a contiguous homogeneous collection of objects ¹⁰. A structure is a contiguous heterogeneous collection of objects in memory. Structures let you easily associate values which are logically related, yet of differing types, by placing these values in contiguous memory locations.

Structures are mainly an assembly language convention. When viewing structures in memory there is really no difference between a structure and a sequence of independent variables, other than that the elements of a structure always occupy contiguous locations. However, structures provide considerable value in an assembly language program where you may refer to the fields of the structure using a high level syntax.

To declare a structure *type* with MASM you use the STRUCT and ENDS directives. The following template provides the basic format:

```
StructureName STRUCT
 <Field Definitions>
StructureName ENDS
```

The <Field Definitions> section contains standard MASM variable declarations (using BYTE, WORD, DWORD, etc.). The following example demonstrates a structure for a complex number:

```
complex struct

Real real8 ?

Imaginary real8 ?

complex ends
```

To declare a variable of type complex, you could use a declaration like the following:

^{10.} That is, all elements of the array are the same type.

Vector	complex {}	5.18 mov bx, IntArray[30]
	ial values you want to supply for the variable "Vector" must appear inside the braces. For e, if you want the assembler to preinitialize "Vector" to (1.0, -1.0) you would use the dec-	
Vector	complex $\{1.0, -1.0\}$	
	efault, you want to initialize <i>all</i> variables of type complex to the same value, you could complex" as follows:	5 10
complex Real Imagina complex	real8 1.0 ary real8 -1.0	5.19 RArray real4 64 dup (?)
You can above.	still override this default initialization by specifying the initial values in the braces as	
5.27	Create a structure for a type <i>string</i> which contains two fields: <i>length</i> which is a single byte and <i>chars</i> which is an array of 80 bytes.	5.20 lea bx, RArray[40]
		5.21 DArray real8 128 dup (?)
does <i>not</i> actually	important to note that a structure definition (using the STRUCT and ENDS directives) of create a structure variable for you. All it does is create a type for declaring variables. To create a structure variable, you must use the structure's data as a data definition directive the "Vector" example above.	5.22 mov bx, J
guages l	access a field of a structure variable you use a syntax similar to that of high-level lan- like "C" or Pascal. A name of the form <i>variable.field</i> selects the specified field in the struc- ector.Imaginary" selects the "Imaginary" field from the "Vector" variable.	add bx, bx add bx, bx add bx, bx mov ax, DArray [bx]
field namaddress of able. In mechanic	ce MASM stores successive fields in contiguous memory locations, you can think of the mes as <i>offsets</i> from the base address of a structure. The <i>base address</i> of a structure is the of the first element of that structure, which corresponds to the name of the structure varimany respects, the <i>variable.field</i> syntax is comparable to <i>variable[field]</i> since both isms compute the address of the specified object by adding the address of variable with owever, MASM will not allow the brackets operator on structure names.	or mov bx, J mov ax, 8 mul bx mov bx, ax mov ax, DArray [bx]
5.28	How would you declare a variable of type "string" (see the previous question) named "Identifier" in your data segment?	
5.29	How would you declare the "Identifier" variable above, initializing the "Length" field to zero?	5.23 Assume J is 32 bits. mov ebx, J mov eax, DArray[ebx*8]

5.30 What instruction could you use to load the value of the "length" field above into the AL register?

5.8 Memory Organization Laboratory Exercises

In this laboratory you will examine how the 80x86 family organizes values in memory. You will also create several data structures in memory and examine them with the CodeView debugger. Finally, you will also assemble and link some very simple assembly language programs and load them into memory with the CodeView debugger.

5.8.1 Before Coming to the Laboratory

Your pre-lab report should contain the following:

- A copy of this lab guide chapter with all the questions answered and corrected.
- A write-up on the CodeView debugger explaining, in your own words, how the following commands work in CodeView: A, D, E (Enter), F, G, I (input), M (Move), O (Output), Q, R, T, and U.
- A write-up explaining how the MOV, ADD, LEA, LES, and MUL instructions work.

See Chapter Two of this laboratory manual for an example pre-lab report.

Note: your Teaching Assistant or Lab Instructor may elect to give a quiz before the lab begins on the material covered in the laboratory. You will do quite well on that quiz if you've properly prepared for the lab and studied up on the stuff prior to attending the lab. If you simply copy the material from someone else you will do poorly on the quiz and you will probably not finish the lab. Do not take this pre-lab exercise lightly.

5.8.2 Laboratory Exercises

In this laboratory you will perform the following activities:

- Demonstrate the use of the CodeView debugger and many of the commands in the debugger
- Demonstrate the operation of the 8086 MOV, LEA, LES, ADD, and MUL instructions and addressing modes.
- Enter several 8086 machine language programs into the CodeView and single step through the programs to execute them.
- Use the debugger to modify the operation of the programs.
- Examine memory locations using CodeView and explore the memory organization of the 8086
- Create various data structures (i.e., arrays and structs) and explore their memory organization.
- Create simple 8086 programs to access the above data structures.
- Explore the various encodings of 8086 instructions.
- Exercise 1: Create an array of the form "A:array [0..3, 0..4] of word;" starting at location 8000:0. Initialize the array elements as you did for exercise 5 with the values 0, 1, 2, 3, 4, 10, 11, 12, 13, 14, 20, 21, 22, 23, 24, 30, 31, 32, 33, and 34. Use row major ordering when creating the array. Dump the memory using the CodeView Dump command to the printer or a file. Include this printout in your lab report and mark each row of the array. Enter the following short machine language program using CodeView's Assemble command. It uses the word at location 8000:80 as the first index (the row number) and location 8000:82 as the second index (the column number) and loads the word at that address into AX. Don't forget that DS must contain 8000h before running this code.

```
mov ax, ds:[80h] ;Get row number (column index)
mov bx, 5 ;Multiply by the size of a row
mul bx
add ax, ds:[82h] ;Add in the column number (row index)
mov bx, ax
```

add bx, bx ;Element size is two mov ax, ds:0[bx] ;Fetch desired array

5.25 A word 16 dup (16 dup (?))

element.

For your lab report: Dump the array and annotate each element of the array. Run the code above with a reasonable pair of values in locations 8000:80 and 8000:82. Capture the results and include them in your lab report. Explain the results.

For additional credit: Run the code above with several different values in locations 8000:80 and 8000:82. Capture the output and describe the results in your lab report.

 Exercise 2: Repeat exercise 7 using column major ordering. Use the following code for this example:

```
bx, ds:[80]
mov
                            ;Fetch first index
add
      bx, bx
                            ;Multiply by column size (4)
add
      bx, bx
      bx, ds:[82]
add
                           ; Add in second index
add
      bx, bx
                           ;Multiply by element size (2)
      ax, ds:0[bx] ;Fetch array element
mov
                    ;Stop inside CodeView.
int
```

Exercise 3: Make a copy of the LAB4.ASM file on the disk accompanying this lab manual. Name the file "LAB4_1.ASM". In the data segment (DSEG) create an array named "A1" which is a single dimensional array of 128 bytes. Create a second array, named "A2" which is a 4x4 array of words. Create a third array, named "A3" which is a 3x3 array of words initialized to the value 00, 01, 02, 10, 11, 12, 20, 21, 22. Use row major ordering for these arrays. Finally, declare two word variables, "I" and "J", and initialize them to zero in the data segment. Now, enter the code into the main program (after the comment which states "Enter your main program here.") which copies A1[i] to A2[i][j] and then copies A2[i][j] to A3[j][i]. Terminate your program with the INT 3 instruction. Use row major ordering for A2 and A3. Next, assemble your code using the following DOS command to run MASM:

ml /Zi lab4_1.asm

Note that the '/Zi" must be an uppercase "Z" and a lowercase "i". the "/Zi" command line parameter tells MASM to include *source information* in the .EXE file. This will produce a file named "LAB4_1.EXE" which you can load into CodeView using the DOS command:

CV LAB4 1

Single step through the code and verify that it works correctly.

For your lab report: Include a printout of the Lab4_1.asm file. Heavily comment each instruction you add to this program to describe its purpose.

For additional credit: MASM lets you create an *assembly listing* of your source code. Use the DOS command "ml /?" to get a list of legal MASM command line options. Determine which one lets you produce and assembly listing. Include the assembly listing with your lab report.

Exercise 4: Add a structure to the Lab4_1.ASM program and create a structure variable in the data segment (DSEG). Modify your main program to load various fields of this structure into the 80x86 registers. Use the CodeView Unassemble command to look at the raw machine code produced by the assembler.

For your lab report: Comment on what you see. Include appropriate screen dumps/captures in your lab report.

Exercise 5: Connect the circuit you built for labs two and three to the parallel printer port on your computer. Use the following output command to write a value to the LEDs on your circuit:

5.26 mov bx, j add bx, bx add bx, bx add bx, i add bx, bx mov ax, a[bx]

5.27 string struct length byte ? chars byte 80 dup (?) string ends

5.28 Identifier string {}

5.29 Identifier string {0}

O port value

Port is the base address of the parallel port to which you've connected your circuit. To determine the appropriate port address, dump memory locations 40:8 through 40:d. The first two locations (40:8 and 40:9) contain the base I/O address for LPT1:. The second two locations (40:a and 40:b) contain the base I/O address for LPT2:. The last pair of locations contain the base address for LPT3:. Typical addresses are 378h, 278h, and 3BCh. If a zero appears in one of these words, then the system did not recognize the associated device. Be sure to select the appropriate port value for your connection.

The *value* operand is the value to write to the printer port. For example, if you've connected your circuit to LPT1: and it is at I/O address 378h (i.e., the word at location 40:8 contains 378h), you can turn off all the LEDs with the command **0 378 0**. Likewise, you can turn on all the LEDs using the command **0 378 ff**. Try turning on each of the LEDS individually with a set of eight "O" commands.

For your lab report: Describe the use of this command to turn on and off various LEDs on your circuit.

5.9 Sample Programs

This section contains several sample programs that demonstrate the concepts in Chapter Four of the textbook. Each of these short programs can be found on the diskette accompanying this lab manual. These programs all assemble and run, although you should run them from the CodeView debugger since they do not produce any output.

5.9.1 Sample Program #1: Simple Variable Declarations

This short program demonstrates how to declare byte, word, and double word global variables. It also demonstrates how to use the typedef directive to create your own variable types. The program also declares some simple pointer variables and the main program accesses data indirectly using those pointers. Finally, this short sample program also demonstrates how to initialize variables you declare in the data segment.

```
; Sample variable declarations
; This sample file demonstrates how to declare and access some simple
; variables in an assembly language program.
; Randall Hyde
; Note: global variable declarations should go in the "dseg" segment:
dseg
              segment
                      para public 'data'
; Some simple variable declarations:
                                          ;"?" means uninitialized.
character
             byte
                        ?
UnsignedIntVar word
DblUnsignedVardword
;You can use the typedef statement to declare more meaningful type names:
integer
                        sword
              typedef
char
             typedef
                        byte
FarPtr
             typedef
                        dword
; Sample variable declarations using the above types:
             integer
J
c1
             char
PtrVar
             FarPtr
```

5.30 mov al, Identifier.Length

```
; You can tell MASM & DOS to initialize a variable when DOS loads the ; program into memory by specifying the initial value in the operand ; field of the variable's declaration:
```

K integer 4
c2 char 'A'
PtrVar2 FarPtr L ;Initializes PtrVar2
with the ; address of K.

; You can also set aside more than one byte, word, or double word of ; storage using these directives. If you place several values in the ; operand field, separated by commas, the assembler will emit one byte

; word, or dword for each operand:

L integer 0, 1, 2, 3 c3 char 'A', 0dh, 0ah, 0 PtrTbl FarPtr J, K, L

- ; The BYTE directive lets you specify a string of characters byte enclosing
- ; the string in quotes or apostrophes. The directive emits one byte of data $% \left(1\right) =\left(1\right) \left(1\right) +\left(1\right) \left(1\right) \left(1\right) +\left(1\right) \left(1\right) \left($
- ; for every character in the string (not including the quotes or apostrophes $% \left(1\right) =\left(1\right) +\left(1\right$
- ; that delimit the string):

string byte "Hello world", 0dh, 0ah, 0

segment

dseg ends

cseg

; The following program demonstrates how to access each of the above ; variables.

para public 'code'

	assume	cs:cseg, ds:dseg	
Main	proc	av daga	These statements are
provided by	mov	ax, dseg	These statements are
the	mov	ds, ax	; shell.asm to initialize
CIIC	mov	es, ax	; segment register.

; Some simple instructions that demonstrate how to access memory:

	lea	bx, L	;Point bx at first word
in L.			
	mov	ax, [bx]	;Fetch word at L.
	add	ax, 2[bx]	;Add in word at L+2 (the
"1").			
	add	ax, 4[bx]	;Add in word at L+4 (the
"2").			
	add	ax, 6[bx]	;Add in word at L+6 (the
"3").			

```
mı ı l
                          K
                                             ; Compute (0+1+2+3)*123.
                          J, ax
                                             ;Save away result in J.
               mov
               les
                          bx, PtrVar2
                                             ;Loads es:di with address of L.
                                             ;Loads 4 into di
               mov
                          di, K
                                             ;Fetch value of L+4.
                          ax, es:[bx][di]
               mov
; Examples of some byte accesses:
                          c1, ' '
                                             ;Put a space into the c1 var.
               mov
                          al, c2
                                             ;c3 := c2
               mov
                          c3, al
               mov
                                             ;Magic number for DOS
Quit:
               mov
                          ah, 4ch
               int
                          21h
                                             ; to tell this program to quit.
Main
               endp
               ends
csea
sseg
               segment
                          para stack 'stack'
stk
              byte
                          1024 dup ("stack
               ends
sseg
                          para public 'zzzzzz'
zzzzzseg
              segment
                          16 dup (?)
LastBytes
              byte
zzzzzseg
               ends
               end
                          Main
```

5.9.2 Sample Program #2: Using Pointers

This brief program demonstrates how to declare and use near and far pointers in an assembly language program.

```
; Using Pointer Variables in an Assembly Language Program
; This short sample program demonstrates the use of pointers in
; an assembly language program.
; Randall Hyde
dseg
              segment
                         para public 'data'
; Some variables we will access indirectly (using pointers):
J
                         0, 0, 0, 0
              word
K
              word
                         1, 2, 3, 4
              word
                         5, 6, 7, 8
; Near pointers are 16-bits wide and hold an offset into the current data
; segment (dseg in this program). Far pointers are 32-bits wide and hold
; a complete segment:offset address. The following type definitions let
; us easily create near and far pointers
nWrdPtr
              typedef
                         near ptr word
fWrdPtr
              typedef
                         far ptr word
; Now for the actual pointer variables:
```

```
Ptr1
               nWrdPtr
                          ?
Ptr2
               nWrdPtr
                          K
                                             ;Initialize with K's
address.
Ptr3
               fWrdPtr
                          L
                                             ; Initialize with L's
segmented adrs.
dseg
               ends
               segment
                          para public 'code'
cseg
               assume
                          cs:cseg, ds:dseg
Main
               proc
               mov
                          ax, dseg
                                             ;These statements are
provided by
               mov
                          ds, ax
                                             ; shell.asm to initialize
the
                                             ; segment register.
               mov
                          es, ax
; Initialize Ptrl (a near pointer) with the address of the J
variable.
                          ax, J
               lea
                          Ptrl, ax
               mov
; Add the four words in variables J, K, and L together using pointers
; these variables:
               mov
                          bx, Ptrl
                                             ;Get near ptr to J's 1st
word.
                          si, Ptr2
               mov
                                             ;Get near ptr to K's 1st
word.
               les
                          di, Ptr3
                                             ;Get far ptr to L's 1st
word.
                          ax, ds:[si]
                                             ;Get data at K+0.
               mov
                                             ;Add in data at L+0.
               add
                          ax, es:[di]
                          ds:[bx], ax
                                             ;Store result to J+0.
               mov
               add
                          bx, 2
                                             ; Move to J+2.
               add
                          si, 2
                                             ;Move to K+2.
               add
                          di, 2
                                             ; Move to L+2.
               mov
                          ax, ds:[si]
                                             ;Get data at K+2.
               add
                          ax, es:[di]
                                             ;Add in data at L+2.
                          ds:[bx], ax
                                             ;Store result to J+2.
               mov
               add
                          bx, 2
                                             ; Move to J+4.
                          si, 2
               add
                                             ; Move to K+4.
               add
                          di, 2
                                             ;Move to L+4.
                          ax, ds:[si]
                                             ;Get data at K+4.
               mov
                          ax, es:[di]
                                             ;Add in data at L+4.
               add
                          ds:[bx], ax
                                             ;Store result to J+4.
               mov
               add
                          bx, 2
                                             ;Move to J+6.
               add
                          si, 2
                                             ; Move to K+6.
               add
                          di, 2
                                             ;Move to L+6.
               mov
                          ax, ds:[si]
                                             ;Get data at K+6.
                                             ;Add in data at L+6.
               add
                          ax, es:[di]
```

```
ds:[bx], ax
                                            ;Store result to J+6.
              mov
Quit:
              mov
                         ah, 4ch
                                            ;Magic number for DOS
              int
                         21h
                                            ; to tell this program to quit.
Main
              endp
              ends
cseg
                         para stack 'stack'
sseg
              segment
stk
              byte
                         1024 dup ("stack
              ends
sseg
                         para public 'zzzzzz'
zzzzzseg
              segment
                         16 dup (?)
LastBytes
              byte
zzzzzseg
              ends
              end
                         Main
```

5.9.3 Sample Program #3:Single Dimension Arrays

This short program demonstrates how to declare, initialize, and access elements of single dimensional arrays.

```
; Sample array declarations
; This sample file demonstrates how to declare and access some single
; dimension array variables in an assembly language program.
; Randall Hyde
               .386
                                                    ; Need to use some 80386 addressing
               option
                          segment:use16
                                            ; modes.
dseg
               segment
                         para public 'data'
J
               word
                                             ;We will use these variables as the
               word
                                             ; indexes into the arrays.
Κ
_{\rm L}
               word
Μ
               word
                          0
JD
              dword
KD
               dword
                          1
LD
               dword
                          2
               dword
; Some simple uninitialized array declarations:
ByteAry
              byte
                          4 dup (?)
WordAry
              word
                          4 dup (?)
DwordAry
                          4 dup (?)
              dword
RealAry
                          4 dup (?)
              real8
; Some arrays with initialized values:
                          0, 1, 2, 3
BArray
              byte
                          0, 1, 2, 3
WArray
              word
                          0, 1, 2, 3
DWArray
              dword
                          0.0, 1.0, 2.0, 3.0
              real8
RArray
```

```
; An array of pointers:
PtrArray
              dword
                         ByteAry, WordAry, DwordAry, RealAry
dseg
              ends
; The following program demonstrates how to access each of the above
; variables.
                         para public 'code'
cseg
               segment
               assume
                          cs:cseg, ds:dseg
Main
              proc
              mov
                         ax, dseg
                                            ;These statements are
provided by
                                            ; shell.asm to initialize
              mov
                         ds, ax
the
              mov
                          es, ax
                                            ; segment register.
; Initialize the index variables. Note that these variables provide
; logical indices into the arrays. Don't forget that we've got to
; multiply these values by the element size when accessing elements
of
; an array.
                         J, 0
              mov
                         K, 1
              mov
              mov
                         L, 2
              mov
                         M, 3
; The following code shows how to access elements of the arrays using
; simple 80x86 addressing modes:
              mov
                         bx, J
                                            ;AL := ByteAry[J]
              mov
                         al, ByteAry[bx]
                         bx, K
              mov
                                            ;AX := WordAry[K]
               add
                         bx, bx
                                            ;Index*2 since this is a
word array.
                         ax, WordAry[bx]
              mov
              mov
                         bx, L
                                            ;EAX := DwordAry[L]
               add
                         bx, bx
                                            ;Index*4 since this is a
double
                         bx, bx
               add
                                            ; word array.
                         eax, DwordAry[bx]
              mov
              mov
                         bx, M
                                            ;BX :=
address(RealAry[M])
              add
                         bx, bx
                                            ;Index*8 since this is a
quad
              add
                         bx, bx
                                            ; word array.
               add
                         bx, bx
               lea
                         bx, RealAry[bx]
                                            ;Base address + index*8.
; If you have an 80386 or later CPU, you can use the 386's scaled
indexed
; addressing modes to simplify array access.
```

```
mov
                          ebx, JD
               mov
                          al, ByteAry[ebx]
                          ebx, KD
               mov
                          ax, WordAry[ebx*2]
               mov
                          ebx, LD
               mov
               mov
                          eax, DwordAry[ebx*4]
                          ebx, MD
               mov
                          bx, RealAry[ebx*8]
               lea
Quit:
               mov
                          ah, 4ch
                                              ;Magic number for DOS
               int
                          21h
                                             ; to tell this program to quit.
Main
               endp
cseg
               ends
sseg
               segment
                          para stack 'stack'
stk
               byte
                          1024 dup ("stack
               ends
sseg
                          para public 'zzzzzz'
zzzzzseg
               segment
LastBytes
               byte
                          16 dup (?)
zzzzzzseg
               ends
               end
                          Main
```

5.9.4 Sample Program #4: Multidimensional Array Declaration and Access

The following sample program demonstrates how to declare, initialize, and access elements of multidimensional arrays.

```
; Multidimensional Array declaration and access
; Randall Hyde
               .386
                                             ; Need these two statements to use
              option
                                            ; 80386 register set.
                          segment:use16
dseg
                          para public 'data'
              segment
; Indices we will use for the arrays.
              word
                          1
J
                          2
Κ
              word
              word
; Some two-dimensional arrays.
; Note how this code uses the "dup" operator to suggest the size
; of each dimension.
B2Ary
                          3 dup (4 dup (?))
              byte
```

```
4 dup (3 dup (?))
W2Ary
              word
D2Ary
              dword
                         2 dup (6 dup (?))
; 2D arrays with initialization.
; Note the use of data layout to suggest the sizes of each array.
                         0, 1, 2, 3
B2Ary2
              byte
                         4, 5, 6, 7
              byte
                         8, 9, 10, 11
              byte
W2Ary2
              word
                         0, 1, 2
              word
                         3, 4, 5
                         6, 7, 8
              word
              word
                         9, 10, 11
D2Ary2
              dword
                         0, 1, 2, 3, 4, 5
              dword
                         6, 7, 8, 9, 10, 11
; A sample three dimensional array.
                         2 dup (3 dup (4 dup (?)))
W3Ary
              word
              ends
dseg
cseg
              segment
                         para public 'code'
              assume
                         cs:cseg, ds:dseg
Main
              proc
                         ax, dseg
              mov
                                            ;These statements are
provided by
                         ds, ax
                                            ; shell.asm to initialize
              mov
the
                         es, ax
                                            ; segment register.
              mov
; AL := B2Ary2[j,k]
                         bx, J
                                            ;index := (j*4+k)
              mov
              add
                         bx, bx
                                            ;j*2
                         bx, bx
                                            ;j*4
              add
              add
                         bx, K
                                            ;j*4+k
                         al, B2Ary2[bx]
; AX := W2Ary2[j,k]
                                            ;index := (j*3 + k)*2
              mov
                         ax, J
              mov
                         bx, 3
              mul
                         bx
                                            ;(j*3)-- This destroys
DX!
              add
                         ax, k
                                            ;(j*3+k)
                                            ;(j*3+k)*2
              add
                         ax, ax
              mov
                         bx, ax
              mov
                         ax, W2Ary2[bx]
; EAX := D2Ary[i,j]
                                           ;index := (j*6 + k)*4
              mov
                         ax, J
```

```
bx, 6
               mov
                          bx
                                             ;DX:AX := j*6, ignore overflow in DX.
               mul
               add
                          ax, k
                                             ;j*6 + k
               add
                          ax, ax
                                             i(j*6 + k)*2
                                             ;(j*6 + k)*4
               add
                          ax, ax
               mov
                          bx, ax
                          eax, D2Ary[bx]
               mov
; Sample access of a three dimensional array.
; AX := W3Ary[J,K,L]
                                             ;index := ((j*3 + k)*4 + 1)*2
                          ax, J
               mov
               mov
                          bx, 3
               mul
                          bx
                                             ; j*3
               add
                          ax, K
                                             ;j*3 + k
               add
                          ax, ax
                                             i(j*3 + k)*2
                          ax, ax
                                             i(j*3 + k)*4
               add
                                             ;(j*3 + k)*4 + 1
               add
                          ax, l
                                             ;((j*3 + k)*4 + 1)*2
               add
                          ax, ax
               mov
                          bx, ax
                          ax, W3Ary[bx]
               mov
Quit:
                          ah, 4ch
                                             ;Magic number for DOS
               mov
               int
                          21h
                                             ; to tell this program to quit.
Main
               endp
               ends
cseg
               segment
                          para stack 'stack'
sseg
stk
               byte
                          1024 dup ("stack
sseg
               ends
zzzzzzseg
               segment
                          para public 'zzzzzz'
                          16 dup (?)
LastBytes
               byte
zzzzzseg
               ends
               end
                          Main
```

5.9.5 Sample Program #5: Structures

This sample program demonstrates how to declare structure types and variables. It also shows how to initialize the fields of a structure at assembly time. Finally, it demonstrates how to access fields of a structure from within an assembly language program and how to deal with pointers to structures.

```
; Sample Structure Definitions and Accesses.
;
; Randall Hyde

dseg segment para public 'data'

; The following structure holds the bit values for an 80x86 mod-reg-r/m byte.

mode struct
modbits byte ?
reg byte ?
```

```
byte
                          ?
rm
mode
               ends
Instr1Adrs
                          {}
                                                    ;All fields
               mode
uninitialized.
Instr2Adrs
                          {}
              mode
; Some structures with initialized fields.
axbx
              mode
                          {11b, 000b, 000b}
                                                    ;"ax, ax" adrs
mode.
axdisp
                          {00b, 000b, 110b}
                                                    ; "ax, disp" adrs
               mode
mode.
cxdispbxsi
               mode
                          {01b, 001b, 000b}
                                                    ;"cx,
disp8[bx][si]" mode.
; Near pointers to some structures:
sPtr1
               word
                          axdisp
sPtr2
               word
                          Instr2Adrs
               ends
dseg
cseg
               segment
                          para public 'code'
               assume
                          cs:cseg, ds:dseg
Main
               proc
               mov
                          ax, dseg
                                             ;These statements are
provided by
               mov
                          ds, ax
                                             ; shell.asm to initialize
the
                          es, ax
                                             ; segment register.
               mov
; To access fields of a structure variable directly, just use the "."
; operator like you would in Pascal or C:
               mov
                          al, axbx.modbits
                          InstrlAdrs.modbits, al
               mov
                          al, axbx.reg
               mov
               mov
                          InstrlAdrs.reg, al
               mov
                          al, axbx.rm
                          InstrlAdrs.rm, al
               mov
; When accessing elements of a structure indirectly (that is, using a
; pointer) you must specify the structure type name as the first
; "field" so MASM doesn't get confused:
                          si, sPtrl
               mov
                          di, sPtr2
               mov
                          al, ds:[si].mode.modbits
               mov
               mov
                          ds:[di].mode.modbits, al
                          al, ds:[si].mode.reg
               mov
               mov
                          ds:[di].mode.reg, al
```

```
al, ds:[si].mode.rm
               mov
                          ds:[di].mode.rm, al
               mov
Quit:
                          ah, 4ch
                                             ;Magic number for DOS
               mov
               int
                          21h
                                             ; to tell this program to quit.
Main
               endp
cseg
               ends
               segment
                          para stack 'stack'
sseg
stk
               byte
                          1024 dup ("stack
               ends
sseg
                          para public 'zzzzzz'
zzzzzseg
               segment
LastBytes
               byte
                          16 dup (?)
zzzzzzseg
               ends
               end
                          Main
```

5.9.6 Sample Program #6: Arrays of Structures

This short program shows you how to declare an array of structures and access elements of that array. It provides examples for one, two, and three dimensional arrays of structures.

```
; Arrays of Structures
; Randall Hyde
dseg
              segment
                         para public 'data'
; A structure that defines an (x,y) coordinate.
; Note that the Point data type requires four bytes.
Point
              struct
Χ
              word
              word
Point
              ends
; An uninitialized point:
Pt1
              Point
                         {}
; An initialized point:
              Point
                         {12,45}
; A one-dimensional array of uninitialized points:
PtAry1
              Point
                         16 dup ({})
                                            ;Note the "{}" inside the parens.
; A one-dimensional array of points, all initialized to the origin.
                         16 dup ({0,0})
PtAry1i
              Point
```

```
; A two-dimensional array of points:
PtAry2
               Point
                          4 dup (4 dup ({}))
; A three-dimensional array of points, all initialized to the origin.
                          2 dup (3 dup (4 dup ({0,0})))
PtAry3
               Point
; A one-dimensional array of points, all initialized to different
values:
iPtAry
               Point
                          \{0,0\}, \{1,2\}, \{3,4\}, \{5,6\}
; Some indices for the arrays:
J
               word
                          1
               word
                          2
L
               word
                          3
               ends
dseg
; The following program demonstrates how to access each of the above
; variables.
               segment
                          para public 'code'
cseg
               assume
                          cs:cseg, ds:dseg
Main
               proc
               mov
                          ax, dseg
                                            ;These statements are
provided by
                          ds, ax
                                             ; shell.asm to initialize
               mov
the
                          es, ax
                                             ; segment register.
              mov
; PtAry1[J] := iPtAry[J]
               mov
                          bx, J
                                            ;Index := J*4 since there
are four
                          bx, bx
                                             ; bytes per array element
               add
(each
                                             ; element contains two
               add
                          bx, bx
words).
              mov
                          ax, iPtAry[bx].X
                          PtAry1[bx].X, ax
               mov
                          ax, iPtAry[bx].Y
               mov
               mov
                          PtAryl[bx].Y, ax
; CX := PtAry2[K,L].X; DX := PtAry2[K,L].Y
               mov
                          bx, K
                                            ;Index := (K*4 + J)*4
                          bx, bx
               add
                                             ;K*2
               add
                          bx, bx
                                             ;K*4
```

```
K*4 + J
              add
                          bx, J
              add
                          bx, bx
                                            ;(K*4 + J)*2
              add
                          bx, bx
                                             ;(K*4 + J)*4
                          cx, PtAry2[bx].X
              mov
                          dx, PtAry2[bx].Y
              mov
; PtAry3[j,k,1].X := 0
                                             ;Index := ((j*3 +k)*4 + 1)*4
              mov
                          ax, j
                         bx, 3
              mov
                         bx
                                            ;j*3
              mul
              add
                                            ;j*3 + k
                          ax, k
                                            ;(j*3 + k)*2
              add
                         ax, ax
                                            ;(j*3 + k)*4
              add
                         ax, ax
              add
                         ax, l
                                            i(j*3 + k)*4 + 1
              add
                         ax, ax
                                            i((j*3 + k)*4 + 1)*2
              add
                          ax, ax
                                            ;((j*3 + k)*4 + 1)*4
              mov
                         bx, ax
                          PtAry3[bx].X, 0
              mov
Quit:
              mov
                          ah, 4ch
                                             ;Magic number for DOS
              int
                          21h
                                             ; to tell this program to quit.
Main
              endp
              ends
cseg
sseg
              segment
                          para stack 'stack'
stk
              byte
                          1024 dup ("stack
              ends
sseg
              segment
                          para public 'zzzzzz'
zzzzzseg
LastBytes
              byte
                          16 dup (?)
zzzzzseg
              ends
               end
                          Main
```

5.9.7 Sample Program #7: Structures and Arrays

This sample program demonstrates how to declare arrays of structures and how to include arrays and structures as fields within a structure. The 80x86 program code also demonstrates how to access the fields and elements of these data types.

```
; Structures Containing Structures as fields
; Structures Containing Arrays as fields
; Randall Hyde
dseg
               segment
                         para public 'data'
Point
               struct
Χ
               word
                          ?
Υ
               word
                          ?
Point
               ends
; We can define a rectangle with only two points.
; The color field contains an eight-bit color value.
; Note: the size of a Rect is 9 bytes.
Rect
              struct
```

```
UpperLeft
               Point
                          {}
LowerRight
               Point
                          {}
Color
               byte
                          ?
Rect
               ends
; Pentagons have five points, so use an array of points to
; define the pentagon. Of course, we also need the color
; field.
; Note: the size of a pentagon is 11 bytes.
Pent
               struct
Color
               byte
                          ?
Pts
               Point
                          5 dup ({})
Pent
               ends
; Okay, here are some variable declarations:
Rect1
               Rect
                          {} {{0,0}, {1,1}, 1}
Rect2
               Rect
                          {}
{}, {}, {}, {}
Pentagon1
               Pent
Pentagons
               ent
Index
               word
dseg
               ends
               segment
                          para public 'code'
cseg
               assume
                          cs:cseg, ds:dseg
Main
               proc
               mov
                          ax, dseg
                                             ;These statements are
provided by
                          ds, ax
                                             ; shell.asm to initialize
               mov
the
                                             ; segment register.
               mov
                          es, ax
; Rect1.UpperLeft.X := Rect2.UpperLeft.X
               mov
                          ax, Rect2.Upperleft.X
                          Rectl.Upperleft.X, ax
               mov
; Pentagon1 := Pentagons[Index]
               mov
                          ax, Index
                                             ;Need Index*11
               mov
                          bx, 11
               mul
                          bx
                          bx, ax
               mov
; Copy the first point:
               mov
                          ax, Pentagons[bx].Pts[0].X
                          Pentagon1.Pts[0].X, ax
               mov
                          ax, Pentagons[bx].Pts[0].Y
               mov
               mov
                          Pentagon1.Pts[0].Y, ax
; Copy the second point:
                          ax, Pentagons[bx].Pts[2].X
               mov
               mov
                          Pentagon1.Pts[2].X, ax
```

```
ax, Pentagons[bx].Pts[2].Y
              mov
                          Pentagon1.Pts[2].Y, ax
              mov
; Copy the third point:
              mov
                          ax, Pentagons[bx].Pts[4].X
                          Pentagon1.Pts[4].X, ax
              mov
                          ax, Pentagons[bx].Pts[4].Y
              mov
              mov
                          Pentagon1.Pts[4].Y, ax
; Copy the fourth point:
                          ax, Pentagons[bx].Pts[6].X
              mov
                          Pentagon1.Pts[6].X, ax
              mov
              mov
                          ax, Pentagons[bx].Pts[6].Y
              mov
                          Pentagon1.Pts[6].Y, ax
; Copy the fifth point:
              mov
                          ax, Pentagons[bx].Pts[8].X
                          Pentagon1.Pts[8].X, ax
              mov
                          ax, Pentagons[bx].Pts[8].Y
              mov
                          Pentagon1.Pts[8].Y, ax
              mov
; Copy the Color:
                          al, Pentagons[bx].Color
              mov
                          Pentagon1.Color, al
              mov
Quit:
              mov
                          ah, 4ch
                                            ;Magic number for DOS
              int
                          21h
                                            ; to tell this program to quit.
Main
              endp
              ends
cseg
              segment
                         para stack 'stack'
sseg
stk
              byte
                         1024 dup ("stack
              ends
sseg
                         para public 'zzzzzz'
              segment
zzzzzseg
                          16 dup (?)
LastBytes
              byte
              ends
zzzzzseg
              end
                         Main
```

5.9.8 Sample Program #8:Pointer to Structures

This sample program demonstrates how to work with pointers to structures and pointers to arrays of structures.

```
; Pointers to structures
; Pointers to arrays of structures
;
; Randall Hyde

.386 ;Need these two statements so we can option segment:use16 ; use 80386 register set.
```

```
dseg
               segment
                          para public 'data'
; Sample structure.
; Note: size is seven bytes.
Sample
               struct
              byte
                          ?
b
                          ?
W
               word
                          ?
d
               dword
Sample
               ends
; Some variable declarations:
OneSampleSample{}
SampleArySample16 dup ({})
; Pointers to the above
OnePtr
              word
                          OneSample
                                            ;A near pointer.
AryPtr
              dword
                          SampleAry
; Index into the array:
Index
                          8
              word
dseg
               ends
; The following program demonstrates how to access each of the above
; variables.
                          para public 'code'
cseg
               segment
                          cs:cseg, ds:dseg
               assume
Main
              proc
               mov
                          ax, dseg
                                            ;These statements are
provided by
                                            ; shell.asm to initialize
                          ds, ax
               mov
the
               mov
                          es, ax
                                            ; segment register.
; AryPtr^[Index] := OnePtr^
                          si, OnePtr
                                            ;Get pointer to OneSample
               mov
                                            ;Get pointer to array of
               les
                          bx, AryPtr
samples
              mov
                          ax, Index
                                            ;Need index*7
                          di, 7
              mov
                          di
               mul
                          di, ax
               mov
               mov
                          al, ds:[si].Sample.b
               mov
                          es:[bx][di].Sample.b, al
               mov
                          ax, ds:[si].Sample.w
              mov
                          es:[bx][di].Sample.w, ax
```

	mov	eax, ds:[si].Samp es:[bx][di].Sampl	
Quit:	mov int	ah, 4ch 21h	;Magic number for DOS ; to tell this program to quit.
Main	endp		1 5 1
cseg	ends		
sseg stk sseg	segment byte ends	para stack 'stack 1024 dup ("stack	
zzzzzzseg LastBytes zzzzzzseg	segment byte ends	para public `zzzz 16 dup (?)	zz'
	end	Main	

5.10 Programming Projects

- Program #1: Create a program with a single dimension array of structures. Place at least four fields (your choice) in the structure. Write a code segment to access element "i" ("i" being a word variable) in the array.
- □ Program #2: Write a program which copies the data from a 3x3 array and stores the data into a second 3x3 array. For the first 3x3 array, store the data in row major order. For the second 3x3 array, store the data in column major order. Use nine sequences of instructions which fetch the word at location (i,j) (i=0..2, j=0..2).
- □ Program #3: Rewrite the code sequence above just using MOV instructions. Read and write the array locations directly, do not perform the array address computations.
- Program #4: The PC's video display is a memory mapped I/O device. That is, the display adapter maps each character on the text display to a word in memory. The display is an 80x25 array of words declared as follows:

```
display:array[0..24,0..79] of word;
```

Display[0,0] corresponds to the upper left hand corner of the screen, display[0,79] is the upper right hand corner, display[24,0] is the lower left hand corner, and display[24,79] is the lower right hand corner of the display.

The L.O. byte of each word holds the ASCII code of the character to appear on the screen. The H.O. byte of each word contains the *attribute* byte (see "The PC Video Display" on page 1069 for more details on the attribute byte). The base address of this array is B000:0 for monochrome displays and B800:0 for color displays.

The diskette accompanying this lab manual contains a sample program named "PROJ4_4.ASM" that is supposed to clear the screen. It contains a main program that uses several instructions you probably haven't seen yet. These instructions essentially execute a for loop as follows:

```
for i:= 0 to 79 do
    for j := 0 to 24 do
        putscreen(i,j,value);
```

Inside this program you will find some comments that instruct you to supply the code that stores the value in AX to location display[i,j]. Modify this program as described in its comments and test the result.

Program #5: Proj5_4.asm on the diskette accompanying this lab manual is a maze generation program. It is complete except for two routines that access the MAZE array (maze:array[0..26, 0..81] of word;) and the screen array (screen:array[0..24, 0..79] of word;). You need to supply the code in the two procedures MazeAdrs and ScrnAdrs to compute the indices into these arrays. On entry to these two routines, dl contains the y coordinate (first index) and dh contains the second coordinate (second index). You code must perform the necessary array index computation and leave the final index value in the AX register. See the comments in the code for further details. Note: this program will only run properly on a color display.

5.11 Answers to Selected Exercises

3) Use the BYTE directive.

Examples:

```
ByteVar1 BYTE ?
CharVar BYTE ?
Boolean BYTE ?
```

Byte variables are useful for declaring small integer variables, boolean variables, character variables, and string variables

- 8) A near pointer is 16 bits long and can only point at data within a specific segment. A far pointer is 32 bits long and can point at any location in memory.
- 11) The following code examples present one possible solution to these problems

a)

```
mov ax, i ;i*4
mov bx, 4
mul bx
add ax, j ;i*4 + j
mov bx, ax
mov al, TD[bx] ;Fetch TD[i,j]
```

12) The following answers provide only one possible solution for each question, of many, to the questions.

a)

```
ebx, 0
                        ;Initialize H.O. word to zero
mov
mov
      ax, i
                  ;i*4
mov
      bx, 4
mul
      bx
      ax, j
                  ;i*4 + j
add
mov
      bx, ax
      al, TD[ebx*1]
                    ;Fetch TD[i,j]
mov
```

15)

```
Array word 0, 1, 2
word 3, 4, 5
word 6, 7, 8
```

	Variables and Data Structures