

Buffer Overflow Example


Slides done by Magnus Almgren


Source code of program example


```
#include <string.h>
void sub2(char *str) {
 char buf[8];
 strcpy(buf,str);
void sub1() {
 char str[] = "Code";
 sub2(str);
int main() {
 sub1();
 return 0;
```















```
bp = bfa0 9698
                                                                     9690
                               sp = bfa0 968c
                                                                                 8412
                               ip = 0804 83de
int main() {
 sub1();
              840d
 return 0;
             8412
                                                                     9680
void sub1() {
 char str[] = "Code";
                                                                     9670
 sub2(str);
                              When calling a function:
                              (0) Setup fcn parameters.
                              (1) Push ip of next instruction
                                                                     9660
void sub2(char *str) {
                              (2) Jump to new fcn
 char buf[8];
                              (3) Update bp
                              (4) Update sp
 strcpy(buf,str);
                              (5) Setup local vars.
                                                                     9650
```

```
bp = bfa0 9698
                                                                     9690
                               sp = bfa0 968c
                                                                                 8412
                               ip = 0804 83de
int main() {
 sub1();
              840d
 return 0;
             8412
                                                                     9680
void sub1() {
 char str[] = "Code";
                                                                     9670
 sub2(str);
                              When calling a function:
                              (0) Setup fcn parameters.
                              (1) Push ip of next instruction
                                                                     9660
void sub2(char *str) {
                              (2) Jump to new fcn
 char buf[8];
                              (3) Update bp
                              (4) Update sp
 strcpy(buf,str);
                              (5) Setup local vars.
                                                                     9650
```



```
bp = bfa0 9698
                                                                        9690
                                sp = bfa0 9688
                                                                                    8412
                                ip = 0804 83df
                                                                                bp<sup>0</sup> 9698
int main() {
 sub1();
              840d
 return 0; 0 8412
                                                                        9680
void sub1() {
 char str[] = "Code";
                                                                        9670
 sub2(str);
                               When calling a function:
                               (3) Update bp
                                    (1) Save old bp
                                                                        9660
void sub2(char *str) {
                                    (2) Setup new bp
 char buf[8];
                               (4) ...
 strcpy(buf,str);
                                                                        9650
```

```
bp = bfa0 9688
                                                                        9690
                                sp = bfa0 9688
                                                                                    8412
                                ip = 0804 83df
                                                                                bp<sup>0</sup> 9698
int main() {
 sub1();
              840d
 return 0; 0 8412
                                                                        9680
void sub1() {
 char str[] = "Code";
                                                                        9670
 sub2(str);
                               When calling a function:
                               (3) Update bp
                                    (1) Save old bp
                                                                        9660
void sub2(char *str) {
                                    (2) Setup new bp
 char buf[8];
                               (4) ...
 strcpy(buf,str);
                                                                        9650
```


```
bp = bfa0 9688
                                                                        9690
                                sp = bfa0 9688
                                                                                   8412
                                ip = 0804 83e1
                                                                               bp<sup>0</sup> 9698
int main() {
 sub1();
              840d
 return 0;
              8412
                                                                        9680
void sub1() {
 char str[] = "Code";
                                                                        9670
 sub2(str);
                               When calling a function:
                               (0) Setup fcn parameters.
                               (1) Push ip of next instruction
                                                                        9660
void sub2(char *str) {
                               (2) Jump to new fcn
 char buf[8];
                               (3) Update bp
                               (4) Update sp
 strcpy(buf,str);
                               (5) Setup local vars.
                                                                        9650
```

```
bp = bfa0 9688
                                                                       9690
                                sp = bfa0 9670
                                                                                   8412
                                ip = 0804 83e1
                                                                               bp<sup>0</sup> 9698
int main() {
 sub1();
              840d
 return 0;
             8412
                                                                       9680
void sub1() {
 char str[] = "Code";
                                                                       9670
 sub2(str);
                               When calling a function:
                               (0) Setup fcn parameters.
                               (1) Push ip of next instruction
                                                                       9660
void sub2(char *str) {
                               (2) Jump to new fcn
 char buf[8];
                               (3) Update bp
                               (4) Update sp
 strcpy(buf,str);
                               (5) Setup local vars.
                                                                       9650
```


```
bp = bfa0 9688
                                                                       9690
                                sp = bfa0 9670
                                                                                   8412
                                ip = 0804 83e1
                                                                               bp<sup>0</sup> 9698
int main() {
 sub1();
              840d
 return 0;
             8412
                                                                       9680
void sub1() {
 char str[] = "Code";
                                                                       9670
 sub2(str);
                               When calling a function:
                               (0) Setup fcn parameters.
                               (1) Push ip of next instruction
                                                                       9660
void sub2(char *str) {
                               (2) Jump to new fcn
 char buf[8];
                               (3) Update bp
                               (4) Update sp
 strcpy(buf,str);
                               (5) Setup local vars.
                                                                       9650
```

```
bp = bfa0 9688
                                                                       9690
                               sp = bfa0 9670
                                                                                   8412
                               ip = 0804 83e4
                                                                               bp<sup>0</sup> 9698
int main() {
                                       bfa0 9683
                               str
                                                                               0065646f
 sub1();
              840d
                                                                                \0 e d o
                              buf
 return 0;
             8412
                                                                               43 ed 6f f4
                                                                    → 9680
void sub1() {
 char str[] = "Code";
                                                                       9670
 sub2(str);
                              When calling a function:
                              (0) Setup fcn parameters.
                              (1) Push ip of next instruction
                                                                       9660
void sub2(char *str) {
                               (2) Jump to new fcn
 char buf[8];
                               (3) Update bp
                              (4) Update sp
 strcpy(buf,str);
                              (5) Setup local vars.
                                                                       9650
```

```
bp = bfa0 9688
                                                                          9690
                                 sp = bfa0 9670
                                                                                      8412
                                 ip = 0804 83ef
                                                                                  bp<sup>0</sup> 9698
int main() {
                                         bfa0 9683
                                str
                                                                                   0065646f
 sub1();
              840d
                                                                                  \0 e d o
43 ed 6f f4
                                buf
 return 0; (1)
              8412
                                                                          9680
void sub1() {
 char str[] = "Code";
                                                                          9670
sub2(str);
                                                                          9660
void sub2(char *str) {
 char buf[8];
 strcpy(buf,str);
                                                                          9650
```




```
bp = bfa0 9688
                                                                        9690
                                sp = bfa0 9670
                                                                                    8412
                                ip = 0804 83ef
                                                                                bp<sup>0</sup> 9698
int main() {
                                        bfa0 9683
                               str
                                                                                 0065646f
 sub1();
              840d
                                                                                 \0 e d o
                               buf
                                                                                              S
 return 0; (1)
             8412
                                                                                 43 ed 6f f4
                                                                        9680
                                                                                              u
                                                                                              b
void sub1() {
 char str[] = "Code";
                                                                        9670
sub2(str);
                                                                        9660
void sub2(char *str) {
 char buf[8];
 strcpy(buf,str);
                                                                        9650
```



```
void sub1() {
  char str[] = "Code";
  sub2(str);
}

  83fa
```


```
void sub2(char *str) {
  char buf[8];
  strcpy(buf,str);
}
```



```
void sub1() {
  char str[] = "Code";
  sub2(str);
}

  83fa
```

```
void sub2(char *str) {
  char buf[8];
  strcpy(buf,str);
}
```




```
int main() {
    sub1(); 840d
    return 0; 0 8412
}
```

```
void sub1() {
  char str[] = "Code";
  sub2(str);
}

  83fa
```

```
void sub2(char *str) {
    char buf[8];
    strcpy(buf,str);
```




```
int main() {
    sub1(); 840d
    return 0; 0 8412
}
```

```
void sub1() {
  char str[] = "Code";
  sub2(str);
}


  83fa
```


```
void sub2(char *str) {
  char buf[8];
  strcpy(buf,str);
}
```




What if the string **str** was longer than 5 characters? (4 characters + ending '\0'-character)

Let's back up a few steps ...







The return address has been overwritten. In this example, probably an invalid address so the program will crash.

