

SORTVIEW

Collector 1.0.2

Customer Installation Guide

Windows installation for Tech Logic AMH data collection

Release	1.0.2
Package	SortViewCollector-1.0.2.zip
SHA-256	28C2C4885F21B16B80920B8B7D721858EB36A6B4AE9EC9197D5FF6E465540A44
Architecture	Windows frozen runtime; HTTPS-only Collector

Purpose

Use this guide to install and activate SortView Collector on the Windows computer that receives your Tech Logic Automated Materials Handling (AMH) log files. The Collector sends supported event data to SortView over HTTPS. It does not require Python, Git, PostgreSQL drivers, or direct database access.

Keep your Collector API token private. Never include it in screenshots, tickets, email, or ordinary documentation.

1. Before you begin

You will need the following before starting the installation:

- Windows administrator access on the Collector computer.
- The complete SortViewCollector-1.0.2.zip package.
- Your SortView Operational Customer ID and Operational Branch ID.
- Your SortView API URL.
- Your private SortView Collector API token.
- The full local or network paths to the Tech Logic Checkins, Rejects, and ACS Log source files.

Important

Do not guess Operational Customer ID, Operational Branch ID, API URL, or source paths. Use the values supplied for your library. These are Collector operational identifiers and may differ from administrative IDs shown elsewhere. A token is scoped to one operational customer and branch, and the preflight will reject a mismatched token.

Recommended onboarding worksheet

Value	Customer-specific setting
Operational Customer ID	
Operational Branch ID	
API URL	
Checkins path	
Rejects path	
ACS Log path	

2. Extract the release package

Copy the ZIP to the Collector computer and extract the entire archive. Depending on the extraction tool, the result may contain an additional nested folder.

Package root

The package root is the folder that directly contains install.ps1, MANIFEST.json, runtime, and tools. Run all package commands from that folder.

```
Get-ChildItem -Path . -Filter "install.ps1" -Recurse | Select-Object FullName
```

Change into the directory returned by that command. Example:

```
Set-Location "C:\Users\<username>\Downloads\SortViewCollector-1.0.2\SortViewCollector-1.0.2"
```

3. Open an elevated PowerShell session

Open Windows PowerShell using Run as administrator, then change to the package root.

```
net session
```

If the shell is elevated, the command should not return an Access Denied error. The installer intentionally refuses to run without administrator rights.

Execution policy

If scripts are blocked, you may attempt a process-only execution-policy change:

```
Set-ExecutionPolicy -Scope Process Bypass -Force
```

A domain Group Policy may override that request. If the effective policy remains RemoteSigned, continue and try the installer normally. Do not change organization-wide policy unless directed by your IT administrator.

4. Install the Collector

Enter your customer-specific settings as PowerShell variables. Replace only the values on the right side of the equals signs.

```
$CustomerId = 123
$BranchId = 4
$ApiUrl = "https://your-sortview-api.example"
$CheckinsPath = "C:\Path\To\Checkins.txt"
$RejectsPath = "C:\Path\To\Rejects.txt"
$AcsPath = "C:\Path\To\ACS Log.txt"
```

PowerShell note

Do not type placeholders such as <CUSTOMER_ID> directly into PowerShell. Angle brackets are parsed as syntax. Use actual values or the variables shown above.

Run the installer:

```
.\install.ps1 -CustomerId $CustomerId -BranchId $BranchId -ApiUrl $ApiUrl -CheckinsPath $CheckinsPath -RejectsPath $RejectsPath -AcsPath $AcsPath
```

A successful install reports that the bundle is FROZEN, verifies the manifest, copies the runtime, creates the data directories, and writes the configuration. The expected installed locations are:

Component	Location
Application runtime	C:\SortView\Collector
Configuration / state / logs	C:\ProgramData\SortViewCollector

5. Set the Collector API token

From the package root, run:

```
.\tools\set-api-token.ps1
```

Paste the private token when prompted. Input is hidden. The script stores the token as a Windows Machine-scope environment variable; it is not written to collector_config.json.

Security

Do not place the raw token in commands, scripts, email, screenshots, tickets, or the configuration file. If a token is exposed, request a replacement and revoke the exposed token.

6. Run guided setup

```
.\tools\finish-install.ps1 -InstallRoot "C:\SortView\Collector" -ConfigPath "C:\ProgramData\SortViewCollector\config\collector_config.json"
```

If prompted to keep or replace an existing Machine-scope token and the correct token was just set, choose K to keep it.

The guided setup performs these operations in order:

1. Read-only install/config checks.
2. Interactive Collector preflight.
3. SYSTEM-context preflight.
4. Starting-cursor bootstrap for all configured sources.
5. Scheduled Task registration in a disabled state.

Stop condition

Do not enable the Scheduled Task unless both preflights pass and bootstrap completes. The guided script is designed to stop at the first problem before it can schedule normal collection.

7. Review preflight results

A healthy installation reports OVERALL: PASS for the interactive preflight and SYSTEM CONTEXT VALIDATION: PASS for the SYSTEM-context preflight.

Check	Expected result
config_loads	PASS
source_paths_exist	PASS
source_paths_readable	PASS
state_dir_writable / status_dir_writable / log_dir_writable	PASS
api_token_visible	PASS
dns_resolution / https_tls_connection	PASS
api_authentication	PASS
token_scope_matches	PASS
no_direct_database_dependency	PASS
collector_runtime_imports	PASS

If guided setup stops

Read the [FAIL] line, correct that specific problem, and rerun finish-install.ps1. Do not reinstall unless support specifically asks you to.

Validated recovery behavior

If configured source files are missing, guided setup stops during preflight, leaves the token in place, and does not create bootstrap state or the Scheduled Task. After correcting the source paths/files, rerunning finish-install.ps1 continues safely.

8. Enable the Collector

After both preflights pass, bootstrap completes, and the Scheduled Task is registered Disabled, enable normal collection:

```
Enable-ScheduledTask -TaskName "SortView Collector"
```

Verify the task is ready:

```
Get-ScheduledTask -TaskName "SortView Collector" | Select-Object TaskName, State
```

The task runs as SYSTEM every 15 minutes. While disabled, Windows will not allow Start-ScheduledTask. Enable it first.

9. Run and verify the first collection

Optionally trigger the first run immediately instead of waiting for the next scheduled trigger:

```
Start-ScheduledTask -TaskName "SortView Collector"
```

After several seconds, inspect Task Scheduler status:

```
Get-ScheduledTaskInfo -TaskName "SortView Collector" | Select-Object LastRunTime,
LastTaskResult, NextRunTime
```

Success criterion

LastTaskResult = 0 indicates the scheduled process completed successfully. For a production installation, leave the task enabled after validation.

Inspect the Collector status file:

```
Get-Content "C:\ProgramData\SortViewCollector\data\status.json"
```

A successful run may show uploaded rows, or status "completed_no_new_rows" when no new events were available. Normally, sources_missing, sources_rotated, and sources_truncated should be empty.

10. Operational reference

Item	Value
Scheduled Task	SortView Collector
Runs as	SYSTEM
Normal cadence	Every 15 minutes
Overlap policy	IgnoreNew
Restart on failure	3 attempts, 5 minutes apart
Execution limit	1 hour
Runtime	C:\SortView\Collector
Config	C:\ProgramData\SortViewCollector\config\collector_config.json
State / status	C:\ProgramData\SortViewCollector\data
Logs	C:\ProgramData\SortViewCollector\logs

11. Troubleshooting and support

If installation or preflight fails, capture the following before contacting support:

- The exact step that failed.
- The complete error message or [FAIL] line.
- Whether interactive preflight passed.
- Whether SYSTEM-context preflight passed.

- Current Scheduled Task state.
- Contents of status.json, if present.
- Relevant files from C:\ProgramData\SortViewCollector\logs.

Do not send secrets

Never send the raw SORTVIEW_API_TOKEN, database credentials, or other secrets in screenshots or support messages.

Authorization failures

If status.json or Collector output reports HTTP 403 with "Agent is not currently authorized to upload data", do not reinstall the Collector, guess new IDs, or replace the token unless SortView support instructs you to. The library or branch may be suspended/inactive, or its operational mapping may require review. Capture the error and contact SortView support without sending the raw API token.

Useful read-only checks

```
Get-ScheduledTask -TaskName "SortView Collector" | Select-Object TaskName, State
Get-ScheduledTaskInfo -TaskName "SortView Collector" | Select-Object LastRunTime,
LastTaskResult, NextRunTime
Get-Content "C:\ProgramData\SortViewCollector\data\status.json"
```

12. Uninstalling

Run the shipped uninstaller from the extracted package root:

```
.\tools\uninstall.ps1
```

By default, the uninstaller removes the Scheduled Task and application runtime but preserves configuration/state/logs and the Machine-scope API token. This supports troubleshooting or a reinstall.

Permanent removal

Use -PurgeData only when you intentionally want to permanently delete SortView configuration, state, status, and logs. The API token must still be removed separately if the machine is being decommissioned.

```
.\tools\uninstall.ps1 -PurgeData
[Environment]::SetEnvironmentVariable("SORTVIEW_API_TOKEN", $null, "Machine")
```

13. Installation completion checklist

- ☐ Package manifest verified successfully.
- ☐ Collector installed to C:\SortView\Collector.
- ☐ Operational Customer ID / Operational Branch ID configuration reviewed.
- ☐ Private Machine-scope API token set.
- ☐ Interactive preflight: PASS.
- ☐ SYSTEM-context preflight: PASS.
- ☐ Starting cursor bootstrapped for all configured sources.
- ☐ Scheduled Task registered initially Disabled.
- ☐ Scheduled Task enabled only after validation.
- ☐ First scheduled/manual run returned LastTaskResult = 0.

- ☐ status.json reviewed; no unexpected missing/rotated/truncated sources.

Installation complete

SortView Collector should remain enabled on a production machine so it can run every 15 minutes.