

CUSTOMER USER MANUAL

From registration to final settlement

Product	HammerTrack Pro Auction Management Software
Manual version	0.7.60
Applies to	Retail Auction and optional Wholesale Auction module
Website	https://hammertrackpro.com

Purpose
This manual is written for auction owners, clerks, cashiers, and setup staff who have never used HammerTrack Pro. Follow the chapters in order when preparing your first auction.

Updated September 30, 2026. Screens show the current application with fictional training data. Sample percentages and amounts are examples; use your saved auction terms.

Copyright 2026 HammerTrack Pro. Customer training and operational reference.

Table of Contents

CUSTOMER USER MANUAL 1

From registration to final settlement . . . 1

1. Read This First 6

What the software includes . . . 6

Current access model . . . 6

2. Installing HammerTrack Pro 7

Before installation . . . 7

Install the program . . . 7

Upgrade an existing installation . . . 7

3. First-Time Setup and Licensing 8

Choose the workstation role . . . 8

Activate the main software license . . . 8

4. Dashboard and Navigation 9

Dashboard Quick Actions . . . 9

Dashboard tabs . . . 9

5. Create and Configure an Auction 10

Create a new auction . . . 10

Duplicate a prior auction . . . 10

Close an auction . . . 10

6. Seller Management 11

Add a seller . . . 11

Seller and bidder number linking . . . 11

Commission priority . . . 11

7. Register Bidders and Buyers 12

Register a bidder . . . 12

Scan a driver license . . . 12

Tax exemption at checkout . . . 12

Driver's license scanner: connect and scan . . . 13

Scanner troubleshooting . . . 14

8. Prepare for Auction Day 15

Pre-auction checklist . . . 15
Network Information . . . 15
Enter and maintain lots before bidding . . . 16

9. Retail Auction - Standard Sale 17

Fast keyboard workflow . . . 17
Verify the sale . . . 17

10. Retail Pass-Out and Lot Controls 18

Use Pass-Out for multiple buyers on one lot . . . 18
Other live controls . . . 18

11. Wholesale Module Activation 19

Activate Wholesale Auction . . . 19

12. Wholesale Auction - Standard Sale 20

Standard wholesale sale . . . 20
Standard example . . . 20

13. Wholesale Pass-Out Mode 21

Meaning of the fields . . . 21
Fast Pass-Out workflow . . . 22
Calculation examples . . . 22
Search a sold item and add another buyer . . . 23

14. Correcting a Sale 24

Correct from the live history . . . 24
Undo during live entry . . . 24
Correct Sale from Cashier . . . 24

15. Buyer Checkout 25

Find and review a buyer . . . 25
Record a cash payment . . . 25
Record check or card . . . 25
Find a buyer without a bidder number . . . 26

16. Split Payments, Refunds, and Mistakes 27

Split payment . . . 27
Refund a buyer . . . 27
Unpaid Buyers . . . 27

17. Buyer Invoices, Receipts, and Bidder Cards 28

Print an invoice . . . 28

Bidder cards . . . 28

Tax-exempt invoice check . . . 28

Set up the printer on each computer . . . 29

18. Seller Settlement 30

View seller sales . . . 30

Record a seller payout . . . 30

Seller print options . . . 30

19. End-of-Night Report 31

Financial summary . . . 31

Record staff or operating payments . . . 31

Print the report . . . 31

20. Reports Available in Version 0.7.60 32

21. Backups and Data Protection 33

Create a backup . . . 33

Recommended schedule . . . 33

What an upgrade preserves . . . 33

22. Administration and Settings 34

Company and auction account information . . . 34

Clerk and cashier access . . . 34

Auction permissions . . . 34

License management . . . 34

23. Troubleshooting 35

24. Frequently Asked Questions 36

25. Technical Support and Update Practice 37

Before requesting support . . . 37

Keeping this manual current . . . 37

26. Software License Agreement 38

1. Licensed Computers . . . 38

2. Nature Of License - Software Is Licensed, Not Sold . . . 38

3. License Ownership And Non-Transferability . . . 38

4. No Transfer Through Equipment Or Media 38
5. No Resale, Distribution, Or Sharing 39
6. Support 39
7. Annual Updates 39
8. Custom Updates And Requested Features 39
9. Software Use And Restrictions 39
10. License Suspension Or Termination 39
11. No Guarantee Of Future Features 39
12. Entire Agreement 39
13. Acknowledgment And Acceptance 40

1. Read This First

HammerTrack Pro runs live auctions from a Windows host computer and can connect a second cashier computer over a private local network. The host owns the auction database. The cashier communicates through HammerTrack Pro and must never open the database file directly.

What the software includes

- Auction setup and duplication
- Global seller and buyer records with auction-specific bidder numbers
- Retail and optional licensed Wholesale live-clerk screens
- Buyer invoices, cash/check/card payments, split payments, refunds, and audited sale corrections
- Seller settlements and item summaries
- Bidder cards, unpaid-buyer review, backups, and End-of-Night reporting

Current access model

Version 0.7.60 does not provide individual user accounts, passwords, or configurable permission roles. Access is controlled by the Windows computer account and the workstation role selected during setup: Live Auction Host or Cashier Workstation. Only trusted staff should have Windows access to either computer.

Protect auction data
Keep the host database on the host computer. Do not place it on a shared, mapped, cloud-synchronized, or network drive. Use HammerTrack Pro Backup Database before and after every auction.

2. Installing HammerTrack Pro

Before installation

- Use a supported 64-bit Windows computer.
- Have Windows administrator permission available.
- For a two-computer setup, connect both computers to the same trusted private router or LAN.
- Keep the signed installer and issued .htplicense file available.

Install the program

Step 1: Copy HammerTrackPro-0.7.60-x64-signed.msi to the computer.

Step 2: Double-click the installer. Approve the Windows administrator prompt.

Step 3: Read and accept the license agreement.

Step 4: Choose the installation folder if prompted; the recommended folder is under Program Files.

Step 5: Finish installation, then open HammerTrack Pro from the Desktop or Start Menu shortcut.

Self-signed installer
If Windows does not yet trust the local HammerTrack Pro certificate, verify that the installer came directly from your HammerTrack Pro provider before continuing. The public certificate may need to be trusted on each computer.

Upgrade an existing installation

Run the newer MSI without uninstalling the older version. The upgrade replaces program files and preserves the database, settings, backups, logs, licenses, and module activations under ProgramData.

3. First-Time Setup and Licensing

Choose the workstation role

Live Auction Host: stores the local database, runs Retail/Wholesale clerk entry, and hosts the secure cashier connection.
Cashier Workstation: connects to the host and runs buyer checkout and seller settlement. It does not open a local shared database.

Activate the main software license




Figure 3-1. Main license activation: copy the Machine ID, then import the issued license.

Step 1: Click Copy Machine ID.

Step 2: Send the Machine ID to the HammerTrack Pro license issuer. For two computers, send both IDs together.

Step 3: Save the issued .htplicense file on the computer.

Step 4: Click Import License, select the file, and confirm the licensed customer name.

Step 5: Repeat the import on every Machine ID included in that license.

> Keep the private key private
> Customers receive only issued license or activation files. Never copy, email, or package the private .pem issuer key.

4. Dashboard and Navigation




Figure 4-1. Dashboard, current-auction settings, and Quick Actions.

Dashboard Quick Actions

Action	Use
Register Bidder	Open buyer registration.
Add Lot	Open full lot entry.
Backup Database	Create a recoverable copy of host data.
Refresh Dashboard	Reload current-auction counts and totals.
Retail Auction	Open standard live-clerk entry.
Wholesale Auction	Open or activate the optional Wholesale module.
Manage Sellers	Create, find, edit, and activate sellers.
Auction Setup	Create, select, duplicate, or close an auction.
Cashier	Open checkout and seller settlement.
Help / User Manual	Open this PDF without internet access.

Dashboard tabs

Dashboard shows the current auction and quick actions. Bidders manages current-auction registrations and global buyer identity details. Lots provides full lot entry and editing. Operational totals and lists always follow the selected current auction. Printer Setup chooses the printer used by this computer.

5. Create and Configure an Auction




Figure 5-1. Auction directory on the left and selected auction details on the right.

Create a new auction

Step 1: From the Dashboard, click Auction Setup.

Step 2: Click New Auction.

Step 3: Complete Auction Number, Auction Name, date/time, location, staff, and company contact information.

Step 4: Set Buyer Premium %, Seller Commission %, Sales Tax %, Sales Tax Basis, and card-processing fee terms.

Step 5: Add invoice and receipt footer text if desired.

Step 6: Click Save Auction, select it in Saved Auctions, then click Load Selected.

> Commercial terms
> Premium, sales tax, seller commission, and card fees come from the selected Auction record. Confirm these values before the first sale. Changing terms after payments or payouts begin can create confusing historical results.

Duplicate a prior auction

Step 1: Select the prior auction.

Step 2: Choose whether to copy sellers and/or registered bidders.

Step 3: Click Duplicate.

Step 4: Edit the new Auction Number, name, date, and other details.

Step 5: Save and load the new auction. Sales and payment history are not copied.

Close an auction

Use Close Auction only after live selling and buyer checkout are complete. Closed auctions remain available for invoice review and seller settlement, but new buyer payments are blocked.

6. Seller Management




Figure 6-1. Seller details and actions on the left; searchable directory on the right.

Add a seller

Step 1: Click Manage Sellers, then Add Seller.

Step 2: Enter a unique Seller Number and the seller or business name.

Step 3: Complete optional contact, tax, commission, payout, and notes fields.

Step 4: Confirm Active is enabled, then click Save Seller.

Seller and bidder number linking

When a seller is saved, HammerTrack Pro creates or links the same-number buyer identity for that auction. If the number already belongs to a different buyer, the save is stopped and you must choose another Seller Number. A seller who buys items can have purchases deducted from settlement proceeds through that durable link.

Commission priority

Settlement calculations use a positive seller commission override first, then the seller default commission, then the selected auction default. Review the effective percentage before recording payout.

7. Register Bidders and Buyers




Figure 7-1. Buyer details on the left and current-auction registrations on the right.

Register a bidder

Step 1: Open the Bidders tab or click Register Bidder.

Step 2: Enter an unused Bidder Number for the selected auction.

Step 3: Select an Existing Buyer when the person is already in the global buyer list, or leave Create New Buyer selected.

Step 4: Enter optional name, address, phone, email, and driver license information.

Step 5: For a tax-exempt buyer, enter Resale License / Tax Exemption Number, State, and select Tax Exempt.

Step 6: Click Save.

> Bidder numbers are auction-specific
> The same person may have a different bidder number in another auction. HammerTrack keeps one durable Buyer identity and a separate registration for each auction.

Scan a driver license

Click Scan Driver's License on the Bidders screen or in Cashier > Add Buyer. Older and newer cards now use one shared handheld scanner window. Follow the illustrated instructions on the next page.

Tax exemption at checkout

When Tax Exempt is saved on the buyer identity, HammerTrack automatically calculates zero sales tax for that buyer. Other buyers use the selected auction sales-tax rate and basis.

Driver's license scanner: connect and scan




Figure 7-2. The shared handheld scanner window waits for a scan and keeps the barcode hidden.

Step 1: Connect a PDF417-capable NETUM or Zebra/Symbol scanner in USB HID keyboard mode. A compatible USB cable, paired receiver, or Bluetooth keyboard connection supplies keystrokes to this PC. A scanner that reads only one-dimensional barcodes cannot read the license PDF417 barcode.

Step 2: Enable PDF417 on the scanner using its manufacturer setup guide. For a NETUM NT-1228BL and reflective cards, select PDF417 > Regular/Inverse Decode > Decode Both (older guides call this Read Normal Phase / Phase Reversal).

Step 3: Open buyer registration, enter the current-auction Bidder Number, and click Scan Driver's License. Keep this window active.

Step 4: Aim at the PDF417 barcode on the back of the license and trigger the scanner. Adjust distance and angle if necessary. A beep alone does not confirm that HammerTrack received the data.

Step 5: Watch the received-character status. HammerTrack parses after transmission pauses and allows extra time for slower transmissions. Waiting before a scan does not cause an inactivity error.

Step 6: After a recognized scan closes the window, review first/last name, address, city, state, ZIP, and license number. Correct any missing or inaccurate fields, complete other optional details, then Save the buyer. Scanning alone does not save a registration.

> Privacy and manual fallback
> Raw barcode text is hidden and discarded after parsing. Only reviewed buyer fields are saved. No camera is needed. If a card cannot be read, Cancel and type the optional details manually; the bidder number is still required.

Scanner troubleshooting

What you see	Next action
No received characters	Keep the scanner window active. Check power, USB/receiver/Bluetooth pairing, USB HID keyboard mode, and PDF417 support. Scan again.
Characters arrive but the scan is rejected	Click Reset / Scan Again and scan the complete barcode. Confirm the scanner is sending the license data without a custom prefix or formatting rule that removes fields.
Reflective or newer card will not decode	For NT-1228BL, enable regular and inverse PDF417 decoding. Reduce glare and vary angle/distance. Other scanner models use their own manufacturer settings.
Wrong or incomplete details	Review and correct the fields manually before saving. Do not assume a successful beep guarantees correct identity data.
Need another attempt	Use Reset / Scan Again. Cancel returns to registration so you can enter details manually.

One scanner action in this version
Older manuals referred to Scan ID and Scan New ID. Version 0.7.59 replaces both with Scan Driver's License. Use the same button for older and newer licenses.

8. Prepare for Auction Day

Pre-auction checklist

- Load the correct auction and verify its number, name, date, location, and status.
- Verify premium, tax basis/rate, card percentage/fixed fee, and seller commission.
- Register sellers and bidders; confirm tax-exempt records.
- Print bidder cards if used.
- Test the scanner, printer, and card terminal. HammerTrack records payments but does not directly process a bank card.
- On two computers, verify the Cashier displays Connected to auction host.
- Create and safely retain a database backup.
- Perform one sample lot, invoice, and print preview before bidders arrive.

Network Information

On the host, open Network Information. The cashier setup uses the host address, pairing key, and certificate fingerprint. If the computer-name address fails, use the Alternate IP shown by the host. Never bypass a fingerprint mismatch.

Enter and maintain lots before bidding




Figure 8-1. The Lots tab provides full lot details and the current-auction lot list.

Step 1: Load the correct auction, then click Add Lot on the Dashboard or open the Lots tab.

Step 2: Choose New for a new record. Enter a unique Lot Number and a clear Description.

Step 3: Choose the Seller by number/name and complete the relevant optional lot details. Save the record.

Step 4: To review or edit a prepared lot, select it from the current-auction list, change its details, and Save.

Step 5: Use the live screen's Quick Add Seller Number and Lot Description when creating lots as bidding proceeds. It assigns the next current-auction lot number.

> Sold items and history
> Use the audited sale-correction workflow for a wrong recorded buyer, quantity, or hammer price. Editing a lot description is not a substitute for correcting a financial transaction.

9. Retail Auction - Standard Sale




Figure 9-1. Retail entry is on the left; the right-side history shows Retail sales throughout the current auction.

Fast keyboard workflow

Step 1: Enter the Seller Number and press Tab.

Step 2: Enter the Lot Description and click Create Lot or press Enter in the description.

Step 3: Hammer Price receives focus with 0.00 selected. Type the per-item hammer price.

Step 4: Press Tab. Bidder Number receives focus with 0 selected. Type the bidder number.

Step 5: Press Tab. Quantity receives focus with 1 selected. Type another quantity or leave 1.

Step 6: Press Enter to record the sale.

> Price is per item
> Retail total equals Hammer Price Each x Quantity. Example: 6 items at $5 each records a $30 hammer total.

Verify the sale

The right-side sale history stays available as you change lots. Scroll to review current-auction Retail transactions, including time, lot, buyer number/name, quantity, price, and total. Select or double-click a transaction to open its audited correction workflow. Use Undo Last Buyer only for the most recent eligible unpaid sale and confirm the prompt.

10. Retail Pass-Out and Lot Controls

Use Pass-Out for multiple buyers on one lot

Step 1: Create the lot and enter Hammer Price Each.

Step 2: Select PASS-OUT MODE.

Step 3: Seller, lot, description, and hammer price lock.

Step 4: Enter Bidder Number, press Tab, enter Quantity, and press Enter.

Step 5: Repeat for every buyer. After each record, focus returns to Bidder Number.

Step 6: Click Close Lot when all buyers are recorded.

Other live controls

Control	Behavior
Pass Item / Next (F4)	Marks an unsold item Passed and advances.
Close Lot (F12)	Closes the current lot deliberately.
Undo Last Buyer (F8)	Removes only the newest eligible unpaid sale after confirmation.
Fullscreen (F11)	Enters/exits fullscreen; Esc also exits fullscreen.
Queued Next Lot	Lets the clerk choose a specific next lot.
Auctioneer Notes	Stores current-lot notes.

Do not advance active Pass-Out accidentally
In Retail Pass-Out, create/advance actions are blocked until Close Lot. This protects the locked lot and price while multiple buyers are entered.

11. Wholesale Module Activation




Figure 11-1. Copy Machine ID, obtain the add-on key, then paste the complete key and activate.

Activate Wholesale Auction

Step 1: Click Wholesale Auction on the Dashboard. The button remains visible even when locked.

Step 2: Copy the Machine ID from the activation window and send it to the license issuer.

Step 3: The issuer creates a Wholesale activation key for the authorized Machine ID or IDs.

Step 4: Open the issued text file and copy the entire key.

Step 5: Paste it into the activation box and click Activate.

Step 6: After successful activation, Wholesale Auction opens and remains available offline on that computer.

> Optional add-on
> Wholesale activation is separate from the main software license. Use Copy Machine ID and request the add-on key from your provider. Replacing a PC requires a key authorized for its Machine ID. Operators do not need the private license-issuing utility.

12. Wholesale Auction - Standard Sale




Figure 12-1. Wholesale uses its own current-auction transaction history on the right.

Standard wholesale sale

Step 1: Enter Seller Number and Lot Description, then create the lot.

Step 2: Enter Hammer Price Each.

Step 3: Enter Bidder Number.

Step 4: Enter Quantity, meaning total items purchased in this standard sale.

Step 5: Leave Pass-Out off. Deals remains 1.

Step 6: Press Enter to record the buyer.

Standard example

Value	Example
Description	Case of glassware
Hammer Price Each	$5.00
Quantity	24
Deals	1
Total Quantity	24
Sale Total	$120.00

13. Wholesale Pass-Out Mode




Figure 13-1. Pass-Out locks price and quantity per deal; enter each buyer and Deals.

Meaning of the fields

Field	Wholesale Pass-Out meaning
Hammer Price Each	Price for one individual item, not the whole deal.
Quantity	Number of items inside one deal; locks when Pass-Out starts.
Deals	Number of identical deals purchased by the current bidder.
Total Quantity	Quantity per Deal x Deals.
Sale Total	Hammer Price Each x Total Quantity.

Fast Pass-Out workflow

Step 1: Create the wholesale lot.

Step 2: Enter Hammer Price Each and the Quantity per Deal.

Step 3: Select PASS-OUT MODE. Seller, lot, description, price, and quantity per deal lock.

Step 4: The cursor starts at Bidder Number. Type the bidder number.

Step 5: Press Tab to move to Deals. Type deals purchased.

Step 6: Press Enter. HammerTrack records that buyer and returns immediately to Bidder Number.

Step 7: Repeat for each buyer.

Step 8: Click Close Lot when the lot is finished. Then enter the next seller and description and create the next wholesale lot.

Calculation examples

Price Each	Qty / Deal	Deals	Total Qty	Sale Total
$5.00	4	6	24	$120.00
$2.50	12	3	36	$90.00
$10.00	1	8	8	$80.00

Separate transaction per bidder
Every Pass-Out buyer is stored as an individual transaction with lot, bidder, price each, quantity per deal, deals, total quantity, and sale total. Do not combine different bidders into one entry.

Search a sold item and add another buyer




Figure 13-2. Search Sold Items retains the selected price and adds a separate purchase.

Step 1: Keep the auction open, even if bidding has finished. From the Retail or Wholesale clerk screen, click SEARCH SOLD ITEMS below the sale history.

Step 2: Type a description such as towels or an exact lot number, then click Search or press Enter. Blank search shows recent items; narrow the search if 100 matches are shown.

Step 3: Select the correct lot, seller, and price. Different recorded prices or deal sizes appear as separate choices. Confirm there is additional stock available.

Step 4: Enter the new Bidder Number. Enter Quantity for Retail, or Deals for Wholesale. The original price each stays locked; Wholesale also retains the original items per deal.

Step 5: Check the hammer total, then click Add Buyer at This Price or press Enter from the entry fields. The window closes after recording one purchase.

> Original buyers keep their purchases
> This adds another sale; it does not move the original purchase. Example: towels sold at $5 each; a new buyer takes 3, adding $15 hammer plus that auction's applicable premium and tax. A previously paid buyer will owe a new balance. Formally closed auctions remain locked.

14. Correcting a Sale

Correct from the live history

Step 1: In Retail or Wholesale, find the transaction in the right-side current-auction history.

Step 2: Select or double-click the row to open the correction window.

Step 3: Verify the lot and buyer. Enter a reason and correct the bidder, quantity, price, or Wholesale deal values as needed.

Step 4: Confirm the correction and review the revised transaction and invoice totals. Original sales remain in the audit history.

Undo during live entry

If the newest sale is wrong and has not been paid, choose Undo Last Buyer (F8), confirm the displayed transaction, and re-enter it correctly. Only the most recent eligible sale can be undone.

Correct Sale from Cashier

Step 1: Open Cashier and look up the buyer currently assigned to the sale.

Step 2: Select the wrong purchase row.

Step 3: Click Correct Sale.

Step 4: Enter the required reason.

Step 5: Choose to remove the sale or replace bidder, quantity, and/or price.

Step 6: Confirm the audited correction.

Paid-sale protection
A paid sale must be refunded sufficiently before it can be reduced, removed, or moved. The original sale is retained as voided history and the replacement is linked for audit.

15. Buyer Checkout




Figure 15-1. Buyer actions above the invoice, payment controls below it, and seller settlement at the bottom.

Find and review a buyer

Step 1: Enter the current auction Bidder Number.

Step 2: Click Lookup Buyer.

Step 3: Confirm the buyer name, invoice status, hammer total, premium, tax, card fee, paid amount, and balance.

Step 4: Review Purchases, Payment History, Pending Split Payments, and Refund History tabs.

Record a cash payment

Step 1: Select Cash. Invoice Amount automatically fills the unpaid balance.

Step 2: Enter Cash Tendered. Verify Change Due.

Step 3: Click Add Payment.

Step 4: Review the pending line, then click Record Payments.

Step 5: Return the displayed change and print the invoice.

Record check or card

For Check, enter the applied invoice amount and a reference when needed. For Card, HammerTrack fills the unpaid base amount and previews the current-auction percentage plus fixed processing fee. Process the displayed total on the external card terminal, add the payment, then record it.

> Card amount rule
> Enter the invoice balance before card fee. HammerTrack adds the configured card fee to the charge and printed invoice. Do not manually add the fee into Invoice Amount.

Find a buyer without a bidder number




Figure 15-2. Search Buyers finds people registered in the current auction.

Step 1: Click Search Buyers in Cashier. You can also search from Bidder Cards.

Step 2: Enter a bidder number, buyer name, or driver's-license number. The list narrows to matching current-auction registrations.

Step 3: Select the correct person and click Use Selected Buyer, or double-click the result.

Step 4: Confirm the buyer and invoice before recording payments or printing.

> No match?
> Check the current auction and spelling. An existing global Buyer must still be registered in this auction. Do not create a duplicate identity just because the buyer has no registration here.

Cashier action rows can scroll horizontally. If an action is off-screen, use the row scrollbar or enlarge the window. Payment actions remain in their own row: Add Payment, Remove Selected, and Record Payments.

16. Split Payments, Refunds, and Mistakes

Split payment

Step 1: Select the first method and enter only that portion.

Step 2: Click Add Payment.

Step 3: Select the second method. HammerTrack suggests the remaining base balance.

Step 4: Add each portion and review Pending Split Payments.

Step 5: Remove any incorrect pending row before recording.

Step 6: Click Record Payments once all portions are correct.

Refund a buyer

Step 1: Look up the paid buyer.

Step 2: Click Refund.

Step 3: Select the original payment.

Step 4: Enter the refundable purchase amount and a required reason.

Step 5: Enter an optional reference and confirm.

Refunds are append-only records. Card-processing fees are retained and cannot be included in the purchase refund.

Unpaid Buyers

Click Unpaid Buyers to reload a current-auction list of bidder number, name, invoice total, paid amount, and remaining balance. An all-paid message appears when no balances remain.

17. Buyer Invoices, Receipts, and Bidder Cards

Print an invoice

Step 1: Look up the bidder.

Step 2: Confirm purchases and payments.

Step 3: Click Print Invoice.

Step 4: Review the professional preview, auction-company information, bidder information, item quantities/prices/totals, premium, tax, card fees, payments, refunds, status, and balance.

Step 5: Print from the preview toolbar.

Bidder cards

Step 1: Click Bidder Cards.

Step 2: Choose a current-auction bidder.

Step 3: Click Print Preview.

Step 4: Confirm landscape orientation, complete bidder number, divider, and auction-company name.

Step 5: Print at 100% scale.

Tax-exempt invoice check

A buyer marked Tax Exempt should show $0.00 sales tax. If tax appears, stop checkout, open bidder registration, correct the buyer record, save it, and look up the invoice again.

Set up the printer on each computer




Figure 17-1. Printer Setup saves a local workstation preference. The pictured printer is a training example.

Step 1: Install the printer in Windows and confirm it is available on this computer.

Step 2: Open Printer Setup from the Dashboard or Cashier.

Step 3: Select the intended printer and click Save Printer.

Step 4: Click Print Test Page and check that it reaches the correct printer. This also saves the selected printer.

Step 5: Repeat on the cashier computer if used; each computer keeps its own choice.

Step 6: Before printing invoices, bidder cards, seller statements, item summaries, or End-of-Night reports, review the preview and paper orientation.

A saved printer is missing
HammerTrack reports an error rather than silently choosing another printer. Reconnect or reinstall it, or reopen Printer Setup and save another installed printer. If no printers are listed, install one in Windows and reopen this window.

18. Seller Settlement

View seller sales

Step 1: At the bottom of Cashier, enter Seller Number.

Step 2: Click Lookup Seller.

Step 3: Review the settlement heading, Seller Lots, Seller Payouts, gross sales, commission/fees, buyer purchase deduction, net amount, paid amount, and remaining balance.

Record a seller payout

Step 1: Select Check, Cash, or ACH/manual electronic method.

Step 2: Enter the payout amount.

Step 3: For Check or ACH, enter the required reference.

Step 4: Confirm the remaining balance and any Hold Check setting.

Step 5: Click Record Seller.

> Early payout warning
> Seller payouts may be recorded before or after auction close, but later sales or buyer purchases can change the final balance. Final settlement after buyer checkout is safer.

Seller print options

Print Settlement produces the standard financial statement. Print Item Summary groups sold items by lot, description, and price each; shows bidder number, quantities, line totals, Total Items Sold, and Total Hammer Sales.

19. End-of-Night Report




Figure 19-1. Financial summary, staff-payment entry, and audit ledger.

Financial summary

Refresh Totals reloads Hammer Sales, Buyer Premiums, Card Fees, Sales Tax, Invoice Total, Buyer Payments, Still Unpaid, Seller Gross, Seller Commission, Seller Payouts, Staff Payments, and Net Cash Movement for the current auction.

Record staff or operating payments

Step 1: Choose Category such as Clerk, Auctioneer, Floor Help, or Kitchen Help.

Step 2: Enter Payee, Amount, Payment Method, and Reference/Notes.

Step 3: Click Record Payment.

Step 4: To correct an entry, select it, click Void Selected, and enter the required reason. The original and void remain visible.

Print the report

Click Print Report, inspect the preview, and print. The report includes branded auction-company information, grouped revenue and expense totals, highlighted net cash movement, staff-payment ledger, and signature lines.

20. Reports Available in Version 0.7.60

Report or view	Where to open it
Dashboard totals	Dashboard; refreshes current-auction bidder, lot, sold, gross, and average values.
Buyer invoice/receipt	Cashier > Lookup Buyer > Print Invoice.
Unpaid buyer report	Cashier > Unpaid Buyers.
Buyer payment/refund history	Cashier tabs after buyer lookup; also printed on invoice.
Seller settlement	Cashier > Lookup Seller > Print Settlement.
Seller item summary	Cashier > Lookup Seller > Print Item Summary.
Seller payout history	Seller Payouts tab and settlement print.
Bidder card	Cashier > Bidder Cards.
End-of-Night report	Cashier > End-of-Night > Print Report.
Audit trail	Operational correction/void history is retained in the database and displayed in relevant ledgers.

Scope
Version 0.7.60 does not include a separate custom report designer, user-permission report, inventory-limit report, or direct card-processor settlement import.

21. Backups and Data Protection

Create a backup

Step 1: On the host Dashboard, click Backup Database.

Step 2: Wait for the success message and note the backup path.

Step 3: Copy a completed backup to a secure external location after HammerTrack closes or after the backup reports success.

Recommended schedule

- Before changing auction settings on auction day.
- Immediately before bidding begins.
- After major breaks when practical.
- After buyer checkout and seller settlement.
- Before installing any software upgrade.

What an upgrade preserves

The installer keeps the host database, backups, logs, workstation settings, main license, and Wholesale activation under ProgramData. Never test restore or destructive corrections against the production auction database.

22. Administration and Settings

Company and auction account information

Company identity is stored with each Auction record: company name, address, city, state, ZIP, phone, and email. Printed invoices and End-of-Night reports use this information. Auction Setup also stores staff names, location, commercial terms, tax basis, card fees, and document footers.

Clerk and cashier access

The host/cashier workstation role controls which operational surface starts on a computer. There are no individual Clerk or Cashier logins in this version. Protect access with Windows accounts, device passwords, physical control, and trusted private networking.

Auction permissions

There is no configurable permission matrix. Staff with access to HammerTrack can use the controls available on that workstation. Establish written procedures for who may close auctions, correct sales, refund buyers, void staff payments, and record seller payouts.

License management

The main .htplicense and Wholesale activation are machine-bound and work offline after installation. Replacing a computer requires a newly issued license/key containing the replacement Machine ID. Keep issuer private keys offline and outside the installer.

23. Troubleshooting

Problem	What to do
Program says no license	Copy the displayed Machine ID and import an issued .htplicense containing that exact ID.
Wholesale button opens activation	Issue and paste a signed Wholesale key for this PC.
Cashier is disconnected	Confirm the host is running, both PCs use the same private network, and host address/pairing key/fingerprint match. Try the Alternate IP.
Wrong tax on invoice	Verify selected auction tax rate/basis and the buyer Tax Exempt flag; save and reload the buyer invoice.
Card payment exceeds balance	Enter only the invoice balance before fee. Let HammerTrack calculate the fee.
Record Payments button appears missing	Maximize/fullscreen the Cashier window or scroll horizontally; use the current 0.7.60 layout.
Scanner beeps but fills nothing	Use PDF417 HID keyboard mode; enable regular and inverse PDF417 for new cards; keep the Scan Driver's License window active.
Names are incomplete after scan	Confirm the latest software version and review/correct every field before saving.
Cannot correct paid sale	Refund enough purchase value first, then use Correct Sale with a reason.
Cannot delete buyer/seller/lot	Operational or financial history prevents deletion; preserve the audit record and use the supported correction workflow.
Manual button cannot find PDF	Reinstall the current MSI or place HammerTrackPro-User-Manual.pdf beside HammerTrack.exe.
Print is clipped	Use Print Preview, correct paper orientation/size, and print at 100% unless the printer requires Fit.

24. Frequently Asked Questions

Does HammerTrack process credit cards?

No. It calculates and records the card portion and configured processing fee. Run the displayed charge on your separate card terminal, then record the payment in HammerTrack.

Can two PCs open the database file?

No. The live-auction host alone owns the local database. The cashier connects through the paired HTTPS service.

Can one buyer be registered in many auctions?

Yes. HammerTrack keeps one global Buyer identity and auction-specific bidder registrations.

Can a seller also buy?

Yes. The seller is linked to the same-number Buyer identity when possible, and unpaid purchases can be deducted from settlement proceeds.

What does Quantity mean in Wholesale Pass-Out?

It means items per deal. Deals is how many identical deals the current bidder buys. Total Quantity equals Quantity per Deal x Deals.

Can I refund a card fee?

No. The audited refund workflow refunds purchase funds only and retains card-processing fees.

Does the software have user passwords?

Not in version 0.7.60. Use Windows security and workstation roles, and limit physical access to authorized staff.

Where is my data?

By default, mutable data is under ProgramData\HammerTrackPro on the host. Use the in-program backup command rather than manually moving a live database.

25. Technical Support and Update Practice

For current contact options, product information, software updates, and support requests, visit https://hammertrackpro.com.

Before requesting support

- Record the software version shown in Apps & Features or installer filename.
- Note whether the computer is Host or Cashier.
- Write down the exact error message without including private license keys, scanner barcode data, buyer personal data, or payment details.
- Describe the last successful action and the steps that reproduce the problem.
- Create a database backup when the program can safely do so.

Keeping this manual current

This manual describes version 0.7.60. The installer includes the offline PDF opened by Help / User Manual. Keep the matching manual with your software update. The screenshots use fictional training data and example auction terms; your auction names, figures, printer names, and Windows display scaling will differ.

> Auction-day emergency rule
> Protect the database and written audit trail first. Do not delete files, bypass license/network security, or edit the SQLite database manually to force an auction-day correction.

26. Software License Agreement

Hammer Track Pro Auction Management Software

Purchaser / Company	Date
_____	_____
Contact Name / Phone	Email
_____	_____
Billing Address / City / State / ZIP	Software License No.
_____	_____

1. Licensed Computers

The Software is licensed for use by the original Purchaser / Company on a maximum of two (2) designated computers: one (1) Clerking PC and one (1) Cashier PC. Additional computers, users, or installations are not included unless separately authorized in writing. Replacement of a licensed computer because of equipment failure, upgrade, or replacement does not transfer the license to another person or company and may require reactivation by the Software Provider.

2. Nature Of License - Software Is Licensed, Not Sold

Hammer Track Pro is licensed, not sold. Payment purchases only a perpetual, limited, non-exclusive, non-transferable license to use the Software in accordance with this Agreement. The Purchaser does not acquire ownership of Hammer Track Pro, its source code, programming, design, intellectual property, documentation, trade secrets, or any other proprietary rights. All right, title, ownership, and intellectual property rights in and to Hammer Track Pro remain exclusively with the Software Provider. The license permits continued use of the licensed version for so long as the Purchaser complies with this Agreement.

3. License Ownership And Non-Transferability

The license is issued exclusively to the original Purchaser / Company identified in this Agreement and is permanently associated with that Purchaser / Company. The license may not be sold, resold, assigned, traded, gifted, leased, rented, loaned, sublicensed, inherited, transferred, or otherwise conveyed to another individual, business, auction company, organization, successor, purchaser, or third party. This restriction applies whether the proposed transfer occurs separately or as part of the sale, transfer, dissolution, merger, or change of ownership of a business, unless the Software Provider expressly authorizes the transfer in writing.

4. No Transfer Through Equipment Or Media

Possession or purchase of a computer, USB drive, installation media, installation files, activation credentials, license key, database, backup, or other copy of Hammer Track Pro does not create ownership of the Software or a valid license for another person or company. A computer containing Hammer Track Pro may be sold or transferred as hardware, but the Hammer Track Pro license does not transfer with that computer. Any new person or company wishing to use Hammer Track Pro must obtain its own license from the Software Provider.

5. No Resale, Distribution, Or Sharing

The Purchaser shall not copy, reproduce, distribute, resell, publish, share, sublicense, or otherwise make Hammer Track Pro available to any unauthorized person or entity. The Purchaser shall not provide installation files, activation information, license credentials, or copies of the Software for the purpose of allowing another person or company to install or operate Hammer Track Pro. Backup copies, if permitted, remain subject to this Agreement and may not be used to increase the number of licensed computers.

6. Support

Technical support, when offered, will be provided only to the original Purchaser / Company named in this Agreement and its authorized representatives. No support will be provided to a subsequent owner, transferee, third party, or unauthorized user.

7. Annual Updates

Software updates are optional. The specific content, timing, and availability of updates may vary by version. The perpetual license to the purchased version does not require the Purchaser to buy annual updates.

8. Custom Updates And Requested Features

Custom modifications, personalized updates, integrations, reports, requested features, or other development work may be available. The scope of work will be determined and approved at the time of the request before work begins.

9. Software Use And Restrictions

The Purchaser agrees not to reverse engineer, decompile, disassemble, bypass licensing controls, remove proprietary notices, modify the Software for redistribution, distribute activation information, or otherwise use the Software in a manner intended to defeat or circumvent the licensing restrictions contained in this Agreement.

10. License Suspension Or Termination

The Software Provider may suspend or terminate the license for unauthorized transfer, resale, copying, distribution, circumvention of licensing restrictions, non-payment when applicable, or other material breach of this Agreement, subject to applicable law. Termination does not transfer ownership of the Software and does not create any right to sell, distribute, transfer, or continue using the Software.

11. No Guarantee Of Future Features

Purchase of the license does not guarantee any future feature, custom feature, compatibility change, upgrade, update, or continued compatibility with future third-party hardware or operating systems unless specifically agreed to in writing.

12. Entire Agreement

This Agreement represents the understanding between the parties concerning licensing of Hammer Track Pro. Any modification, waiver, or transfer of these terms must be made in writing and authorized by the Software Provider.

13. Acknowledgment And Acceptance

By signing below, the Purchaser acknowledges that the Purchaser has read, understands, and agrees to this Agreement, including the two-computer license limit and the restrictions on transfer and resale. The Purchaser specifically acknowledges: HAMMER TRACK PRO IS LICENSED, NOT SOLD. Payment grants only the right to use Hammer Track Pro under this Agreement and does not transfer ownership of the Software or its intellectual property.

PURCHASER / COMPANY	SOFTWARE PROVIDER
Signature: _____	Signature: _____
Printed Name: _____	Printed Name: _____
Date: _____	Date: _____

End of HammerTrack Pro Customer User Manual