




LAN-A: Minimal 50 Host
 LAN-B: Minimal 40 Host
 Minimal 2 subnet cadangan
 Tidak menggunakan VLSM

Range Host Table

Subnet	Network ID	Range Host Usable	Broadcast
Lan-A	192.168.0.0/26	192.168.0.1 – 192.168.0.62	192.168.0.63
Lan-B	192.168.0.64/26	192.168.0.65 – 192.168.0.126	192.168.0.127
Unused-1	192.168.0.128/26	192.168.0.129 – 192.168.0.190	192.168.0.191
Unused-1	192.168.0.192/26	192.168.0.193 – 192.168.0.254	192.168.0.255

Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
Customer Router	G0/0	192.168.0.1	255.255.255.192	N/A
	G0/1	192.168.0.65	255.255.255.192	N/A
	G0/1/0	209.165.201.2	255.255.255.255	N/A
Lan-A Switch	VLAN 1	192.168.0.2	255.255.255.192/26	192.168.0.1
Lan-B Switch	VLAN 1	192.168.0.66	255.255.255.192/26	192.168.0.65
PC-A	NIC	192.168.0.62	255.255.255.192/26	192.168.0.1

PC-B	NIC	192.168.0.126	255.255.255.192/26	192.168.0.65
------	-----	---------------	--------------------	--------------

Customer Router

```
enable
configure terminal
hostname CustomerRouter
enable secret Class123
line console 0
password Cisco123
login
exit
interface g0/0
ip address 192.168.0.1 255.255.255.192
no shutdown
exit
interface g0/1
ip address 192.168.0.65 255.255.255.192
no shutdown
exit
end
write memory
```

LAN-A Switch

```
enable
configure terminal
interface vlan 1
ip address 192.168.0.2 255.255.255.192
no shutdown
exit
ip default-gateway 192.168.0.1
end
write memory
```

LAN-B Switch

```
enable
configure terminal
interface vlan 1
ip address 192.168.0.66 255.255.255.192
```

```
no shutdown
exit
ip default-gateway 192.168.0.65
end
write memory
```