



Client Login (https://www.assistanz.com/members/)

• Contact Us (https://www.assistanz.com/contact-us)

1 +1 888 500 1070 (Toll Free)



About Us (https://www.assis

**Cloud Services** 

**IMS Cons** 

Mobility (https://www.assiste

(HTTPS://WWW.ASSISTANZ.COM/)

Home (Https://Www.assistanz.com) > Blog (Https://Www.assistanz.com/Blog/) > Blog (Https://Www.assistanz.com/Catego (Https://Www.assistanz.com/Category/Blog/Containers/) > Running Windows Container In Windows 2016

# Running Windows Container in Windows 20

① April 3, 2017

Posted by: Loges

Category: Blog, Containers

(https://www.assiwindows-



# Running Windows Container in Windows 2016

In this blog, we will show you how to running windows container in windows 2016 using docker commands.

# **OVERVIEW**

We are using the docker client command **docker.exe** to run the windows containers in windows 2016. There options available in docker command. you can use the help page to find different options about this command.

#### **RUN WINDOWS CONTAINER IN AN INTERACTIVE MODE**

To run a container in an interactive mode, use the below command.

# docker run -it microsoft/nanoserver cmd

In the above example,

docker - Command name

run - sub option of to run the container

-it - To run the container in interactive mode

microsoft/nanoserver – Image name for this container

**cmd** – To execute the cmd.exe process for interactive experience

```
Administrator: Windows PowerShell (2)

PS C:\> docker run -it microsoft/nanoserver cmd_ (https://www.assistanz.com/wp-
```

content/uploads/2017/04/image-9.png)

Note: By default, docker will use the latest images if you are not provide the tag nan image.

Also, we can provide tag along with the image name as shown below.

# docker run -it microsoft/nanoserver:latest cmd

Once docker started successfully it shows the command prompt.

```
Administrator: Windows PowerShell

Microsoft Windows [Version 10.0.14393]
(c) 2016 Microsoft Corporation. All rights reserved.

C:\>hostname
0365c42e285f

C:\>_
```

content/uploads/2017/04/image-10.png)

• To stop the container, type **exit** and press enter.

#### DISCONNECT THE CONTAINER

- To keep the container in the running mode, press CTRL key+PQ
- Once you press these keys it will disconnect from the container.

```
Administrator: Windows PowerShell

Microsoft Windows [Version 10.0.14393]
(c) 2016 Microsoft Corporation. All rights reserved.

C:\>hostname
0365c42e285f

C:\>
PS C:\>
______
```

content/uploads/2017/04/image-11.png)

• To list the docker process, type the below command.

# docker ps

```
PS`C:\> docker ps
CONTAINER ID IMAGE COMMAND CREATED STAT
NAMES
0365c42e285f microsoft/nanoserver:latest "cmd" 22 minutes ago Up 2
romantic_kirch
PS C:\> _
```

(https://www.assistanz.com/wp-content/uploads/2017/04/image-12.png)

#### **STOP THE CONTAINER**

• To stop the container, type below command.

**Syntax:** docker stop <container ID> or <container name>

Example: docker stop 03

Note: We can use the first two character of container ID for short form.

```
PS C:\> docker stop 03
03
PS C:\> _
```

(https://www.assistanz.com/wp-content/uploads/2017/0-

• There are no running containers available now.



(https://www.assistanz.com/wp-content/uploads/2017/04/image-14.png)

• To show all the containers including stopped, type the below command.

#### docker ps -a



(https://www.assistanz.com/wp-content/uploads/2017/04/image-15.png)

# START THE CONTAINER

• To start the container, type the below command.

**Syntax:** docker start <container ID> or <container name>

Example: docker start 03

```
PS C:\> docker start 03
03
(https://www.assistanz.com/wp-content/uploads/2017/04/ima
```

```
PS C:\> docker ps
CONTAINER ID IMAGE COMMAND CREATED STATUS
NAMES
0365c42e285f microsoft/nanoserver:latest "cmd" 41 minutes ago Up 5 minutes
romantic_kirch
PS C:\> _
```

(https://www.assistanz.com/wp-content/uploads/2017/04/image-17.png)

# **SETTING NAME FOR CONTAINER**

• By default, Microsoft will choose a random name for a container. To set a name while creating the container, type command.



(https://www.assistanz.com/wp-content/uploads/2017/04/image-18.png)

• Once the container created successfully, press **CTRL+PQ** to disconnect from the container. Then type **docker ps** the container(s).



(https://www.assistanz.com/wp-content/uploads/2017/04/image-19.png)

• So we can use the name **srv01** to stop, start and delete the containers.

```
PS C:\> docker stop srv01
srv01
PS C:\> _ (https://www.assistanz.com/wp-content/uploads/2017
```

# **DELETE A CONTAINER**

• To delete a container, type the below command.

**Syntax:** docker rm <container ID> or <container name>

Example: docker rm srv01



(https://www.assistanz.com/wp-content/uploads/2017/0

• If you try to delete the running container using **rm** command it shows the below error.

```
PS C:\> docker rm 03
Error response from daemon: You cannot remove a running container 0365c42e285f613f5e66f92da03e8071ec70ba29bb9c283
6a2094c44e. Stop the container before attempting removal or use -f
PS C:\> _
```

(https://www.assistanz.com/wp-content/uploads/2017/04/image-22.png)

• To delete the running container, type the below command.

Syntax: docker rm -f <container ID> or <container name>

Example: docker rm -f 03



(https://www.assistanz.com/wp-content/uploads/2017/04

#### RUNNING IN DETACH MODE WHILE CREATING THE CONTAINER

• To run in the detach mode while creating the container, type the below command.

Syntax: docker run -d <container image> <process command>

Example: docker run -d microsoft/nanoserver ping 127.0.0.1 -t

```
Administrator: Windows PowerShell
PS C:\> docker run -d microsoft/nanoserver ping 127.0.0.1 -t
:68701621fad06f5152b624cdbe78f032767b5d67569d3d085150f1153de75b01
PS C:\> _
```

content/uploads/2017/04/image-24.png)

When we list the docker process, we can able to see the container running in background.



content/uploads/2017/04/image-25.png)

• To start another process inside a running container, type the below command.


**Syntax:** docker exec -it <container ID> or <container name> command>

**Example:** docker exec -it 68 cmd



content/uploads/2017/04/image-26.png)

• After few seconds, it shows the command prompt. Type **hostname** to verify the container.



content/uploads/2017/04/image-27.png)

• Type **exit** to exit from the container. Now execute the **docker ps** command to view the docker process list.



(https://www.assistanz.com/wp-content/uploads/2017/04/image-28.png)

The command which we ran during detach mode is still running in the background.

# **COLLECTING INFORMATION ABOUT CONTAINER**

• To view the information about the container, type the below command.

Syntax: docker inspect <container ID> or <container name>

**Example:** docker inspect 68

```
## Administrator Windows PowerPall

PS C:\> docken inspect 68

{
    "Id": "68701621fad06f5152b624cdbe78f032767b5d67569d3d085150f1153de75b01",
    "Created": "2017-04-03T07:46:37.74737612",
    "Path": "ping",
    "Args: [
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "2127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
    "127.0.0.1",
```

content/uploads/2017/04/image-29.png)

It shows the information about the container in JSON format.

#### **VIDEO**