PRODUCT OWNER QUICK GUIDE

Time-Phased Material Plan

How to read projected stock, recommended orders, and expedite flags

A weekly row, explained

One row represents one material at one plant. Values use that material's unit of measure.

Plant	Material	On Hand	Min / Max	W0 · 1 Nov	W+1 · 8 Nov
P_AGR	PK-BAG-45	60,000	50,000 / 600,000	**79,993** +30,000 order Expedite	**69,985** + order if shown

Bold: projected stock at bucket end

Blue: recommended order quantity

Red: release due by horizon start

What the labels mean

Projected stock

Expected remaining stock after demand, receipts, and the recommended order are included.

+N order

Planned supply in this bucket. It is already included in projected stock; do not add it a second time.

Expedite / Capacity

Expedite: release date is on/before W0. Capacity: projected stock is above the configured maximum.

PK-BAG-45 · W0 example

Opening stock	60,000
Gross demand (inferred)	−10,007
Recommended order	+30,000
Projected stock	**79,993**

Before the order, stock is 49,993: 7 below the 50,000 minimum. MOQ is 30,000, so order quantity is 30,000. Screenshot values imply no W0 receipts.

Calculation flow

1 · DEMAND
Forecast × BOM usage with configured scrap

→

2 · AVAILABLE STOCK
Opening/projected stock + scheduled receipts − demand

→

3 · NET NEED
max(0, minimum stock − available stock)

→

4 · ORDER
max(net need, MOQ)

Then: Projected stock = available stock + planned order. Lead time shifts the order release earlier.

Current implementation applies MOQ but does not round to order multiples or cap the order at Max.

Expand a material to inspect Gross Requirements, Scheduled Receipts, Net Requirements, Projected Inventory, and Planned Order Release. This is a recommendation, not a created PO.

When a number looks surprising

Check gross demand and BOM units, uploaded on-hand and dated receipts, then minimum stock, MOQ, lead time, scrap, and capacity settings. Demo data is illustrative; validate with approved inputs before making procurement decisions. See time_phased_material_plan_guide.md for the full explanation.

MRP Product Owner Guide · Planning values use the configured material unit of measure.