



CACHATTO Secure Container AD

Administrator manual

Public beta version

July 3, 2023

table of contents

Chapter 0	Introduction	3
	About this manual	3
	Product Summary.....	3
	About the contents of the description.....	3
	Images and illustrations used in this manual	3
	Trademarks	3
	Revision history.....	3
Chapter 1	Items to check before installation	Four
	Operating requirements.....	Four
	Active Directory Linkage	Four
	Environments that do not work properly.....	7
Chapter 2	Usage environment	8
	2.1 About target Windows accounts	8
	2.2 Start the program.....	8
	2.3 Program Installation.....	8
	2.4 Saved files.....	8
Chapter 3	Admin settings	9
	3.1 Confirmation/editing of CACHATTO administrator account.....	9
	3.2 About Polling Status.....	Ten
	3.3 Confirmation of license information.....	Ten
	3.4 Security policy settings.....	Ten
	3.5 Setting up an authentication server.....	11
	3.6 User registration	11
	3.7 Bulk registration of users.....	12
Chapter 4	User Procedures	13
	4.1 User Startup Procedures	13
	4.2 Use of CACHATTO Private Connect.....	15
	4.3 Uninstalling CACHATTO SecureContainer.....	15
Chapter 5	system maintenance.....	16
	5.1 CACHATTO SERVER MAINTENANCE.....	16
	5.2 CACHATTO SecureContainer Client Logs.....	16
	5.3 Things to check when startup fails or malfunctions occur	16

Chapter 0 Introduction

About this manual

This manual is a manual for administrators that describes the procedures and explanations for using CACHATTO SecureContainer AD using the CACHATTO server provided as a cloud service or on-premise format.

All the items of the CACHATTO server management screen and the construction setting procedure for on-premises configuration are not posted. For more detailed information on the CACHATTO server, please refer to the "CACHATTO Administrator's Manual" posted on the CACHATTO support site.

[procedure]

1. Open the CACHATTO support site
2. Click "Manuals/Documents/Videos"
3. Click "CACHATTO Administrator Manual"
4. Browsing the posted manual

Product Summary

CACHATTO SecureContainer AD generates a virtual disk after turning on the Windows terminal, and after signing in to the Windows terminal with an Active Directory account, the virtual disk is mounted and a work area is constructed. Data stored in that virtual disk will be deleted when you sign out.

By using CACHATTO SecureContainer and the encryption function of Windows, we will take measures against terminal theft and loss. You can use cloud services such as Microsoft 365 in a secure business area type and edit files using MS Office.

About the content

The contents described in this manual are the latest information as of the time described in the revision history. Please note that it may be changed after posting.

Images and illustrations used in this manual

The images and illustrations used in this manual may differ from the actual ones.

Trademarks

The company names and product names mentioned in this manual are trademarks or registered trademarks of their respective companies. The company names, product names, and service names described in this manual do not necessarily have™is not appended.

Revision history

Revision date	Revision details
July 3, 2023 (Public beta compatible version)	First edition created

Chapter 1 Items to check before installation

Operating requirements

	Minimum usage requirements	Recommended environment
OS	Windows 10/11	Windows 10/11
CPU	Intel Core i5-6300U equivalent	Intel Core i5-8265U equivalent
RAM	4GB	8GB

* Supported OS versions of Home / Pro conform to Microsoft. We will also end our support for versions that Microsoft has ended support for.

* Windows 10/11 Home/Pro are supported, Enterprise, LTSB, IoT are not included. Please contact the CACHATTO Support Center if you wish to use it in any other Windows 10/11 environment. * We do not guarantee that this product can be used in any environment that meets the above specifications. This product may not work properly depending on the environment such as Windows settings and security software.

*Supported languages: Japanese, English

Please use the following version to use CACHATTO Private Connect.

- CACHATTO 6.18.0 or later (Please contact us individually for RHEL, CentOS, Rocky Linux verified versions)


Active Directoryalignment

This product assumes an environment linked with Active Directory.

Please use it as a user with the following policies enabled.


● Hide C drive in explorer

User Configuration > Administrative Templates > Windows Components > File Explorer > Hide these specified drives > Restrict to C drive only



- Prohibit C drive access in Explorer

Computer Configuration > Policies > Administrative Templates > Windows Components > File Explorer > My Computer > Prevent drive access from My Computer > Restrict C drive only



- Prohibit execution of specified apps


User Configuration > Policies > Administrative Templates > System > Do not run specified Windows applications

- Prohibit execution of Command Prompt

User Configuration > Policies > Administrative Templates > System > Prevent access to Command Prompt


- Prevent Registry Editor from running

User Configuration > Policies > Administrative Templates > System > Prevent access to registry editing tools



- If there is no operation for more than the specified time, Windows will be locked. Either of the following can be set.


Computer Configuration > Windows Settings > Security Settings > Local Policies > Security Options > Interactive logon: Computer inactivity limit



User Configuration > Policies > Administrative Templates > Control Panel > Personalization > Enable screen saver

User Configuration > Policies > Administrative Templates > Control Panel > Personalization > Password protect screensaver


User Configuration > Policies > Administrative Templates > Control Panel > Personalization > Screen Saver Timeout



Restrictions on the use of external storage devices

User Configuration > Policies > Administrative Templates > System > Removable Storage Access > Removable Disks:
Deny read access

User Configuration > Policies > Administrative Templates > System > Removable Storage Access > Removable Disks:
Deny write access



environment that does not work properly

CACHATTO Private Connect conflicts with other VPN software, so please stop the service or uninstall other VPN software.

Chapter 2 Usage Environment

2.1 About target Windows accounts

CACHATTO SecureContainer AD works for accounts without administrator privileges.

2.2 Start the program

Application launch is not restricted.

To restrict the launch of apps, use Active Directory group policy or asset management software.

2.3 Program installation

Program installation is not restricted. Please use asset management software when distributing programs.

2.4 About save files

Files generated and downloaded by "CACHATTO User" are saved on a virtual disk mounted on Z:. Storage limit is 32GB.

* Depending on the PC, the virtual disk mount destination may be a different drive.

Chapter 3 Administrator Settings

important:

The settings made by the administrator are carried out from the "CACHATTO Server Management Screen". Please access the URL provided by our company with a browser and log in. If you do not know the URL or login information, please contact us.

3.1 Confirmation/editing of CACHATTO administrator account

Click "Administrator information" from the CACHATTO management screen, and check/edit the items of "Change administrator information" and "Management screen login URL". Then click the OK button to save.

<Company ID>

The company ID issued by our company is displayed. This item cannot be changed.

<Admin ID>

Enter any ID.

<administrator password>

The password of the currently logged in administrator. The number of "*" displayed is different from the actual number of password digits. Only alphanumeric characters, underscores "_", hyphens "-", and dots "." can be used in the administrator password. Also, when using alphabetic characters, distinguish between uppercase and lowercase letters.

<Re-enter administrator password>

After entering (changing) the administrator password, enter the same password.

<administrator name>

Enter the administrator name.

<contact email address>

Administrator contact email address. Destination of the admin login URL.

<Use management screen>

You can change the availability of the management screen or delete the administrator.

<allow>

Activate that administrator account.

<Stop>

Disable that administrator account.

<delete>

Remove this administrator account.

<Administrator access settings>

You can limit the pages (confirmation of registered content, whether or not to change it) displayed on the management screen of the registered administrator. When registering as a new user, a link to [>>Customize page] will be displayed after registration (click the [OK] button). "Administrator access settings" screen Click [>>Customize page] to display the "Administrative privilege settings" screen. You can restrict access to the management screen by administrator.

If you select the [Permission to change settings] check box, you can restrict access for the administrator selected on the "Select administrator" screen (page) on a page-by-page basis. If you log in to the management screen with the administrator's girlfriend's ID, pages that do not have the [Permission to change settings] checkbox unchecked will not be displayed in the menu on the left side of the page, and you will be able to confirm the registration details. and cannot be changed.

By default, the pages that are allowed are limited.

"System maintenance" cannot be set because it is a function limited to administrators with full authority. Finally, when you click the [OK] button, the message "Administrator has been registered" is displayed, and registration or change of administrator information is completed.

3.2 About Polling Status

Click [Server Status] in "Management Information" and confirm that "Polling Status" is "OK". Users cannot log in while polling is NG.

ポーリング情報	
ポーリングステータス	 OK, Last Poll Time: 2023/06/08 12:53:40
ポーリング停止/開始	ポーリング停止

3.3 Confirmation of license information

From the CACHATTO management screen, click [Management Information] > [License Information]. The "License Information" screen appears. Each user needs to know the access point name and company ID as information required for login, so please check her on this page.

<access point name>

The name of the CACHATTO access point you are using. It will be used for user login, so please inform the user along with other login information.

Example) In the case of "sbc.cachatto.jp", the login URL is <https://sbc.cachatto.jp/>

<Company ID>

An ID assigned to each CACHATTO server. It will be used for user login, so please inform the user along with other login information.

<Number of purchased licenses>

The number of CACHATTO licenses that can be registered. The total amount of 3 IDs, 2 IDs for monitoring and 1 ID for verification, is added.

<license type>

The name of the product you purchased. To use CACHATTO SecureContainer AD, you need CACHATTO Desktop licenses for the number of users

<Expiration date (year/month/day)>

This is the expiration date. The expiration date is 23:59:59 on the displayed date. 60 days before the expiration date and 30 days before the expiration date, a "License Expiration Notification Email" will be sent to the registered administrator's email address.

3.4 Setting Security Policy

The setting items required for using CACHATTO SecureContainer AD are listed below. It is usually not necessary to change settings for items not described below, but it may be necessary when performing advanced settings. For details of each item, please refer to the attached "CACHATTO Administrator Manual".

<Terminal ID authentication>

When using terminal ID authentication, enable "terminal ID authentication method".

<SmartLogin usage settings>

Turn off "SmartLogin".

<User function restrictions>

- Check "Tablet/PC" under "Interface to use".
- To set the MDM policy described later, click "MDM Policy Settings".
- Click ">> Policy setting page" in "Group policy setting"

3.5 Setting up an authentication server

Log in to the administration screen and click "Server Settings" > "Authentication Server Settings".

<AD/LDAP Server ID>

If not registered, [NEW] is displayed. When registering, "Host name/IP address" is displayed. If it is already registered, the set "Host name/IP address" will be displayed, so select it as necessary.

<AD/LDAP host name/IP address>

For new registration: Enter the server host name or IP address. If registered: The registered host name or IP address is displayed.

<AD/LDAP port>

Enter the port to connect to. If left blank, number 389 will be automatically set.
Standard port numbers: "Non-SSL: 389" "SSL: 636"

<SSL/TLS settings>

Select ON when using SSL for communication with the LDAP server, and select OFF when not using SSL communication.

<NetBIOS domain name>

If your LDAP server uses Active Directory, enter the NetBIOS domain name of your LDAP server. Hit the autodetect button and you will automatically get her NetBIOS domain name. If the acquisition is successful, it will automatically enter her NetBIOS domain name.

If you cannot get it automatically, please enter it directly.

(Example) If "NetBIOS domain name\user name" is "EJAN\Taro", enter EJAN

3.6 User Registration

Please log in to the management screen and click "User settings" > "User registration".

note:

It is usually not necessary to change the settings of items not described below, but it may be necessary when performing advanced settings. For details on each item, please refer to the attached "CACHATTO Administrator Manual".

<CACHATTO login ID>

Your login ID for CACHATTO. Enter the user logon name registered in Active Directory.

<Authentication method>

CACHATTO Select the login password authentication method. Please select "AD/LDAP".

Since the AD/LDAP server item is displayed, select and set the authentication server registered in "3.5 Authentication Server Settings" from the pull-down menu.

<Interface used>

Check "Tablet/PC"

<Available apps>

Check the user "CACHATTO Desktop".

*If you do not check "CACHATTO Desktop", you cannot log in to CACHATTO SecureContainer AD.

yeah.

<Terminal ID authentication method>

Select whether or not to use terminal ID authentication when logging in. Applies the same settings as "Security Policy" > "Device ID Authentication Method" on the administration screen. If you turn off the check box, you can select the individual terminal ID authentication radio button.

To use shared terminal ID authentication, select the shared terminal group registered in "User settings" > "Shared terminal ID registration". Any terminal registered in the selected shared terminal group can be used.

<device registration code>

Register the device registration code displayed on LoginApp and decide in advance which devices can log in to CACHATTO. This item is not displayed if [Device registration function] is turned off in the security policy.

<SmartLogin usage settings>

Since SmartLogin is not used in CACHATTO SecureContainer AD, set it to OFF or the same setting as the security policy.

<Email address settings>

Enter the user's email address in "Email address (required)". When an email is sent from her CACHATTO server to the user by the administrator's operation, the email address listed here will be the destination.

3.7 Bulk registration of users

To create and edit a large number of user accounts at once, please use bulk registration with a CSV file.

Click "User settings" > "Bulk registration" and click the "Download" icon in "User information CSV file download" to download the CSV file containing the user information created in 3-7. Enter the information for the additional users there, upload the file in "Manual registration" and "Upload his CSV file on the local PC to register" and click the "Register" icon please.

Click "Description of each item" to check the outline of each item and the CSV file setting format. Unnecessary CSV file items can be excluded in "User information CSV registration item settings" on the same page.

Chapter 4 User Procedures

4.1 User start-up procedure

procedure

1 CACHATTO Secure Container ADto install

Sign in to Windows with an account that has administrator privileges and run the installer provided by e-Jan Networks. Install according to the instructions of the wizard.

2 ADSign in with your account

Sign out from an account with administrator privileges and sign in with an AD account on the Windows sign-in screen.

3 CACHATTOlog in to

Click "Account" in LoginApp.



Register your account information.

<access mode>

Select "CAP". Depending on the version, it is described as "access point" instead of "CAP".

<access point URL>

Please enter the URL listed on the following page of the CACHATTO server.

<login type>

Select "Fixed password" or "AD/LDAP". Which login type to use depends on administrator settings.

<Company ID>

Enter the values listed on the following page of the CACHATTO server.

<display name>

This is the name that will appear in the LoginApp pull-down menu. It is not actually used as login information. Enter each of the above items and click "Apply" to automatically set.

With the above steps, you can start using CACHATT SecureContainer AD.

4.2 Use of CACHATTO Private Connect

This is a function to remotely access the internal network from CACHATTO SecureContainer and access internal servers and cloud services.

This function is provided as a paid optional function separate from CACHATTO SecureContainer. *If you would like a trial, please contact our sales representative or his CACHATTO support center.

If this function is enabled in the administrator settings, the connection will start after login with LoginApp is completed, and the notification message "Starting remote connection..." will be displayed at the bottom right of the screen.

After that, the icon in the task tray at the bottom of the screen changes. If the icon indicates that the cable is connected, the remote connection is OK. If the cable is not connected, the icon is red! mark is displayed.

If communication is interrupted due to network switching, etc., execute "Start Remote Connection" from the right-click menu of the icon to reconnect to CACHATTO Private Connect.

note:

To use CACHATTO Private Connect, you need to install and configure the CACHATTO Private Connect server on the server where the CACHATTO server is running.

For details on the procedure, see the separate manual.

4.3 Uninstalling CACHATTO SecureContainer

Double-click or right-click CACHATTO SecureContainer in the program list of "Uninstall a program" in "Control Panel" to uninstall it.

Chapter 5 System maintenance

5.1 CACHATTO SERVER MAINTENANCE

You can update the CACHATTO server, check user access logs, edit notifications from administrators to users, and more.

For information on how to use this function, please refer to the "CACHATTO Administrator's Manual" posted on the CACHATTO support site.

5.2 CACHATTO SecureContainer Client Log

In the event of a problem, the CACHATTO Support Center may ask the user to acquire and share the log generated in the Windows folder below. In that case, please provide the files contained in this folder.

C:\ProgramData\e-Jan Networks\Log

Pressing Shift + D + Enter on the CACHATTO SecureContainer icon on the Windows desktop will launch CACHATTO SecureContainer AD in debug mode and generate more detailed logs. When requesting this from us, please use this mode to reproduce the event and acquire the log.

5.3 Things to check when startup fails or malfunctions occur

Please set the following folders as exclusion targets in your security software.

- C:\Program Files (x86)\e-Jan Networks\CACHATTO Secure Container
- C:\ProgramData\e-Jan Networks\Apps