

High-probability momentum options trading system for Nifty ✓

Act as an expert Quantitative Trading Engineer and Institutional Derivative Strategist. I want to build a high-probability momentum-catching system for intraday options buying (focused on Nifty/Bank Nifty) from absolute scratch.

Forget all previous architectures, code implementations, or constraints we have discussed. I want a completely fresh, unbiased, and genuine

Show more

Quantitative Momentum Engine for Intraday Options Buying

Architecture Design for Nifty/BankNifty — Tick-by-Tick Sharekhan Feed

FOUNDATIONAL PHILOSOPHY

Before the architecture: options buying has a brutally asymmetric cost structure. Theta decays every second, IV can crush your premium even on a correct directional call, and slippage on wide bid-ask spreads eats edge instantly. The entire engine must be built around **one core principle**:

Only enter when the expected momentum magnitude exceeds the combined cost of theta decay + IV crush + slippage — within a defined time window.

Every module below serves this single constraint.

MODULE 1 — THE LOGIC CORE

1.1 The Three-Axis Signal Model

Entry is triggered only when all three axes align simultaneously. A signal on two out of three is explicitly rejected.

AXIS 1: Price Axis	→ Directional momentum with structural validity
AXIS 2: Volume Axis	→ Institutional participation confirmation
AXIS 3: Volatility Axis	→ IV expansion ahead of premium, not behind it

Each axis produces a score from 0-10. **Minimum combined threshold: 21/30.**

1.2 AXIS 1 — Price Action Core

A. Microstructure Breakout Condition

You are not trading a candle breakout. You are trading a **tick-velocity breakout** — the rate of price change per unit volume, not per unit time.

Price Velocity (PV) = $\Delta \text{Price} / \Delta \text{Volume_ticks}$

Rolling window: last 50 ticks

Baseline PV = median(PV over last 500 ticks)

Breakout PV = current 10-tick rolling PV

Signal fires when: Breakout_PV > 2.5 σ above Baseline_PV

This catches moves where price is moving *fast per unit of volume traded* — the signature of genuine directional institutional flow, not high-frequency noise.

B. VWAP Structural Positioning

VWAP Band = VWAP $\pm$ (1.5 $\times$ σ_{VWAP})

where σ_{VWAP} = rolling std dev of price from VWAP over session

Bullish condition: LTP crosses above VWAP_Upper_Band with positive PV

Bearish condition: LTP crosses below VWAP_Lower_Band with negative PV

Rejection filter: If price crossed VWAP_Upper_Band more than 2 $\times$
in last 30 minutes without follow-through $\rightarrow$
downgrade Axis 1 score by 3 points (fakeout zone)

C. Tick-Level Order Flow Imbalance (OFI)

This is the single most powerful microstructure signal available from your tick feed:

For each tick:

If tick_price $\geq$ ask_price $\rightarrow$ Buyer-initiated $\rightarrow$ OFI += volume

If tick_price $\leq$ bid_price $\rightarrow$ Seller-initiated $\rightarrow$ OFI -= volume

Else $\rightarrow$ Neutral

Rolling OFI(60 ticks) = Σ directional_volume over last 60 ticks

Normalized OFI = OFI(60) / Total_Volume(60)

Strong bull signal: `Normalized_OFI > +0.65`
 Strong bear signal: `Normalized_OFI < -0.65`
 Fakeout indicator: `|Normalized_OFI| < 0.30` on a price breakout → REJECT

Axis 1 Scoring:

Condition	Points
<code>PV > 2.5σ</code>	+4
VWAP band breach confirmed	+3
<code>Normalized OFI > 0.65</code>	+3
OFI direction matches price direction	+1 (bonus)
Fakeout zone flag active	-3

1.3 AXIS 2 — Volume Expansion Core

Raw volume is useless. You need **relative volume with time-of-day normalization**.

A. Time-Normalized Volume Surge (TNVS)

Markets have predictable volume profiles: surge at open, trough at midday, surge at close. A 2× volume at 10:15 is very different from 2× at 2:45.

`TNVS = Current_Volume_Rate / Historical_Avg_Volume_Rate[same_minute_of_day]`

Historical baseline: rolling 10-session average for each minute bucket

Strong signal: `TNVS > 3.0` (volume is 3× normal for this time of day)

Moderate signal: `TNVS > 1.8`

Reject: `TNVS < 1.4` (not enough institutional participation)

B. Volume Acceleration (not just level)

`Vol_Accel = dVolume/dt` over last 5 ticks vs. prior 5 ticks

If `Vol_Accel > 0` and increasing → accumulation in progress

If `Vol_Accel` peaks and turns → exhaustion warning (exit signal, not entry)

C. Options Chain Volume Shift

Pull the options chain OI and volume snapshot (refreshed every ~30 seconds from your API):

```
CE_Volume_Surge = CE_Volume(last_5min) / CE_Volume(prior_30min_avg_per_5min)
PE_Volume_Surge = PE_Volume(last_5min) / PE_Volume(prior_30min_avg_per_5min)
```

Directional Conviction Ratio (DCR):

Bull: $\text{CE_Volume_Surge} / \text{PE_Volume_Surge} > 2.5$

Bear: $\text{PE_Volume_Surge} / \text{CE_Volume_Surge} > 2.5$

This confirms options buyers are piling into one direction – institutional desks do not misallocate capital at 3× normal volume

Axis 2 Scoring:

Condition	Points
TNVS > 3.0	+4
TNVS 1.8–3.0	+2
Vol_Accel positive and rising	+3
DCR > 2.5 in signal direction	+3
Vol_Accel already decelerating at entry	–3

1.4 AXIS 3 — Volatility & OI Core

A. IV Expansion Lead Indicator

The critical failure mode of options buyers: **entering after IV has already expanded**. The premium move you see on your screen is *partly* IV expansion that has already happened. You need to catch IV *before* it expands.

IV_Lead_Signal:

Track the ATM option's implied vol refreshed every tick
(back-calculate from LTP using Black-Scholes with known inputs)

$\text{IV_Velocity} = \Delta \text{IV} / \Delta \text{time over last 60 seconds}$

Entry condition: $\text{IV_Velocity} > 0$ AND IV is still within 1σ of session's IV baseline (low absolute IV, rising IV velocity)

Danger zone: IV already $> 1.5\sigma$ above session baseline → IV crush risk HIGH → reduce position size or skip

B. OI Change Velocity (the institutional footprint)

OI is updated in snapshots. Between snapshots, estimate using:

$$\text{OI_Proxy} = \Sigma(\text{buyer-initiated volume}) - \Sigma(\text{seller-initiated volume})$$

[using OFI from Axis 1]

$$\text{True OI Delta} = (\text{New_OI_snapshot} - \text{Prior_OI_snapshot}) / \text{time_elapsed}$$

Bull signal: Price $\uparrow$ + OI $\uparrow$ = Fresh longs being built $\rightarrow$ Strong

Bull signal: Price $\uparrow$ + OI $\downarrow$ = Short covering $\rightarrow$ Momentum may be weak/shorter

Bear signal: Price $\downarrow$ + OI $\uparrow$ = Fresh shorts being built $\rightarrow$ Strong

Bear signal: Price $\downarrow$ + OI $\downarrow$ = Long unwinding $\rightarrow$ Momentum may be short-lived

C. VIX Regime Filter

India VIX regimes:

VIX < 13: Low vol regime $\rightarrow$ momentum moves are smaller,
premiums are cheap but moves may disappoint

VIX 13-18: Optimal zone $\rightarrow$ good premium moves with reasonable IV

VIX 18-24: Elevated regime $\rightarrow$ moves are bigger but IV crush on reversals is violent

VIX > 24: Danger zone for options buyers $\rightarrow$ bid-ask spreads widen,
slippage is severe, skip or halve position size

Score adjustment based on VIX regime is applied as a multiplier, not additive

Axis 3 Scoring:

Condition	Points
IV_Velocity > 0 AND IV within session baseline	+4
OI expanding in signal direction (fresh positions)	+3
OI + Price both confirming direction	+2 (bonus)
VIX in optimal regime (13-18)	+1 (bonus)
IV already > 1.5 σ above baseline	-4
OI declining (short cover / long unwind only)	-1

1.5 The Fakeout Detection Filter

This is the engine's immune system. Before any signal crosses the 21/30 threshold, it must pass the fakeout battery:

FAKEOUT BATTERY (any ONE hit → trade REJECTED):

1. Spread Toxicity Check:

Bid-Ask spread > 0.8% of option premium → market makers pricing in uncertainty → skip

2. Price Reversal Memory:

If Nifty/BankNifty breached this exact price level in last 45 minutes and reversed → "contested zone" flag → require OFI > 0.75 (higher bar)

3. Time-of-Day Filter:

09:15-09:45 → BLOCKED (opening auction noise, gap fills, false moves)

11:30-12:00 → CAUTION (volume trough, moves often reverse)

15:00-15:30 → BLOCKED (expiry day and near-expiry exception: allowed only on strong trend days)

4. Theta Runway Check:

If days_to_expiry ≤ 2 AND signal is not on expiry day itself:

Minimum signal threshold raised to 25/30 (theta too aggressive)

5. Whipsaw Frequency Monitor:

If underlying crossed VWAP > 3× in last 20 minutes →

choppy market flag → REJECT all signals for 15 minutes

MODULE 2 — TIMING & CONFIRMATION

2.1 The Three-Tick Confirmation Protocol

Never enter on the first confirming tick. Wait for micro-confirmation:

CONFIRMATION SEQUENCE:

Tick T0: Signal crosses 21/30 threshold → ALERT state (not entry)

Tick T1-T3 (within 8 seconds):

Requirement A: Price has not retraced more than 0.15% from T0 price

Requirement B: OFI remains in signal direction (no sudden reversal)

Requirement C: Volume on T1-T3 ticks ≥ volume on T0 tick

(acceleration, not deceleration)

If all three met at T3: ENTRY AUTHORIZED

If any fails: Signal downgraded, restart confirmation timer
 If 8 seconds elapse without confirmation: Signal CANCELLED

This 8-second window is deliberate. Institutional momentum moves do not wait 8 seconds — they *persist* for 8 seconds. A fakeout reverses within 3–4 ticks.

2.2 VWAP Deviation Entry Calibration

Optimal entry zone:

For a bullish breakout above VWAP_Upper_Band:

Entry should NOT be at the breakout candle high

Entry is placed at: VWAP_Upper_Band + 0.1% (just above the breakout point)

Why: Breakout entries at the high of the breakout candle often chase the move. Entering at the band itself risks a retest.

The 0.1% buffer confirms the break is real.

Dynamic entry: Use limit order at the calculated entry price

Validity: 5 seconds

If not filled: reject (price has moved too far,
chasing now → adverse fill)

2.3 Institutional Backing Verification

For a move to have institutional backing, two of three must be true:

1. Block trade signature: Any single tick with volume > 5× the session's average per-tick volume → institutional print
2. Options skew shift: Put-Call skew on ATM options must shift in signal direction within the confirmation window
3. Consecutive directional ticks: ≥ 7 of last 10 ticks are buyer-initiated (bull) or seller-initiated (bear) via OFI classification

MODULE 3 — RIDING THE MOMENTUM

3.1 Position Sizing — The Volatility-Adjusted Unit

Never size based on capital percentage alone. Size based on expected move vs. option premium:

Risk_Per_Trade = 1.5% of trading capital (hard cap)

$\text{Max_Loss_Per_Option} = \text{Entry_Premium} \times 0.40$

(you will exit at 40% premium loss – this is your hard stop)

$\text{Contracts} = \text{floor}(\text{Risk_Per_Trade} / (\text{Entry_Premium} \times 0.40 \times \text{lot_size}))$

Example:

Capital: ₹5,00,000

Risk per trade: ₹7,500

Entry premium: ₹80

Hard stop: $\text{₹}80 \times 0.40 = \text{₹}32$ per unit

Lot size: 75

Max loss per lot: $\text{₹}32 \times 75 = \text{₹}2,400$

Contracts: $\text{floor}(7500 / 2400) = 3$ lots

3.2 The Dynamic Trailing Exit Framework

This is the most critical module for options buyers. Static stops get hit by noise; no stops lead to ruin. The trail must respond to both **premium behavior** AND **underlying behavior**.

PHASE 1 – PROTECTION PHASE (Entry to +30% premium gain)

Stop: Hard stop at $\text{Entry_Premium} \times 0.60$ (maximum 40% loss)

Action: No trail yet. Simply protect against catastrophic loss.

Exit condition: Premium drops to 60% of entry price → EXIT IMMEDIATELY

PHASE 2 – MOMENTUM PHASE (+30% to +80% premium gain)

Stop: Trail to breakeven + 5% once +30% is reached

Trail method: Trail stop rises to $(\text{Peak_Premium} \times 0.75)$

This means: if premium hits ₹112 on ₹80 entry (+40%),
stop moves to $\text{₹}112 \times 0.75 = \text{₹}84$ (breakeven protected)

Volume exit signal: If TNVS drops below 1.0 (volume dying) →
tighten trail to $\text{Peak} \times 0.85$

PHASE 3 – ACCELERATION PHASE (+80% premium gain and beyond)

Stop: Trail tightens to $\text{Peak_Premium} \times 0.80$

This locks in 64% of the maximum gain achieved

Volume exhaustion rule: If 3 consecutive ticks show $\text{Vol_Accel} < 0$ →
EXIT NEXT TICK at market (do not wait for stop)

PHASE 4 – EXHAUSTION DETECTION (Override all phases)

If ANY of these fire → EXIT IMMEDIATELY regardless of phase:

a) OFI reversal: Normalized OFI flips direction for 5 consecutive ticks

b) Volume cliff: TNVS drops > 50% in under 60 seconds (volume evaporating)

- c) IV Velocity reversal: IV_Velocity turns negative (IV crush beginning)
- d) Underlying price: Nifty/BankNifty reverses and recrosses VWAP in opposite direction
- e) Bid-ask spread: Spread widens > 1.5% of premium
(market makers widening → smart money exiting)

3.3 Time-Based Exit Rules

Theta decay is not linear intraday – it accelerates in the final hour.

MANDATORY TIME EXITS:

If position entered before 12:00 PM and no Phase 2 reached by 12:30 PM → EXIT (trade thesis has failed; theta eating you alive)

If position still open at 14:45 → EXIT regardless of P&L
(last 45 minutes: theta + liquidity risk + reversal risk)

Maximum position holding time: 45 minutes

If held 45 minutes with profit but no exhaustion signal → Exit 50% of position (book partial, let the rest trail)

3.4 The Partial Profit Harvesting Rule

On strong momentum moves (Phase 3 reached):

At +80% premium gain: Book 33% of position


At +120% premium gain: Book another 33%

Let final 33% trail to exhaustion

Rationale: Options premium moves are not linear. The first 80% of a move may take 8 minutes. The next 40% may take 25 minutes with violent oscillations. Booking partials eliminates the psychological trap of watching a ₹40,000 gain become ₹15,000.

MODULE 4 — THE ARCHITECTURAL WORKFLOW

4.1 System Architecture Overview



| LAYER 1: DATA INGESTION ENGINE |

- Tick normalizer (timestamp alignment, duplicate filter)
- Ring buffer: last 1000 ticks per instrument in RAM
- Snapshot handler: OI chain refreshed on API push
- Latency monitor: flag if tick gap > 500ms



| LAYER 2: SIGNAL COMPUTATION ENGINE (runs every tick) |

- └─ Price Velocity Calculator
- └─ VWAP + Band Calculator (rolling, session-anchored)
- └─ OFI Classifier (bid-ask classification per tick)
- └─ TNVS Calculator (time-normalized volume)
- └─ IV Back-Calculator (Black-Scholes inversion, per tick)
- └─ OI Delta Estimator
- └─ Axis Scorer (Axis 1 + 2 + 3 → composite score)

| Score ≥ 21/30 → ALERT

▼

| LAYER 3: CONFIRMATION & FAKEOUT FILTER |

- └─ 3-Tick Confirmation Timer (8-second window)
- └─ Fakeout Battery (5 rejection tests)
- └─ Spread Toxicity Check
- └─ Time-of-Day Gate
- └─ Theta Runway Validator

| Confirmed → SIGNAL

▼

| LAYER 4: RISK FILTER & POSITION SIZER |


- └─ VIX Regime Check → size multiplier
- └─ Daily loss limit gate (halt if > 3% daily drawdown)
- └─ Max concurrent positions check (hard limit: 2)
- └─ Volatility-adjusted contract calculator
- └─ Entry price limit order generator

| Approved → ORDER

▼

| LAYER 5: ORDER EXECUTION |

- └─ Limit order: Entry price + 0.1% buffer
- └─ Validity: 5 seconds (then cancel)
- └─ Fill confirmation listener



4.2 Latency Budget

Each layer has a hard latency budget. If exceeded, the tick is processed but marked as degraded:

Layer 1 (Ingestion):	< 2ms	
Layer 2 (Signal Comp):	< 8ms	[most compute happens here]
Layer 3 (Confirmation):	< 1ms	[simple logic gates]
Layer 4 (Risk Filter):	< 2ms	
Layer 5 (Order Send):	< 50ms	[API network round trip dominates]
Layer 6 (Exit Engine):	< 5ms	[runs on every tick, must be fast]

Total budget tick-to-order: < 70ms

4.3 Implementation Stack Recommendation

Language: Python (asyncio for WebSocket handling) + NumPy for ring buffers
[Cython compile the inner OFI + IV loops if latency is marginal]

Data Store: In-memory ring buffer (deque with maxlen) – no database writes on the hot path. SQLite write only on trade events.

IV Calc: Pre-compute Black-Scholes IV table for common premium ranges at startup → lookup table instead of real-time Newton-Raphson [reduces Layer 2 from ~8ms to ~2ms]

Scheduling: asyncio event loop with priority queues:
Priority 1: Exit engine ticks (open positions)
Priority 2: Signal computation
Priority 3: Analytics writes

CRITICAL OPERATING RULES

These sit above all logic and cannot be overridden by any signal:

RULE 1 – Daily Loss Circuit Breaker:

If daily P&L < -3% of capital → system goes to OBSERVATION MODE only.
No new entries for the remainder of the session. No exceptions.

RULE 2 – Maximum 2 Concurrent Positions:

Options buying with multiple open positions compounds theta exposure.
Hard limit of 2 simultaneous positions.

RULE 3 – No Signal Stacking:

If one position is in Phase 1 (still unprotected), no new entry is permitted regardless of signal score. Protect before you add.

RULE 4 – Weekly Recalibration:

Every Friday post-close, review the signal quality tracker.
If >60% of signals in a score band (e.g., 21-23) resulted in losses, raise the entry threshold by 1 point for the following week.
The market changes; your thresholds must follow.

RULE 5 – The Silence Rule:

If the engine has not fired a valid signal by 11:30 AM, it is a low-momentum day. Raise the minimum composite threshold to 24/30 for any afternoon signals. Dead markets kill options buyers.

SUMMARY — THE CORE LOGIC IN ONE SENTENCE

Enter only when price is accelerating *faster than normal per unit volume* (not just moving fast), with three times the expected institutional volume for that time of day, while implied volatility is *still rising from a low base* — confirmed by

8 consecutive seconds of non-reversal — and exit the moment any one of volume, OFI direction, or IV velocity turns against you, regardless of where the stop is.

That single discipline, applied mechanically and without discretionary override, is where the edge lives.

Using the above logic build a dashboard to show which strike option call or put will be the best to buy....

Let me read the frontend design skill first before building this.

Reading frontend design skill >

Now I'll build this — a full AI-powered options strike recommendation dashboard that implements the momentum engine logic with live simulation and scoring.

Created a file, read a file >

Here's your **Nifty Momentum Engine Dashboard** — a fully live, tick-simulated implementation of the entire quantitative framework. Here's what's running inside:

What the dashboard does:

Live tick simulation — Generates realistic tick-by-tick price action with trend regimes, momentum cycles, and time-of-day volume profiles (high at open, trough midday, surge at close). Refreshes every 600ms.

3-Axis Scoring Engine (live, every tick):

- **Axis 1** — Price Velocity z-score, VWAP deviation z-score, normalized OFI (Order Flow Imbalance)
- **Axis 2** — Time-Normalized Volume Surge (TNVS), volume acceleration, Directional Conviction Ratio proxy
- **Axis 3** — IV velocity (back-calculated via Black-Scholes inversion), OI delta proxy, VIX regime multiplier

Strike Recommender — Computes ATM, OTM-1, OTM-2, and ITM for the detected direction (CE/PE), with real Black-Scholes premiums, full Greeks (Δ , Γ , Θ , V), breakeven distance, probability of profit, and volatility-adjusted lot sizing.

Fakeout Battery — 5 live filters running every tick, flagging PASS/FAIL in real time.

Exit Phase Tracker — All 4 phases (Protection → Momentum → Acceleration → Exhaustion) with their exact rules displayed.

Controls you can adjust:

- Switch between **NIFTY** / **BANKNIFTY**
- Drag the **VIX slider** (10–30) and watch scores, sizing, and regime flags update live
- Set your **capital** to get precise lot-size recommendations
- Click any **strike card** to expand the full trade plan with entry, stop, targets, and exit rules



Nifty momentum dashboard

Code · JSX

[Download](#)

GUIDE ME TO SET THIS UP. I HAVE CREATED A FOLDER PATH.
C:\sharekhan_terminal\NIFTY MOMEMENTUM DASHBOARD FROM AI

Let me give you a complete, step-by-step setup guide for your exact folder path.
Now I'll build a comprehensive, beautiful setup guide as an interactive widget.

Setup Guide – Nifty Momentum Dashboard

Folder: C:\sharekhan_terminal\NIFTY MOMENTUM DASHBOARD FROM AI

[✓ Install Node.js](#)[Create Project](#)[Add Dashboard File](#)[Edit App.jsx](#)[Clear CSS](#)[Launch Dashboard](#)[Common Errors](#)[Daily Use](#)**2**

Create the React project inside your folder

This sets up the full project skeleton automatically

STEP 1 – OPEN COMMAND PROMPT

Press Windows key + R → type cmd → press Enter

STEP 2 – NAVIGATE TO YOUR FOLDER

```
cd "C:\sharekhan_terminal\NIFTY MOMENTUM DASHBOARD FROM AI"
```

[Copy](#)

STEP 3 – CREATE THE REACT APP (RUN THIS ONCE)

```
npm create vite@latest . -- --template react
npm install
```

[Copy](#)

⚠ The dot (.) at the end means "create the project right here in this folder" – do not remove it. This will take 1-2 minutes.

WHEN IT ASKS QUESTIONS, ANSWER LIKE THIS:

```
✓ Select a framework: > React
✓ Select a variant: > JavaScript
```

✓ When you see "Done. Now run: npm run dev" – the project was created successfully

☐ Ran npm create vite and npm install without errors

[← Previous](#)[Next step →](#)

Here's your complete 8-step interactive guide — click through each step using the "Next step →" button or jump to any step using the pills at the top.

Quick summary of what you need to do:

1. **Install Node.js** — one-time download from nodejs.org (LTS version)
2. **Create the project** — two commands in Command Prompt inside your folder

3. **Drop in your .jsx file** — copy `nifty_momentum_dashboard.jsx` into the `src` folder
4. **Edit App.jsx** — replace its contents with 5 lines that load your dashboard
5. **Clear index.css** — remove the default Vite styles
6. **Run** `npm run dev` — then open `http://localhost:5173` in Chrome
7. **Troubleshoot** — Step 7 covers every common error with exact fixes
8. **Daily use** — Step 8 shows how to launch it in seconds every morning, plus how to create a desktop shortcut

The checkboxes in each step let you track what you've done. Every code block has a **Copy** button so you don't have to type anything manually.

If you get stuck at any specific step, just tell me exactly what error message you see and I'll fix it.

GIVE ME A LINK FOR THE ABOVE CONVERSATION. IT SHOULD CONTAIN EVERYTHING CODES AND ALL. WANT TO SHARE THIS WITH OTHER AI

Unfortunately, I can't generate a shareable link to this conversation — that's not something I have the ability to do. Link sharing is controlled by the Claude.ai interface itself, not by me.

Here's how to get a shareable link yourself:

On Claude.ai (desktop):

1. Look for the **Share** button at the top right of this conversation
2. Click it → it will generate a public link to this full conversation including all code
3. Copy that link and share it

If you don't see a Share button:

- The feature may not be available on your current Claude plan, or it may have been updated since my knowledge cutoff. Check under the conversation's settings/options menu (the three dots ⋮ near the conversation title).

Alternative ways to share everything:

If sharing isn't available, the cleanest options are:

- **Export as PDF** — Right-click anywhere on the page → Print → Save as PDF. Captures all code blocks.

- **Copy the .jsx file** — The dashboard file `nifty_momentum_dashboard.jsx` you downloaded contains the entire working engine. That single file is shareable on its own.
- **Claude.ai support page** — Search `https://support.claude.ai` for "share conversation" to get the most current instructions for your plan.

