EE263 Autumn 2014–15 Sanjay Lall

# Lecture 13 Linear dynamical systems with inputs & outputs

- inputs & outputs: interpretations
- transfer function
- impulse and step responses
- examples


# Inputs & outputs

recall continuous-time time-invariant LDS has form

$$\dot{x} = Ax + Bu, \qquad y = Cx + Du$$

- Ax is called the *drift term* (of  $\dot{x}$ )
- Bu is called the input term (of  $\dot{x}$ )

picture, with  $B \in \mathbf{R}^{2 \times 1}$ :



# Interpretations


write 
$$\dot{x} = Ax + b_1u_1 + \cdots + b_mu_m$$
, where  $B = [b_1 \cdots b_m]$ 

- state derivative is sum of autonomous term (Ax) and one term per input  $(b_iu_i)$
- each input  $u_i$  gives another degree of freedom for  $\dot{x}$  (assuming columns of B independent)

write  $\dot{x}=Ax+Bu$  as  $\dot{x}_i=\tilde{a}_i^Tx+\tilde{b}_i^Tu$ , where  $\tilde{a}_i^T$ ,  $\tilde{b}_i^T$  are the rows of A, B

ullet ith state derivative is linear function of state x and input u


## **Block diagram**



- $A_{ij}$  is gain factor from state  $x_j$  into integrator i
- ullet  $B_{ij}$  is gain factor from input  $u_j$  into integrator i
- ullet  $C_{ij}$  is gain factor from state  $x_j$  into output  $y_i$
- $D_{ij}$  is gain factor from input  $u_j$  into output  $y_i$

interesting when there is structure, e.g., with  $x_1 \in \mathbf{R}^{n_1}$ ,  $x_2 \in \mathbf{R}^{n_2}$ :

$$\frac{d}{dt} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} = \begin{bmatrix} A_{11} & A_{12} \\ 0 & A_{22} \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix} + \begin{bmatrix} B_1 \\ 0 \end{bmatrix} u, \qquad y = \begin{bmatrix} C_1 & C_2 \end{bmatrix} \begin{bmatrix} x_1 \\ x_2 \end{bmatrix}$$



- $x_2$  is not affected by input u, i.e.,  $x_2$  propagates autonomously
- $x_2$  affects y directly and through  $x_1$

#### **Transfer function**

take Laplace transform of  $\dot{x} = Ax + Bu$ :

$$sX(s) - x(0) = AX(s) + BU(s)$$

hence

$$X(s) = (sI - A)^{-1}x(0) + (sI - A)^{-1}BU(s)$$

SO

$$x(t) = e^{tA}x(0) + \int_0^t e^{(t-\tau)A}Bu(\tau) d\tau$$

- $\bullet$   $e^{tA}x(0)$  is the unforced or autonomous response
- ullet  $e^{tA}B$  is called the input-to-state impulse response or impulse matrix
- $(sI-A)^{-1}B$  is called the *input-to-state transfer function* or *transfer matrix*

with y = Cx + Du we have:

$$Y(s) = C(sI - A)^{-1}x(0) + (C(sI - A)^{-1}B + D)U(s)$$

SO

$$y(t) = Ce^{tA}x(0) + \int_0^t Ce^{(t-\tau)A}Bu(\tau) d\tau + Du(t)$$

- ullet output term  $Ce^{tA}x(0)$  due to initial condition
- $H(s) = C(sI A)^{-1}B + D$  is called the *transfer function* or *transfer matrix*
- $h(t) = Ce^{tA}B + D\delta(t)$  is called the *impulse response* or *impulse matrix* ( $\delta$  is the Dirac delta function)

with zero initial condition we have:

$$Y(s) = H(s)U(s), \qquad y = h * u$$

where \* is convolution (of matrix valued functions)

#### intepretation:

•  $H_{ij}$  is transfer function from input  $u_j$  to output  $y_i$ 

## Impulse response

impulse response  $h(t) = Ce^{tA}B + D\delta(t)$ 

with x(0) = 0, y = h \* u, *i.e.*,

$$y_i(t) = \sum_{j=1}^{m} \int_0^t h_{ij}(t-\tau)u_j(\tau) d\tau$$

#### interpretations:

- $h_{ij}(t)$  is impulse response from jth input to ith output
- $h_{ij}(t)$  gives  $y_i(t)$  when  $u(t) = e_j \delta(t)$
- $h_{ij}( au)$  shows how dependent output i is, on what input j was, au seconds ago
- i indexes output; j indexes input;  $\tau$  indexes time lag

## **Step response**

the step response or step matrix is given by

$$s(t) = \int_0^t h(\tau) \ d\tau$$


#### interpretations:

- $s_{ij}(t)$  is step response from jth input to ith output
- $s_{ij}(t)$  gives  $y_i$  when  $u = e_j$  for  $t \ge 0$

for invertible A, we have

$$s(t) = CA^{-1} \left( e^{tA} - I \right) B + D$$

# Example 1



- unit masses, springs, dampers
- $u_1$  is tension between 1st & 2nd masses
- $u_2$  is tension between 2nd & 3rd masses
- $y \in \mathbf{R}^3$  is displacement of masses 1,2,3

$$\bullet \ \ x = \left[ \begin{array}{c} y \\ \dot{y} \end{array} \right]$$


system is:

$$\dot{x} = \begin{bmatrix} 0 & 0 & 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 0 & 0 & 1 \\ -2 & 1 & 0 & -2 & 1 & 0 \\ 1 & -2 & 1 & 1 & -2 & 1 \\ 0 & 1 & -2 & 0 & 1 & -2 \end{bmatrix} x + \begin{bmatrix} 0 & 0 \\ 0 & 0 \\ 1 & 0 \\ -1 & 1 \\ 0 & -1 \end{bmatrix} \begin{bmatrix} u_1 \\ u_2 \end{bmatrix}$$

eigenvalues of A are

$$-1.71 \pm i0.71$$
,  $-1.00 \pm i1.00$ ,  $-0.29 \pm i0.71$ 

## impulse response:




## roughly speaking:

- ullet impulse at  $u_1$  affects third mass less than other two
- ullet impulse at  $u_2$  affects first mass later than other two

## Example 2

#### interconnect circuit:



- $u(t) \in \mathbf{R}$  is input (drive) voltage
- $x_i$  is voltage across  $C_i$
- output is state: y = x
- unit resistors, unit capacitors
- step response matrix shows delay to each node


system is

$$\dot{x} = \begin{bmatrix} -3 & 1 & 1 & 0 \\ 1 & -1 & 0 & 0 \\ 1 & 0 & -2 & 1 \\ 0 & 0 & 1 & -1 \end{bmatrix} x + \begin{bmatrix} 1 \\ 0 \\ 0 \\ 0 \end{bmatrix} u, \qquad y = x$$

eigenvalues of A are

$$-0.17, \quad -0.66, \quad -2.21, \quad -3.96$$

step response matrix  $s(t) \in \mathbf{R}^{4 \times 1}$ :



- shortest delay to  $x_1$ ; longest delay to  $x_4$
- ullet delays pprox 10, consistent with slowest (i.e., dominant) eigenvalue -0.17

# DC or static gain matrix

• transfer function at s=0 is  $H(0)=-CA^{-1}B+D\in\mathbf{R}^{m\times p}$ 

• DC transfer function describes system under *static* conditions, *i.e.*, x, u, y constant:

$$0 = \dot{x} = Ax + Bu, \qquad y = Cx + Du$$

eliminate x to get y = H(0)u

• if system is stable,

$$H(0) = \int_0^\infty h(t) dt = \lim_{t \to \infty} s(t)$$

(recall: 
$$H(s) = \int_0^\infty e^{-st} h(t) \ dt$$
,  $s(t) = \int_0^t h(\tau) \ d\tau$ )

if 
$$u(t) \to u_{\infty} \in \mathbf{R}^m$$
, then  $y(t) \to y_{\infty} \in \mathbf{R}^p$  where  $y_{\infty} = H(0)u_{\infty}$ 

DC gain matrix for example 1 (springs):

$$H(0) = \begin{bmatrix} 1/4 & 1/4 \\ -1/2 & 1/2 \\ -1/4 & -1/4 \end{bmatrix}$$

DC gain matrix for example 2 (RC circuit):

$$H(0) = \begin{bmatrix} 1 \\ 1 \\ 1 \\ 1 \end{bmatrix}$$

(do these make sense?)

# Discretization with piecewise constant inputs

linear system  $\dot{x} = Ax + Bu$ , y = Cx + Du

suppose  $u_d: \mathbf{Z}_+ \to \mathbf{R}^m$  is a sequence, and

$$u(t) = u_d(k)$$
 for  $kh \le t < (k+1)h$ ,  $k = 0, 1, ...$ 

define sequences

$$x_d(k) = x(kh),$$
  $y_d(k) = y(kh),$   $k = 0, 1, ...$ 

- h > 0 is called the *sample interval* (for x and y) or *update interval* (for u)
- u is piecewise constant (called zero-order-hold)
- $x_d$ ,  $y_d$  are sampled versions of x, y

$$x_{d}(k+1) = x((k+1)h)$$

$$= e^{hA}x(kh) + \int_{0}^{h} e^{\tau A}Bu((k+1)h - \tau) d\tau$$

$$= e^{hA}x_{d}(k) + \left(\int_{0}^{h} e^{\tau A} d\tau\right)B u_{d}(k)$$

 $x_d$ ,  $u_d$ , and  $y_d$  satisfy discrete-time LDS equations

$$x_d(k+1) = A_d x_d(k) + B_d u_d(k), y_d(k) = C_d x_d(k) + D_d u_d(k)$$

where

$$A_d = e^{hA}, \qquad B_d = \left(\int_0^h e^{\tau A} d\tau\right) B, \qquad C_d = C, \qquad D_d = D$$

called discretized system

if A is invertible, we can express integral as

$$\int_0^h e^{\tau A} \ d\tau = A^{-1} \left( e^{hA} - I \right)$$

**stability:** if eigenvalues of A are  $\lambda_1, \ldots, \lambda_n$ , then eigenvalues of  $A_d$  are  $e^{h\lambda_1}, \ldots, e^{h\lambda_n}$ 

discretization preserves stability properties since

$$\Re \lambda_i < 0 \Leftrightarrow |e^{h\lambda_i}| < 1$$

for h > 0

## extensions/variations:

- ullet offsets: updates for u and sampling of x, y are offset in time
- multirate:  $u_i$  updated,  $y_i$  sampled at different intervals (usually integer multiples of a common interval h)

both very common in practice

# **Dual system**

the dual system associated with system

$$\dot{x} = Ax + Bu, \qquad y = Cx + Du$$

is given by

$$\dot{z} = A^T z + C^T v, \qquad w = B^T z + D^T v$$

- all matrices are transposed
- role of B and C are swapped

transfer function of dual system:

$$(B^T)(sI - A^T)^{-1}(C^T) + D^T = H(s)^T$$

where 
$$H(s) = C(sI - A)^{-1}B + D$$


(for SISO case, TF of dual is same as original) eigenvalues (hence stability properties) are the same

# Dual via block diagram


in terms of block diagrams, dual is formed by:

- transpose all matrices
- swap inputs and outputs on all boxes
- reverse directions of signal flow arrows
- swap solder joints and summing junctions

## original system:



## dual system:



# **Causality**

interpretation of

$$x(t) = e^{tA}x(0) + \int_0^t e^{(t-\tau)A}Bu(\tau) d\tau$$

$$y(t) = Ce^{tA}x(0) + \int_0^t Ce^{(t-\tau)A}Bu(\tau) d\tau + Du(t)$$

for  $t \geq 0$ :

current state (x(t)) and output (y(t)) depend on past input  $(u(\tau))$  for  $\tau \leq t$ 

i.e., mapping from input to state and output is causal (with fixed initial state)

now consider fixed *final* state x(T): for  $t \leq T$ ,

$$x(t) = e^{(t-T)A}x(T) + \int_T^t e^{(t-\tau)A}Bu(\tau) d\tau,$$

*i.e.*, current state (and output) depend on future input!

so for fixed final condition, same system is anti-causal

#### Idea of state

x(t) is called *state* of system at time t since:

- future output depends only on current state and future input
- future output depends on past input only through current state
- state summarizes effect of past inputs on future output
- state is bridge between past inputs and future outputs

## Change of coordinates

start with LDS  $\dot{x} = Ax + Bu$ , y = Cx + Du

change coordinates in  $\mathbf{R}^n$  to  $\tilde{x}$ , with  $x = T\tilde{x}$ 

then

$$\dot{\tilde{x}} = T^{-1}\dot{x} = T^{-1}(Ax + Bu) = T^{-1}AT\tilde{x} + T^{-1}Bu$$

hence LDS can be expressed as

$$\dot{\tilde{x}} = \tilde{A}\tilde{x} + \tilde{B}u, \qquad y = \tilde{C}\tilde{x} + \tilde{D}u$$

where

$$\tilde{A} = T^{-1}AT, \qquad \tilde{B} = T^{-1}B, \qquad \tilde{C} = CT, \qquad \tilde{D} = D$$

TF is same (since u, y aren't affected):

$$\tilde{C}(sI - \tilde{A})^{-1}\tilde{B} + \tilde{D} = C(sI - A)^{-1}B + D$$

## Standard forms for LDS

can change coordinates to put A in various forms (diagonal, real modal, Jordan . . . )

e.g., to put LDS in diagonal form, find T s.t.


$$T^{-1}AT = \mathbf{diag}(\lambda_1, \dots, \lambda_n)$$

write

$$T^{-1}B = \begin{bmatrix} \tilde{b}_1^T \\ \vdots \\ \tilde{b}_n^T \end{bmatrix}, \qquad CT = \begin{bmatrix} \tilde{c}_1 & \cdots & \tilde{c}_n \end{bmatrix}$$

SO

$$\dot{\tilde{x}}_i = \lambda_i \tilde{x}_i + \tilde{b}_i^T u, \qquad y = \sum_{i=1}^n \tilde{c}_i \tilde{x}_i$$




(here we assume D=0)

## Discrete-time systems

discrete-time LDS:

$$x(t+1) = Ax(t) + Bu(t), \qquad y(t) = Cx(t) + Du(t)$$



- ullet only difference w/cts-time: z instead of s
- interpretation of  $z^{-1}$  block:
  - unit delayor (shifts sequence back in time one epoch)
  - latch (plus small delay to avoid race condition)

we have:

$$x(1) = Ax(0) + Bu(0),$$

$$x(2) = Ax(1) + Bu(1)$$
  
=  $A^2x(0) + ABu(0) + Bu(1)$ ,

and in general, for  $t \in \mathbf{Z}_+$ ,

$$x(t) = A^{t}x(0) + \sum_{\tau=0}^{t-1} A^{(t-1-\tau)}Bu(\tau)$$

hence

$$y(t) = CA^t x(0) + h * u$$

where \* is discrete-time convolution and

$$h(t) = \begin{cases} D, & t = 0 \\ CA^{t-1}B, & t > 0 \end{cases}$$

is the impulse response

#### $\mathcal{Z}$ -transform

suppose  $w \in \mathbf{R}^{p \times q}$  is a sequence (discrete-time signal), i.e.,

$$w: \mathbf{Z}_+ \to \mathbf{R}^{p \times q}$$

recall  $\mathcal{Z}$ -transform  $W = \mathcal{Z}(w)$ :

$$W(z) = \sum_{t=0}^{\infty} z^{-t} w(t)$$

where  $W:D\subseteq \mathbf{C}\to \mathbf{C}^{p\times q}$  (D is domain of W)

time-advanced or shifted signal v:

$$v(t) = w(t+1), t = 0, 1, \dots$$

## $\mathcal{Z}$ -transform of time-advanced signal:

$$V(z) = \sum_{t=0}^{\infty} z^{-t} w(t+1)$$
$$= z \sum_{t=1}^{\infty} z^{-t} w(t)$$
$$= zW(z) - zw(0)$$

#### Discrete-time transfer function

take  $\mathcal{Z}$ -transform of system equations

$$x(t+1) = Ax(t) + Bu(t), \qquad y(t) = Cx(t) + Du(t)$$

yields

$$zX(z) - zx(0) = AX(z) + BU(z), \qquad Y(z) = CX(z) + DU(z)$$

solve for X(z) to get

$$X(z) = (zI - A)^{-1}zx(0) + (zI - A)^{-1}BU(z)$$

(note extra z in first term!)

hence

$$Y(z) = H(z)U(z) + C(zI - A)^{-1}zx(0)$$

where  $H(z)=C(zI-A)^{-1}B+D$  is the discrete-time transfer function note power series expansion of resolvent:

$$(zI - A)^{-1} = z^{-1}I + z^{-2}A + z^{-3}A^2 + \cdots$$