ATTACKDEFENSE LABS COURSES

PENTESTER ACADEMYTOOL BOX PENTESTING

JUNT WORLD-CLASS TRAINERS TRAINING HACKER

PATY RED TEAM LABS ATTACKDEFENSE LABS

TRAINING COURSES ACCESS POINT PENTESTER

TEAM LABS PENTESTY TO THE OLD OF DOLD-CLASS TRAINERS I WORLD-CLASS TRAINING COURSES PAY THE OLD OF DOLD-CLASS TRAINING THAN THE STAINING TO TEAM LAB

ATTACKDEFENSE LABS TRAINING COURSES PENTESTER ACADEM

COURSES TO LABS TRAINING COURSES PENTESTER ACADEM

COURSES TO LABS TRAINING COURSES PENTESTER ACADEM

COURSES TO LABS TRAINING THAN THE STI'

S POINT WORLD-CLASS TRAINERS TRAINING HACKER

TOOL BOX

TOOL BOX

TOOL BOX TOOL BOX WORLD-CI'

WORLD-CLASS TRAINERS TRAINING HACKER

TOOL BOX TOOL BOX WORLD-CI'

WORLD-CLASS TRAINERS RED TEAM

TRAINING CO'

PENTESTER ACADEMY TOOL BOX

TRAINING

Name	Windows: Securing WinRM Service
URL	https://attackdefense.com/challengedetails?cid=2032
Type	Windows Exploitation: Services

Important Note: This document illustrates all the important steps required to complete this lab. This is by no means a comprehensive step-by-step solution for this exercise. This is only provided as a reference to various commands needed to complete this exercise and for your further research on this topic. Also, note that the IP addresses and domain names might be different in your lab.

Note: By default if you are using Windows Server 2012 R2+ then, WinRM service is already up and running. You need to configure the service in order to access it remotely. In this manual we are demonstrating how to secure WinRM service for learning purposes.

Securing WinRM

In this manual we are going to discuss the following points.

- 1. Strong Password for Administrator account
- 2. Configuration of HTTPS listener for WinRM and Disable HTTP listener
- **3.** Dedicated User for WinRM service with minimal privilege.
- **4.** Client side TrustedHosts management
- **5.** Configure host firewall to restrict WinRM access to allow communication only to specific devices.
- **6.** Stop & Disable the WinRM service if not in use. By default it is up and running.

Strong Password for Administrator account

When there is a requirement to configure the WinRM service for remote access, then, it is very important to use strong passwords for all the remote manager users, especially the high privileged ones. This would reduce some amount of risks and when an attacker launches a brute force attack then it would generate a huge amount of noise and we can block/prevent from such attacks by monitoring the log events.

We can use **net** command to change the administrator password if it's a weak one.

Step 1: Changing administrator password.

Command: net user administrator 'aL0{sO5%qK2!IC0:'

PS C:\Users\Administrator> <mark>net</mark> user administrator 'aL0{s05%qK2!1C0:' The command completed successfully.

PS C:\Users\Administrator>

We have successfully changed the administrator password. The password contains Uppercase, Lowercase, Numbers, Symbols. This is just a random password.

Configuration of HTTPS listener and Disable HTTP listener

By default WinRM service is configured on HTTP listener. One can easily sniff the HTTP traffic and get the plaintext credentials. However, we can create a self sign certificate and configure WinRM HTTPS listener which is more secure than HTTP listener and doesn't send plaintext credentials in the network.

Step 1: Removing HTTP listener

Command: winrm delete winrm/config/Listener?Address=*+Transport=HTTP winrm enumerate winrm/config/listener netstat -a

```
PS C:\Users\Administrator> winrm enumerate winrm/config/listener
PS C:\Users\Administrator> netstat -a
Active Connections
 Proto Local Address
                         Foreign Address
 TCP
     0.0.0.0:135
                         server:0
                                           LISTENING
 TCP 0.0.0.0:445
                                           LISTENING
                         server:0
      0.0.0.0:3389
 TCP
                                            LISTENING
                         server:0
 TCP
     0.0.0.0:47001
                                            LISTENING
                        server:0
 TCP
     0.0.0.0:49664
                                           LISTENING
                        server:0
 TCP 0.0.0.0:49665
                        server:0
                                           LISTENING
 TCP
      0.0.0.0:49666
                                           LISTENING
                         server:0
 TCP
      0.0.0.0:49667
                         server:0
                                            LISTENING
 TCP
      0.0.0.0:49668
                         server:0
                                            LISTENING
 TCP
      0.0.0.0:49669
                                            LISTENING
                         server:0
 TCP
       0.0.0.0:49670
                         server:0
                                            LISTENING
```

LISTENING

We can observe that we have successfully deleted the HTTP listener and port 5985 is not listening.

server:0

Note: Check the target machine IP address. In my case it is "10.0.0.88" and remember to replace the below IP with your valid target machine IP address.

Step 2: Generating self sign certificate.

TCP 10.0.0.88:139

Note: We are generating certificates for local setup so we can use the server IP address for DnsName.

Command: New-SelfSignedCertificate -DnsName "10.0.0.88" -CertStoreLocation Cert:\LocalMachine\My

```
PS C:\Users\Administrator> New-SelfSignedCertificate -DnsName "10.0.0.88" -CertStoreLocation Cert:\LocalMachine\My

PSParentPath: Microsoft.PowerShell.Security\Certificate::LocalMachine\My

Thumbprint Subject
------
37E8C8F6C289225DEF8AE1E02A0D6479B4F6AE58 CN=10.0.0.88

PS C:\Users\Administrator> 

PS C:\Users\Administrator>
```



Step 3: Creating a HTTPS winrm listener using "Certificate Thumbprint" and Hostname.

Command: winrm create winrm/config/Listener?Address=*+Transport=HTTPS '@{Hostname="10.0.0.88";

CertificateThumbprint="37E8C8F6C289225DEF8AE1E02A0D6479B4F6AE58"}' netstat -a

```
PS C:\Users\Administrator> winrm create winrm/config/Listener?Address=*+Transport=HTTPS '@{Hostname="10.0.0.88"; Certif
ResourceCreated
   Address = http://schemas.xmlsoap.org/ws/2004/08/addressing/role/anonymous
    ReferenceParameters
       ResourceURI = http://schemas.microsoft.com/wbem/wsman/1/config/listener
       SelectorSet
           Selector: Address = *, Transport = HTTPS
PS C:\Users\Administrator> netstat -a
Active Connections
 Proto Local Address
                               Foreign Address
                                                      State
 TCP
        0.0.0.0:135
                               server:0
                                                      LISTENING
 TCP
        0.0.0.0:445
                               server:0
                                                      LISTENING
                                                      LISTENING
 TCP
        0.0.0.0:3389
                               server:0
 TCP
        0.0.0.0:5986
                               server:0
                                                      LISTENING
  TCP
        0.0.0.0:47001
                               server:0
                                                      LISTENING
        0.0.0.0:49664
                                                      LISTENING
                               server:0
```

Step 3: We need to create a firewall rule to allow 5986 incoming traffic.

Command: New-NetFirewallRule -DisplayName "Windows Remote Management (HTTPS-In)" -Name "WinRMHTTPSIn" -Profile Any -LocalPort 5986 -Protocol TCP -Verbose

```
PS C:\Users\Administrator> New-NetFirewallRule -DisplayName "Windows Remote Management (HTTPS-In)"
Profile Any -LocalPort 5986 -Protocol TCP -Verbose
VERBOSE: New-NetFirewallRule DisplayName: WinRMHTTPSIn
Name
                      : WinRMHTTPSIn
DisplayName
                      : Windows Remote Management (HTTPS-In)
Description
DisplayGroup
Group
Enabled
                      : True
                      : Any
Profile
Platform
                      : {}
                      : Inbound
Direction
Action
                      : Allow
EdgeTraversalPolicy
                     : Block
_ooseSourceMapping
                      : False
LocalOnlyMapping
                      : False
Owner
PrimaryStatus
                      : OK
                      : The rule was parsed successfully from the store. (65536)
Status
                    : NotApplicable
: PersistentStore
EnforcementStatus
PolicyStoreSource
PolicyStoreSourceType : Local
PS C:\Users\Administrator> _
```

The HTTPS listener is up and running.

Dedicated User for WinRM service with minimal privilege.

It is obvious that we can't give an administrator user account access to all the clients. Also, we should not provide normal users with administrator privileges. We should select their role and we should create a group for that specific role and then the users are only able to access those services. i.e Event Log Readers, Performance Monitor, Backup Operators, etc..

We will be creating a normal user i.e **winrmdemo** and adding the user to **Remote Management Users**, **Event Log Readers**.

Remote Management Users:

Members of this group can access WMI resources over management protocols (such as WS-Management via the Windows Remote Management service). This applies only to WMI namespaces that grant access to the user.

Event Log Readers:

Members of this group can read event logs from local machine

Also, please note by default any users which we create on the windows machine using GUI are a member of the "**users**" group. This group restricts users from making any accidental or intentional system-wide changes but these users can run most of the applications.

Step 1: Creating a "winrmdemo" user and adding this user to remote management users and event log readers groups.

Command:

\$secureString = convertto-securestring '@bcDeF_771' -asplaintext -force
New-LocalUser "winrmdemo" -Password \$secureString -FullName "WinRM Demo"
-Description "WinRM Demo Account"

We have successfully, created an user i.e "winrmdemo".

Step 2: Adding user to local group member.

Commands:

Add-LocalGroupMember -Name 'Event Log Readers' -Member 'winrmdemo' Add-LocalGroupMember -Name 'Remote Management Users' -Member 'winrmdemo'

```
PS C:\Users\Administrator> Add-LocalGroupMember -Name 'Event Log Readers' -Member 'winrmdemo'
>> Add-LocalGroupMember -Name 'Remote Management Users' -Member 'winrmdemo'
PS C:\Users\Administrator> _
```

We have added the user in the Remote Management Users and Event Log Readers groups.


We have successfully configured the WinRM service on the remote server.


Step 3: Switch to the attacker machine and connect to the winrm service using winrmdemo user.

Commands:

#Store credentials to \$cred

\$cred = Get-Credential





Connecting to the machine

\$soptions = New-PSSessionOption -SkipCACheck Enter-PSSession -ComputerName 10.0.0.88 -Port 5986 -Credential \$cred -SessionOption \$soptions -UseSSL

```
PS C:\Users\Administrator> $soptions = New-PSSessionOption -SkipCACheck
PS C:\Users\Administrator> Enter-PSSession -ComputerName 10.0.0.88 -Port 5986 -Credential $cred -SessionOption $soptions -UseSSL
[10.0.0.88]: PS C:\Users\winrmdemo\Documents> whoami
server\winrmdemo
[10.0.88]: PS C:\Users\winrmdemo\Documents> =
```

We are connected to the remote server using 'winrmdemo' user over HTTPS listener.

Client side TrustedHosts Management

We do not have to add the remote hosts to our "TrustedHosts" as we are connected to the remote server via HTTPS. It is only required when the remote server is running WinRM service on HTTP listener.

We can verify by running below command on the attacker machine. You could exit the PSSession or run another powershell terminal to execute the below command.

Command: Start-Service winrm

Get-ChildItem WSMan:\localhost\Client\TrustedHosts

```
PS C:\Users\Administrator> Start-Service winrm
PS C:\Users\Administrator> Get-ChildItem WSMan:\localhost\Client\TrustedHosts

WSManConfig: Microsoft.WSMan.Management\WSMan::localhost\Client

Type Name SourceOfValue Value
----
System.String TrustedHosts

PS C:\Users\Administrator> ____
```

We can observe that we have not added any TrustedHost entries.

Configure host firewall to restrict WinRM access to allow communication only to specific machines.

This is the best possible way to block unwanted devices to connect to the WinRM service. This will block any brute force attempt.

We need to modify the firewall rule and we need to add trusted machines IP addresses only for incoming connections to the WinRM service. This way only someone who has that specific IP address eg: "X.X.X.X" only can connect. We can also add subnet instead of single IP addresses.

Please make sure about your attacker machine IP address.

Command: Get-NetFirewallrule -DisplayName 'Windows Remote Management (HTTPS-In)' | Get-NetFirewallAddressFilter | Set-NetFirewallAddressFilter -RemoteAddress 10.0.0.27

Note: The above command would overwrite all existing entries for this rule and add the remote address 10.0.0.27.

```
PS C:\Users\Administrator> Get-NetFirewallrule -DisplayName 'Windows Remote Management (HTTPS-In)' | Get-NetFirewallAddressFilter | Set-NetFirewallAddressFilter -RemoteAddress 10.0.0.27
PS C:\Users\Administrator> _
```

97 05T 0VT 05T 0VT

Now, only the 10.0.0.27 host is allowed to connect to the WinRM service.

Switch to the attacker machine and connect to the server.

```
PS C:\Users\Administrator> Enter-PSSession -ComputerName 10.0.0.88 -Port 5986 -Credential $cred -SessionOption $soptions -UseSSL [10.0.0.88]: PS C:\Users\winrmdemo\Documents> [10.0.0.88]: PS C:\Users\winrmdemo\Documents> _
```

Stop & Disable the WinRM service if not in use

It is always a good practice to disable or remove the WinRM service if it is not in use. We can stop and disable the service using powershell as shown below and run this command on the target machine.

Step 1: Delete HTTP or HTTPS listener

Note: We have already deleted HTTP listener while configuring HTTPS listener, so we are only deleting HTTPS listener now.

Command: winrm delete winrm/config/Listener?Address=*+Transport=HTTPS

Step 2: Stop and disable the WinRM service.

Commands: Stop-Service winrm

Set-Service -Name winrm -StartupType Disabled

Get-Service winrm

```
PS C:\Users\Administrator> Stop-Service winrm
PS C:\Users\Administrator> Set-Service -Name winrm -StartupType Disabled
PS C:\Users\Administrator> Get-Service winrm

Status Name DisplayName
-----
Stopped winrm Windows Remote Management (WS-Manag...

PS C:\Users\Administrator> ____
```

We have successfully stopped and disabled the WinRM service.

References:

- Installation and configuration for Windows Remote Management (https://docs.microsoft.com/en-us/windows/win32/winrm/installation-and-configuration-for-windows-remote-management)
- Enable-PSRemoting
 (https://docs.microsoft.com/en-us/powershell/module/microsoft.powershell.core/enable-psremoting?view=powershell-7)
- WinRM Security
 (https://docs.microsoft.com/en-us/powershell/scripting/learn/remoting/winrmsecurity?vie w=powershell-7)