

# TRAILING-STOP LESSONS — XOM & SPCX

KORNIS PROTOCOL · WORKED EXAMPLES · THE TRAIL IS A LEASH LENGTH, NOT A PRICE

## The formula, once

**Trail value (\$)** =  $1.5 \times (\text{5-minute ATR of the STOCK}) \times \text{your option's delta}$ . It rides that many dollars behind the OPTION's highest price since you placed it — ratcheting up, never down. Use it only AFTER T1 (half off, runner free); from the entry candle it just turns your structural stop into a noise stop. The number is small because it's a distance, not a level — and it scales with the stock's price and volatility, which is why a \$40 stock and a \$160 stock need very different trails.

## LESSON 1 — XOM (calm, penny-wide, ~\$160)

XOM's 5-minute ATR runs about **\$0.25–0.30**. On a 0.70Δ call:

| Delta | 5-min ATR | $1.5 \times \text{ATR} \times \Delta$ | TRAIL VALUE | LIMIT OFFSET |
|-------|-----------|---------------------------------------|-------------|--------------|
| 0.70  | \$0.28    | $1.5 \times 0.28 \times 0.70 = 0.29$  | \$0.30      | \$0.15       |
| 0.60  | \$0.28    | $1.5 \times 0.28 \times 0.60 = 0.25$  | \$0.25      | \$0.15       |

**Fidelity ticket:** Positions → XOM call → Trade → ORDER TYPE → Trailing Stop Limit (\$) → Trail amount **0.30**, Limit offset **0.15** → Day → Preview → Place. Example: option running at \$6.20 → stop sits at \$5.90; option ticks to \$6.80 → stop auto-climbs to \$6.50. It never falls back.

## LESSON 2 — SPCX (wild, wide-ranging, high-beta)

SPCX is a different animal — its ranges are large (14-day ATR has run north of \$20; intraday 5-minute ATR often **\$0.60–1.00**). A \$0.30 trail that's perfect for XOM would get you shaken out on SPCX's normal breathing in seconds. On a 0.70Δ contract:

| Delta | 5-min ATR | $1.5 \times \text{ATR} \times \Delta$ | TRAIL VALUE | LIMIT OFFSET |
|-------|-----------|---------------------------------------|-------------|--------------|
| 0.70  | \$0.70    | $1.5 \times 0.70 \times 0.70 = 0.74$  | \$0.75      | \$0.30       |
| 0.70  | \$1.00    | $1.5 \times 1.00 \times 0.70 = 1.05$  | \$1.05      | \$0.40       |
| 0.60  | \$0.70    | $1.5 \times 0.70 \times 0.60 = 0.63$  | \$0.65      | \$0.30       |

**Fidelity ticket:** same path, Trail amount **\$0.75** (calm day) to **\$1.05** (wild day), Limit offset **\$0.30–0.40**. THE LESSON IN ONE LINE: the trail must be wider than the stock's normal wiggle or the noise stops you out; SPCX wiggles 3× XOM, so its trail is 3× wider. Always size the leash to the animal.

## How to get the real ATR in 10 seconds

Open the Cockpit, pull the ticker — the 5-minute ATR is on THE READ panel and in the status line. Multiply:  $1.5 \times \text{that} \times \text{your delta} = \text{your trail}$ . Or eyeball it: look at the last 5–6 candles; the average height of one candle ≈ the 5-min ATR. Trail = about 1.5 of those candles, converted to option dollars by delta.

Trailing stops: after T1 only. Day orders only (flat by 2:45). The trail is the leash length, not a price. Wider stock = wider trail. Verify the fill behaves in Fidelity before trusting it with size.