19

20

21

22

23

24

25

19 Once the hollowing and finishing have been completed, abrade the inside of the box base. A Velcro pad attached to a bar makes the process easier. Abrade to finish, seal and apply oil finish. Do not abrade the recess for the tenon

20 Now mount the lid section in the scroll chuck. Hollow as for the base section. Try to ensure that the thickness of the wall is the same as the width of the flange inside the lid section. This is not critical but makes for a tidier box. Abrade, seal and finish as for the lid section

21 Now fit the base section into the lid. Your fit should be tight enough for the next stage, but if you are uncertain, wrap the join with masking tape to hold the two halves together. Using a 10mm spindle gouge carefully remove the holding tenon taking light cuts. Make the finished surface slightly concave. Abrade and seal

22 Now remove the box from the chuck. Separate the two halves and mount the lid section in the chuck. Use the box tenon to hold on to – some paper towel will protect the tenon from marking. Do not screw the jaws down too hard here. Using the 10mm spindle gouge remove the holding tenon, taking light cuts from the outside in. The bevel pressure will push the lid towards the chuck which helps to reduce the possibility of knocking the workpiece off the chuck

23 Make a series of decorative 'V' cuts and scorch them using a piece of Formica. You might decide to skip this step and decorate in a different manner, or perhaps not decorate at all. If so, abrade, seal and finish at this point. You can also cut a small chamfer on the top edge here to imitate the end of a threaded bar

24 I chose to pyrograph my usual text on the lid section. The text is blocked out freehand but you could draw it in first if you are not confident doing so. If you are making this box as a gift, perhaps for an engineer, then you could personalise the box with appropriate text

25 Once completed seal the lid section and apply the finish as before. If you wish you can also use a UV sealer on the pyrography to protect it from fading in sunlight. If the fit of the lid is still a little tight then you can gently abrade the tenon to loosen the fit ●

LEFT: Alternative version of the box from a square

WT_287_45_49_ANDY_COATESckbdJRACSD.indd 49 06/11/2015 09:46