5

6

7

8

9


10

11

12

5 Using pull cuts begin to form the final shape of the ogee – a long, lazy 'S' shape when viewed from the side of the blank. Form the foot to the marked diameter, making it about 15mm deep. Continue shaping and aim for the finishing cuts to take you from one reference mark to the other in a single flowing cut. Abrade the finished surface to 400 grit, seal and apply paste wax

6 Remount the blank in the scroll chuck on your prepared tenon. Ensure the blank runs true. The rim should sweep in and down so make light cuts to form the shape, and remove waste behind the cut as required. You can use your bowl gouge on its wing for this series of cuts. Aim for a 4–5mm rim thickness, and a rim width of about 50mm. Do not begin to form the 'bowl' section just yet. The inner material is required as a barrier and support at this stage

7 Using the edge of the long ground bowl gouge round over the rim so that it has a gentle curve. Next abrade the rim and rim edge to 320 grit. Now stop the lathe and run a length of masking tape around the circumference of the rim. Press it down firmly front and back. Then wrap the underside of the bowl in old newspaper and secure firmly with masking tape

8 Take a tool with a sharp point and use the tip to lightly cut through the masking tape about 5mm from the edge of the rim. Peel off the inner ring of tape and you should have a perfectly masked rim section. If not, take another 1mm and repeat until you have. Pat down any lifting edges

9 With the rim and underside protected, you can apply the first coat of paint. Follow the can's guidelines and make light passes, never overloading the surface. Allow to dry and then 'knock it back' with a light pass of 600-grit abrasive. Wipe all the dust away before applying a second coat. You may wish to repeat this step again if necessary. Allow to fully dry/cure. Note the drying times for water-based artists' paints can be longer than for cellulose-based paints

10 As soon as the paint is properly cured begin to remove the tenon and underlying waste wood. Aim for a flat surface which will form a pad of wood raised above the inner edge of the inside rim depth

11 Begin to remove some of the central waste, leaving a band of wood next to the painted rim. Make the band about 12mm wide. It should be about 5–7mm proud of the inner edge of the rim surface. Slightly dish the central surface, but do not form the bowl at this stage

12 Using a 10mm spindle gouge, or a 10mm parting and beading tool, form a bead from the 12mm band you left. You will naturally form 'V' cuts to right and left of the bead. Once completed, abrade the bead to 320 grit taking care not to catch the painted surface

WT_288_45_49_ANDY_COATESckbdmbACSD.indd 47 09/12/2015 13:04