13 Now you need to mask off the painted rim. Take care not to have masking tape adhere to the painted surface. Extend the masking tape over onto the bead, ensuring that it at least covers the outer of the two 'V'-cuts either side of the bead. Mark the outer 'V'-cut with a pencil line

14 Using the sharp corner of your skew chisel carefully cut through the masking tape on the pencil line. Be careful not to let any of the edge of the tool connect with wood either side of the 'V'-cut or it will catch

15 Remove the inner masking tape carefully and press down any lifting edges. You should have a cleanly masked off rim now. Next, increase the size of the inner 'V'-cut using either the skew chisel or a spindle gouge on its side. Be careful not to catch the surface of the bead. Most of the surface created will be turned away later, but this provides material for a frame later

16 Now take your contrasting paint colour and following the guidelines on the can prepare to spray the bead. Don't be tempted to hurry the process by applying too much paint. Repeated thin coats always result in a better finish. You may again wish to apply at least two coats, knocked back with 600 grit between dry coats

17 Using a 2mm parting tool, freshly re-ground, take a careful cut through the masking tape on the outer 'V'-cut at the side of the bead. There's no need to go to deep just yet as you will return here shortly. For now just cut through the masking tape to clean wood

18 Carefully remove the masking tape from the rim section and underside of the bowl. You may find that despite all of your best efforts that there have been leaks of paint, or that the 2mm cut reveals paint that has wicked through the grain to leave a stain. If this is the case re-cut the 2mm section to clean up. Try to aim for a finish that does not require abrading – the chances are you will damage the paint surface while abrading the cut

19 Now you can begin to form the bowl. As ever you can approach this in a number of ways. You can use a pull cut from centre towards the rim, or a push cut from the rim to the centre. Whichever you find easiest is fine. It is often easier to form the bowl using the latter cut, however

20 When you get close to the inner 'V'-cut to the inside of the bead, cut a flat surface, 2–3 mm wide and leave this alone. Then take the 2mm parting tool and make a matching cut to the one you made on the other side to the inside of the bead. You can now begin to hollow out the bowl

13

14

15

16

17

18


19

20



WT_288_45_49_ANDY_COATESckbdmbACSD.indd 48 09/12/2015 13:05