9 Now start to part through the rim, not forgetting to keep this at right angles to the disc and also taking a clearance cut to the right to stop the parting tool binding. When you are almost through the rim listen very carefully as you get close to parting through, once you hear a change in sound, stop the lathe and you should be able to just pull the ring free. It is also advisable to slow the lathe speed down when getting near to depth. It is all too easy to just make one last cut and have something go wrong.

10 Use a sanding wheel in the chuck to sand the inside of the disc to a smooth finish, this will be finished by hand sanding to remove all marks. This surface needs to be as good as the outside

11 The disc needs to be cut in half, I am cutting through on the end grain on the bandsaw, but this could be done with a handsaw just as well. Do make sure that the ring will be cut into equal halves for this design

12 Find the centre of the half, you then need to drill a hole through each half (see 'Marking a hole on a turned circle'). Use a scrap piece of timber to reduce breakout when the drill bit goes through. I used an 8mm drill bit for this. You now need to mount a piece for the base. You could use the centre from the disc but this would waste a lot of timber, so mount a new piece and cut a recess for the chuck. Reverse and clean the edge of the base. Turn a simple ogee with the bowl gouge

13 Use the fluted parting tool to add a bead on the base edge to match the bead on the arms. Sand through all the abrasives grades from 120 to 400, checking that all the marks have been removed, then seal with sanding sealant

14 Mount a piece for the stem between centres and seize the spigot for the base next to the steb centre. Next mark the length for the spigot that will go into the arms sections, these need to be 3mm in length less than the two arms thickness for the cap to fit into the arms. Now turn the basic stem shape. Refine the stem shape by taking a smaller cut. Next, reduce the spigot for the arms down to 8mm in diameter to match the drill diameter. Sand and seal the stem

15 I used a buffing system to finish all parts before assembling them. Be careful to make sure that the arms are at 90° to each other. When gluing to the stem, I made a small cap to fit into the top of the arms just to finish it off

16 The finished candelabra should look something like this ●

9

10

11

12

13

14

15

16

WT_289_87_90_PHILIP_GREENWOOD_bd, MBJRpgS.indd 90 22/12/2015 10:29