INFORMATION AND PLANS

EQUIPMENT USED
Bandsaw
25mm roughing gouge
Bowl gouge – or parting tool or skew
30mm skew chisel
6mm bowl gouge
300 x 100 x 1mm brass and copper sheets
Dividers
Tin snips
Gloves
Heavy duty tailstock centre

TIMBER REQUIREMENTS
Oak – measuring 440 x 120mm

FINISHING OPTIONS

Instead of polishing the candle cup to a high shine, either leave sanded, or as in the picture below, try some Verdigris solution over the surface to give a weathered look. I've sourced the Verdigris solution easily from the internet



1 You can clearly see the glue joints on this blank, which is made up of four offcuts. To drive this blank, I'm using a large four prong drive in the headstock and in the tailstock a standard single point revolving tailstock centre. If you're intending to make a larger candlestick and find that your four prong drive isn't big enough, then there's nothing wrong with using a small faceplate to give you the same result. Make sure you do your checks and that you know the lathe speed before you start. If you have a variable speed lathe then turn the speed to its lowest position and if a fixed speed, then turn down to a low speed to start you off. Also make sure all levers are tight and know that the spindle locks are engaged

1

WT_290_33_37_CANDLESTICK_CW_bdVSmbCW.indd 34 28/01/2016 14:27