9 The circular section should meet the square section at right angles. I used the skew chisel, on its side, as a scraper to get into the corner and clean up the angle between them. I put a layer of plastic insulating tape around the square section to protect the corners in case I caught them accidentally with the skew, but it proved unnecessary

10 With the tricky bit done, use the 13mm gouge to continue rounding over the front section and a cardboard template to guide the cutting. This is fairly straightforward, but don't forget to keep your fingers clear of the square section with its corners whirling around

11 When the shaping of the hemispherical front section is complete, remove the assembly from the lathe and use a knife blade to split the pieces apart. You should find that the paper joints split easily, leaving a thin layer of paper on each face. This results in two identical elm sections, only one of which is needed for the next step

12 Taking one of the elm sections, draw a line between the small corners and use this to find the centre of the curved section. Draw a circle approximately 6–7mm inside the curve to represent the thickness of the bowl. Adjust the position of the centre as necessary to obtain an even wall thickness. When you are satisfied that you have the best bowl centre position, mark it carefully

13 Use another paper joint to mount the bowl block back onto the backplate, placing the tailstock centre on the marked bowl centre to position it correctly. Add a couple of scrap wood support blocks and cramp everything in place until the glue sets

14 Using the 13mm bowl gouge, start to hollow the bowl. The pencil line on the upper surface is a guide to wall thickness. Continue to hollow the bowl until the bulk of the waste has been removed

15 Use the skew, again in scraping mode, to define the outer edge of the bowl and shape it into a slight curve. This continues the bowl shape into the solid part of the block and is important in giving rise to the 'emerging bowl' illusion. Now, complete the turning of the bowl interior

16 Sand the inside of the bowl from 120–400 grit. Split the bowl free from the backplate and use a sanding disc to remove residual paper from any flat surfaces. Using a cork block, finish the flat surfaces from 120–400 grit

9


10

11

12


13

14

15

16

WT_291_51_55_ELM_BC_vsMBbcbdSD.indd 54 24/02/2016 16:22