

EmpowerService Installation Instructions

If you have licensed the EmpowerService you need to install the service on a network server. This is usually the same server on which you installed the EmpowerSupport application.

[Install the Latest Version of EmpowerWin on the EmpowerService Server](#)

Use EmpowerSupport to install the EmpowerWin application on the server.

You need to have the EmpowerWin application installed on the same server as the EmpowerService because the EmpowerService references the EmpowerWin dll files.

Please see the instructions in the document EmpowerNet Installation Instructions for Version Updates for instructions to install the EmpowerWin application.

[Install EmpowerService](#)

- Navigate to the folder in which the latest version of EmpowerWin was downloaded.
- Folder can be found by running the EmpowerSupport application and clicking on the Settings – Location link in the Navigation Panel on the left-hand side of the window.
- Run the EmpowerService MSI file in this folder.
- When the installation begins a welcome screen will be displayed.
- On the welcome screen click Next.
- On the destination folder screen click Next.
- Click Install.
- Click Finish

Edit EmpowerService.exe Config File

- Navigate to the folder in which the EmpowerService was installed.
 - C:\Program Files (x86)\EmpowerNET\2.0\EmpowerService
- Open the file EmpowerService.Exe.Config in Notepad. Change the line:

```
<add key="WorkingDirectory" value="" />
```

By adding the folder in which the EmpowerWin application is installed between the quotation marks.

```
<add key="WorkingDirectory" value="C:\Program Files (x86)\EmpowerNET\2.0\EmpowerWin\" />
```

- Save the file

Copy Empower.Config File to the EmpowerService Folder

- Navigate to the folder in which EmpowerWin is installed on the server.
- Copy the Empower.Config file from that folder into the folder in which EmpowerService is installed.
- You should now have three files in the folder:
 - Empower.config
 - EmpowerService.exe
 - EmpowerService.exe.config

Modify the EmpowerService Service

- Open the Control Panel in Windows, Administrative Tools, Services.
- The EmpowerService.MSI file created a new service: EmpowerService. You may have to refresh the Services to see the new EmpowerService service.
- Right click on the EmpowerService service and select Properties from the pop-up menu.
- Click on the Log On tab.
- Click the Use Account radio button. Set the Account to svc_empowersupport. Enter the password. Go back to the General tab and set the startup parameter to Automatic.
- You need to assign the svc_empowersupport as the Log On account because when it was created it:
 - is assigned Administrative privileges
 - is assigned LogOnAsAService role
 - is a member of the Empower Users Group

Installing EmpowerService for Multiple Databases

Each EmpowerService service runs against a single database – the database specified as the default database in the Empower.config file, residing in the same folder as the EmpowerService.exe being run by the service.

To install EmpowerService for multiple databases, for each additional database

- Follow the “Install EmpowerService” instructions found on page one of this document.
- When you get to the Destination Folder screen, specify a unique folder for that database. As a suggestion, include the database name in the folder name. In the example below, the database name is Main, and EmpowerService is being installed into a folder called EmpowerServiceMain.



- Continue with the “Install EmpowerService” instructions.
- Navigate to the folder in which you installed the initial EmpowerService.
 - Copy the EmpowerService.exe.config file from that folder to the EmpowerService folder for this database.
 - Copy the Empower.config file from that folder to the EmpowerService folder for this database.
- In the folder for this database use Notepad to edit the Empower.config file and change the DefaultConnectionString value shown as xxx below to reference the database name for this database.

```
<add key="DefaultConnectionString" value="xxx" />
```

- Use the Command prompt to manually create this service using the following command:

```
sc.exe create <new_service_name> binPath= "path to the service executable"
```

Using our database Main example, the command would be

```
sc.exe create EmpowerServiceMain binPath= "C:\Program Files  
(x86)\EmpowerNET\2.0\EmpowerServiceMain\EmpowerService.exe"
```

- Follow the “Modify the EmpowerService Service” instructions found on page two of this document to change the Log On account and the startup parameter for this service.

Updating EmpowerWin on the Server that runs the EmpowerService Service(s)

- Because the EmpowerService service uses the EmpowerWin dll files, the EmpowerService won't start unless the correct version of EmpowerWin is installed.
- Every 15 minutes the EmpowerService service looks to see if the database pointed to by its Empower.config file (found in the same folder as the EmpowerService exe), is a different version from the EmpowerWin installed on the server.

If it is, the EmpowerService uninstalls EmpowerWin and reinstalls it. The EmpowerService.exe.config file (found in the same folder as the EmpowerService exe), tells EmpowerService the folder in which to reinstall EmpowerWin.

- When multiple copies of the EmpowerService service are running, it's possible that they will try to uninstall/reinstall EmpowerWin at the same time and not be successful.

Therefore, when running multiple copies of the EmpowerService service it's best to use EmpowerSupport to manually install EmpowerWin on the server running the EmpowerService services each time you upgrade your Empower databases. After installing EmpowerWin on that server, confirm that the EmpowerService services are all running.