DCS SORTIE STARTER

USER GUIDE

Pick a map, an era, and an aircraft — fly a living world in minutes.
Airfields dressed. SAMs up. The strike group at sea. Your flight plan stays yours.

VERSION 1.123.0
Developed by Authentic Media LLC · robgrady.com · provided as-is - no warranty, no liability ·

Select, don't search. Get a living DCS mission with period-inspired settings in under a minute — no editor, no Lua. We set the stage, you write the play: you are never handed a flight plan you did not ask for. Author an exact route when you want to plan it yourself. Waypoints appear only where the mission itself calls for them: a routed strike (the strike templates), a curated training ride whose printed syllabus IS the flight plan (the White Knights rides carry the squadron's own route, because the route is the lesson), or the **Automatic waypoints** tickbox you switch on yourself, or an **authored route** you enter in Builder.

The four doors

While mission options load, the page shows a loading notice. You can select a door immediately; it opens when the catalog is ready. If loading fails, choose **Retry**. Your selected destination is retained.

Fly Now — the fastest path. One screen, three picks: what do you want to practice (Tanker Time, BFM Merge, Kill the Guns, Beat the SAM), in what, and where. Era, base, weather and comms are derived for you; a single "spice" notch sets the opposition (calm / realistic / hostile) and the re-rolls a fresh layout of the same picks. Tanker Time and BFM Merge start you **airborne** — behind the tanker at its assigned block, or in your chosen BFM geometry.

Library — find individual **Missions** or multi-mission **Collections**. Search titles, aircraft/nicknames, maps, activities and collection mission names. Expand **Filters & sort** for aircraft, map, era, activity, mission setup and **Threat** (opposition intensity, not pilot skill). Three featured picks appear when unfiltered; each appears only once. Collection cards show their mission count and fixed requirements.

Use **My DCS content** to declare installed maps, aircraft and additional modules such as Supercarrier. These preferences stay on this device. **Compatible with my content** checks all requirements of a fixed collection; unknown or incomplete requirements remain unconfirmed and are excluded. For configurable missions, it looks for a matching aircraft, era and map and opens that combination in the detail view. Changing those selections refreshes the summary. Generate from the detail or **Customize in Builder**. Use **Save to My missions** to keep this selection for later; **My missions** is also available at the top of Library. Ownership is your declaration, not an inspection of your DCS installation.

A collection download contains its authored missions and does not change with Builder selections. The detail lists the flying sequence and separate Mission and Briefing links. Historical dates, classifications and sources remain in the setting disclosure. **Train** organizes the same rides into a learning sequence and records progress in this browser.

Train — the Training Pipeline. Learn it, fly it, fight it. Three schools in the order every air force runs them: Ground School and UPT (the history chapter, then fly an airplane — formation, timing, the tanker, in any jet), FRS — Know Your Jet (the contact phase, systems, the squadron's tactical checkout, weapons, and a check ride), MQT — Fight the Jet (employment). Every ride is a generated Library mission with its brief and kneeboard; where the Mission Editor can see what you are doing it grades you and opens a scorecard, and where it cannot the card says so. Units that are not built yet are shown as **planned**, with the reason. Tick units done as you fly them to the standard on their brief — the record lives in your browser and nowhere else. A virtual squadron takes the **squadron kit** (printed program, a gradesheet with one row per ride, the readings) and downloads the missions from each track. The first course is the F-4E Phantom II.

Builder — the full wizard. Theater, era, coalition, aircraft, airfield dressing, the Threat Dial (including the guns-only tier: AAA belts, zero SAMs), support, corridors, map graphics — everything, in seven screens.

Mission readiness before Generate

Builder's Review, configurable Library mission details and Fly Now show a **Mission readiness** card. It checks the effective recipe and lists terrain, player aircraft and known ship-module requirements. **Your content** compares these requirements with your declaration in Library → My DCS content; it cannot inspect your installation. It identifies human aircraft and veteran AI wingmen, or says an authored flight will be counted after generation. Aircraft counts exclude cockpit crew positions; use the mission briefing and module's join instructions for a human crewmate.

Ground departures show size-compatible stands before allocation and the number with measured static-aircraft directions. Remaining stands use field or geometric defaults. These measurements govern statics, not player taxi behavior; generation still allocates parking and may select a different friendly field when required. Carrier deck allocation happens during generation. Stores are composed then; inspect **Your loadout** in the resulting Mission Kit.

Selection checked does not mean the sortie was flown. The card names the app release and explicitly marks DCS flight validation **unverified**. AI/support assets, installed module versions and every mod dependency are not fully certified. Read generation warnings and DCS load warnings. A failed setup check explains which selection needs correction. If the check is unavailable, Generate still performs the engine's compatibility checks.

Your mission kit

Every generate ends with the **Mission Kit**: the `.miz` (with its install path), the **briefing pack** (a PDF — SITUATION/MISSION/EXECUTION brief, theater chart with the numbered threat order of battle, comms/nav card with diverts and fuel boxes — plus Markdown for Discord), the **kneeboard** riding in-jet (RShift+K: comms card, airfield data, theater overview with the live threat rings), the loaded **flight plan** on routed strike missions, and the **DTC setup card** for the F-14B(U). On the **Nevada map the flight plan is threaded through the Nellis corridors** — the FLEX turnout, the Sally Corridor or the Alamo Corridor to the north ranges, FYTTR and Indian Springs to the south range, the west road round the Box, and a published recovery home — with the corridors and gates drawn on the F10 map and briefed with their sources. On the **Syria map** the same standard applies — the Levant corridors: from the Galilee fields up the coast and over the Bekaa, or J14 to Rosh Pina and over Hermon; from Akrotiri the SIDs to IREFA and the sea road to NIKAS; from Incirlik the W74 Northern Watch road and the Hatay and Kilis gates; from Muwaffaq Salti the Amman TMA and L200 to Al-Tanf — with a Levant chart in the kneeboard and the brief. On **Cold War Germany** (Cold War era only) it is the Central Region of 1985, either side of the line: from the Eifel, the Hunsrück, the Pfalz and Rhein-Main over the Taunus to the Low Level Transit Routes through the HAWK belt — the Fulda Gap at Point Alpha, the Werra at Herleshausen, the Harz road to Helmstedt, the Hof corridor; from the Rhineland and the Weser the A2 to Helmstedt and the Heath to the Elbe crossings; and, flying red, from the Berlin ring, Merseburg or Parchim along the GDR's own flight lines to the same six gates. The ADIZ, the HAWK and Nike belts, the Berlin corridors, the LFAs and the ranges are on the chart.

Formation: the position ladder

The formation stages put a small card on the LEFT of your screen at eye level — the same side lead is on, clear of the comms menu and the message log — that names the one input to make: **HOLD**, **ADD POWER**, **EASE OFF**, **COME UP**, **COME DOWN**, **OPEN OUT**, **REJOIN**, and **STEADY**, which means "you are out of position but already closing at the right rate, so add nothing". Read it with the edge of your vision; you should never have to leave lead to use it. A ladder at the top shows your range — CLOSE, SLOT, OUT, LOST. It cannot show left/right (the mission measures range from lead, not which side you are on), so lateral comes from the sight picture. Turn it

off any time with F10 → FORMATION: turn the position ladder OFF.

Can't see it? F10 → FORMATION: show the position ladder now draws one immediately. Do that on the ramp before you take off: if a card appears, the ladder is working and will follow you all sortie; if nothing appears, the picture is not rendering on your machine and the sortie is not the place to find that out. While the ladder is fitted, lead stops nagging you in the corner — the card says it, so the text does not repeat it.

Lead also waits for you: at the first two route points he orbits until you have been in the slot for fifteen seconds, then flies the profile. He gives up after a few minutes and goes anyway. Neither happens on a check ride.

Discord profiles and My missions

Sign-in is optional: Fly now, Library, Train and Builder still work as a guest. Choose **Sign in** in the header, then **Continue with Discord**. Discord asks for your basic identity; we do not request your email, server memberships or permission to post. We store your Discord ID, a stable Sortie Starter profile ID and profile name. This login currently applies to Sortie Starter; it does not automatically sign you into other Authentic applications.

Use **Save to My missions** in Library details, Builder Review or Fly Now before generating. A collection also has a **Save** button beside each mission. Signing in is required to save to your profile. If you click Save as a guest, continue with Discord in the same tab; we finish that specific save after you return, provided session storage is available and you return within ten minutes. If browser storage is blocked, sign in first, select the mission again and click Save. Cancelling sign-in does not save the selection.

Open **My missions** in the header or Library, or bookmark **/my-missions**. This is your personal page. Search by mission name, aircraft or map; filter **All missions**, **Original files**, **Saved setups**, **Library picks** or **Shared**, and sort by save date or mission name. Use the **Map** and **Aircraft** dropdowns together to narrow the list; search and mission-type filters still apply. **Clear search and filters** resets all filters when no missions match. Library picks use their published collection's declared map and aircraft requirements; these can cover several maps or aircraft and do not certify a specific aircraft in every sortie. Missing metadata appears as **Not specified**. Shared pages offer the same filters when they contain multiple missions. Saving from the Library or Builder keeps you where you are and shows a **View My missions** link.

Original files are retained `.miz` and matching **Mission Kit** downloads, kept as generated even after an app upgrade. **Saved setups** hold settings and seed; **Open in Builder** generates with the current app/content. **Library picks** reference authored missions or collections; their downloads use the current published version. The selected version is shown under the card's additional details. A reference is not a retained copy of that publication; removed content may be unavailable. Choose **Rename** directly on a card, enter a descriptive mission name (up to 80 characters), then **Save name**. The new name follows that saved item and its shared page; original files, settings and existing share links stay the same. Use **More actions → Remove** to remove an item. Removing an original deletes its retained files. An unsaved result's **Save settings** keeps its captured recipe, not the downloaded original file.

Share a mission or your page

Everything starts **Private**. On a card, choose **Share**, review what will be visible, then **Create share link** and **Copy link**. Anyone with the link can see your profile name and that mission's settings or files without signing in. They can open a setup in Builder or download the shared original/published content. Other private saves stay hidden. Paste the link into Discord or a message yourself; the app does not post to Discord.

Choose **Share my page → Enable shared page** to create your personal link. This unlisted page contains **only missions you have explicitly shared**. Enabling an empty page does not publish private saves or automatically share future saves. Use **Manage page link** to copy or preview the page later. Shared pages are not listed in a public directory and request that search engines do not index them; the link can still be forwarded to anyone.

Use **Manage link → Stop sharing this mission** to stop an individual link. **Manage page link → Stop all sharing** stops the page and every individual link. Creating new links later does not reactivate old ones. Removing a mission or deleting your profile also stops its links. Files already downloaded cannot be recalled. Builder recipe links and public Library downloads remain separate from these revocable profile links.

Profile and saving settings

On your My missions page, open **Settings**, edit your profile name and use **Save profile**. This name appears on content you choose to share. **Save newly generated missions on this browser** is enabled initially. Turn it off to download without retaining files. If browser storage is blocked and the preference cannot be retained, the interface reports that; sign out to generate as a guest without saving. Signing out ends this browser's session; sessions expire after 30 days. Cancelling sign-in leaves guest generation available.

With saving enabled, Generate from Fly now, a configurable Library mission or Builder stores the `.miz`, its resolved settings, release and matching Mission Kit from the same build. The Kit includes available briefing and kneeboard pages. Repeating an identical generation within a release reuses the archive. Authored collection downloads and downloads made before signing in are not automatically copied into the original-file archive.

You can keep 100 saved selections plus 100 original missions or 100 MB of original mission/Kit storage per profile. If a save fails or space is full, keep your download, remove an item and retry. A failed save is not confirmation of an archive. **Export settings** downloads profile and mission metadata and recipes as JSON; download original files separately. **Delete profile** removes this app's profile, saves, sessions and shared links. Download originals first. This does not delete your Discord account or data in another Authentic app.

Quick start (Builder path)

1. Pick a **map** and an **era**. The era is a hard filter: a WWII starter will not offer you a Hornet, and a modern starter will not offer a Spitfire.
2. Pick **who's flying** (just you, or a 2-4 ship), your side, home airfield, and aircraft. Choose **Veteran AI wingmen** to replace some human seats with AI pilots in your flight.
3. Toggle **building blocks** (everything is optional — defaults are sensible).
4. **Generate** — your Mission Kit appears and the `.miz` downloads. Drop it in `Saved Games/DCS/Missions/` and fly, or open it in the Mission Editor.
5. **Share** — "Copy share link" regenerates this exact mission for anyone: the same recipe + seed reproduces the mission within the same generator release.

Privacy note: we count what missions get generated (map, aircraft, mission type) to decide what to build next — never who generated them.

Flying with veteran AI wingmen

In **Builder → Flight → Who's flying**, choose **4-ship** and set **Veteran AI wingmen** to **3** for your aircraft plus three AI wingmen. This creates a single-player mission: put the `.miz` in `Saved Games/DCS/Missions/` and fly. The wingmen use DCS **High** skill, the level labelled veteran here, and belong to your own flight. Use the

wingman radio menu to command them.

For a two- or three-ship, you can likewise assign up to one or two AI wingmen. If two or more aircraft remain human seats, they are multiplayer clients; host the mission through **Multiplayer → New Server**. Leave the AI count at **None — human seats** to keep the existing multiplayer setup. Reducing flight size reduces the AI count as needed to retain at least one human aircraft. Share links and saved Builder settings retain this choice.

All aircraft in the flight use the selected airframe and loadout. AI wingmen follow native DCS behavior; this option does not script attack geometry or formation procedures. Fixed crew-ops flights and authored Case III recovery rides do not offer this option. Existing training rides retain their authored wingmen when no custom AI count is selected.

The standard comm ladder

Every starter uses the same predefined comms, so learn it once:

Ch	Agency	Callsign	Freq (UHF)	TACAN	Notes
1	Your flight	(varies)	305.725	—	flight common — DCS loads it on CH 1
2	Carrier	Mother	264.425	71X	ICLS 11 · Link4 336 · ACLS on
3	AWACS	Overlord	251.475	—	land-based E-3/A-50
4	Tanker	Texaco	253.625	39Y	speeds/altitudes per type
5	Plane guard	Angel	262.050	—	carrier flight ops
6	CAP	(squadron)	258.175	—	carrier air wing
7	Tactical	—	254.325	—	inter-flight coordination
8	AEW Hawkeye	(squadron)	259.925	—	carrier air wing (CH 3 when there is no AWACS)
last	Guard	—	243.000	—	monitored — fixed by regulation
—	FARPs	(name)	127.525+	—	0.25 steps per pad

The same ladder is printed on the in-jet **kneeboard** (comms card page) and in the mission briefing, and it is loaded into every UHF preset radio the jet has (both sets in an F-14 or a Hornet). All carrier systems are

pre-activated: TACAN 71X "STN", ICLS channel 11, Link4 on 336, and ACLS — tune and go.

Your own comm plan

Squadrons have their own SOP. In the Builder, **Support & presentation → Comm plan** shows the ladder as a table: a Default column and a This mission column. Leave it alone and nothing changes. Overwrite a cell and everything that prints or programs that frequency follows — the tanker's own radio, the AWACS, the boat, the cockpit presets, the card, the kneeboard and the F-14B(U) DTC page — and the card marks the row custom.

What the table refuses, and why: **Guard** is 243.000 by regulation and cannot be moved; a frequency **off the 25 kHz raster** (253.630) is refused with the nearest channel named, because no radio can tune it; a frequency **outside UHF 225–400** is refused unless the aircraft's own radios reach it (a Mustang's VHF flight frequency is fine for a Mustang). Two rows on one frequency are allowed with a warning — co-channel is legal, sometimes intended, often a slip. **Channels are fixed**: that is what makes the plan learnable across every starter.

Profiles save a set of overrides in this browser under a name ("Squadron SOP") and fill the table on demand. The overrides ride in the recipe, so a **share link** reproduces the mission with the custom plan — the wingman does not need the profile. Copy JSON gives the overrides as a `comms` block for the API (`{"comms": {"tanker": 271.5}}`).

Building blocks

• **Airfield dressing** — era/faction-correct static aircraft on real parking stands,

ground support equipment, fuel farms, tents, comms towers. Density: sparse/normal/busy.

• **Air defenses** — complete, functional SAM sites with doctrinal layouts (SA-2/3/6/11,

Hawk, Patriot by era/side) plus SHORAD at fields. WWII gets flak, not SAMs, and the **War on Terror** era gets no SAMs at all — the threat there is truck-mounted and emplaced guns, dense and low, and the Threat Dial scales the gun line.

• **Enemy air** — CAP flights and the BFM adversary spawn with an era- and

role-correct weapons fit: a 1978 MiG-21 carries R-13Ms and R-60s, a modern MiG-29S carries R-27ERs, R-77s and R-73s. You never pick the enemy's loadout — era and mission type imply it — but you are always told what it is. Look for the **ENEMY AIR** block on the theater chart and on the in-jet kneeboard: it names the fit and what it means for how you fight him. At Threat Dial intensity 1–2 the bandits carry a lighter fit, so the dial changes the character of the fight and not only the head count.

• **Tanker / AWACS** — on station behind friendly lines with the standard freqs above.

Not available in WWII (no AAR or AWACS in 1944 — the era gate is strict). In the **War on Terror** era there is no red AWACS, because there is no red air force.

• **Carrier strike group** — see below.

• **Ambient air traffic** — AI transports starting up and flying between friendly fields.

• **Pattern traffic** — AI aircraft recovering into, or departing from, your own

field at mission start (landing / takeoff / both; fighters, cargo, helicopters or mixed; up to 8 aircraft). Formation departures — departing aircraft lining up on the runway and rolling as two-ship sections, using DCS 2.9.30's AI runway line-up — appears here once the feature's encoding has been verified against a Mission-Editor-saved file; until then the option is not offered rather than offered and ignored.

• **Functional FARPs** — pads with the fuel/ammo/command/comms vehicles required for rearm/refuel to actually work.

• **Strike targets** — depot / convoy / C2 packages in the enemy rear, each with a trigger zone ready for your own mission logic.

• **Practice range** — bombing ring and strafe line in the friendly rear.

• **Nav kneeboard** — comms card, airfield data (runways, stands), and a theater overview schematic, rendered into the jet's kneeboard.

The carrier strike group

Pick a hull and you get its **real strike group**: the Roosevelt sails as CSG-9 with USS Lake Erie (CG-70) and DESRON 23 destroyers; the Truman as CSG-8 with USS Gettysburg; the Forrestal as a 1980s Med battle group with USS Ticonderoga. Screen stations follow doctrine: plane-guard destroyer astern, AAW cruiser on the beam, pickets on the bow quarters. The group steams into wind on BRC.

Iraq also supports carriers in the Gulf. In Builder, enable Carrier strike group and select **CARRIER** as home base for a carrier-capable aircraft. The authored position is offshore at 28.8°N / 49.65°E; the steaming heading stays within the checked sea-room window. Regional scenery detail varies. The strike group is a training adaptation, not a verified naval deployment; Cold War coalition assignment does not imply Iraqi ownership of a US carrier. Optional strike waypoints and their timed package originate at the carrier and use its ship-linked recovery point. Native mission and geographic checks are complete; a DCS flight check remains.

Deck configuration follows real spotting practice:

• **Recovery** — the landing area is clear (angle, waist cats, EL4, port stern); the bow is packed in tight uniform herringbone rows across the cat tracks, E-2s nose-out on the point, helos in the corral.

• **Launch** — cats, JBDs, and taxi flow clear; spares spotted aft.

• **Packed** — port-visit deck, everything fouled including the angle. No-fly.

Check the aircraft types you want on deck; rows are spotted one squadron per row. Deck equipment (tugs, MJ-1 loaders, crash gear) sits at real stations. Optionally launch the air wing's **CAP** (2-ship on the threat axis at 25k, e.g. VFA-146 Blue Diamonds) and **E-2 Hawkeye** AEW orbit covering the force.

Template packs

• **Crew Ops: Jester IZLID Strike (F-14B(U), pilot seat)** — you fly; Jester operates the back seat. Run designation from the F10 CREW menu: start the IZLID, confirm its effect, then cease. Progress is player-paced.

• **Crew Ops: Iceman GCI Intercept (F-14B(U), RIO seat)** — command the AI pilot from the F10 CREW menu while running the intercept from the pit.

• **RIO Fleet Defense (F-14A/B)** — use the cockpit Iceman menu in solo play, or fly with a human crewmate. It does not use the B(U) mission-command API.

The F-4E training rides are a separate course; these F-14 crew-command features do not apply to the Phantom.

Templates are one of the places waypoints appear (the AI pilot needs steerpoints to fly). The second is a **curated training ride** — the White Knights rides carry the squadron's own route automatically, since flying that exact ground track is the lesson. The third is **Automatic waypoints**, the tickbox on the Targets screen — off unless you turn it on, and it builds WP1 → IP → TARGET → home with a kneeboard leg card to fly it off.

Authoring your flight plan (v1.123.0)

Open **Builder → Support & presentation → Your flight plan** and choose **Author an exact route**. Add up to 32 waypoints after the aircraft start. Select a numbered marker or list row to edit its name, coordinates, altitude and speed. Click the schematic or drag a marker to move the selected point. Use **Move up**, **Move down**, **Delete point** and **Undo** to revise it. Choose **Fit route** to zoom around your points or **Show theatre** to return. The schematic loads only when needed and shows airfields and the map's coordinate envelope; it contains no terrain, threats or historical boundaries. Changing the map retains your coordinates; review any out-of-bounds errors. Builder context changes retain your route; opening another Library mission replaces the recipe.

Builder displays **feet MSL** and **knots TAS**. Coordinates accept decimal latitude/longitude or DCS theatre metres (X north, Y east). The API/MCP stores altitude in **metres MSL/BARO** and speed in **metres per second TAS**. AGL, MGRS entry and IAS conversion are not included in this release. The start point remains separate; adding a route does not set your starting position.

Choose **End at last waypoint**, **Recover at home** (airfield or carrier), or a named map airfield. Recovery adds a native landing point; it does not design an instrument approach, grant access to an enemy field or check carrier sea room. Purpose labels (Transit, Rendezvous, Initial point, Target reference, Egress) add no tasks, target groups or triggers. Fixed training routes reject overrides. Author-defined routes are labelled as not historically source-verified; a reconstruction becomes an adaptation. Custom points replace template transit routing and require Automatic waypoints to be off. Guided route generation is a later feature.

Routes survive share links, local restore and saving the recipe to My missions. The mission, downloadable navigation data, brief and paginated kneeboard carry the authored route. Supported F-14B(U) cartridges carry route coordinates; aircraft-specific navigation capacity and cartridge altitude loading still require DCS verification. Waypoint ETAs are advisory estimates from distance and requested TAS, excluding wind/climb allowance; no automatic timing coach, package or arrival-time locks are added. Review terrain clearance and aircraft performance in DCS. Existing missions keep their previous routing by default.

Uploading an authored mission pack

Site operators can open **Admin → Mission packs** and upload a `.sspack`, a ZIP of missions, or one `.miz` (maximum 256 MB). A successful upload opens the review page; check its title, prerequisites, flying order and descriptions, then choose **Save and publish**. Keep a local copy of the original pack.

Server storage is full/unavailable means the server could not save the pack; it does not establish that the archive is invalid. Ask the site operator to restore capacity or access, then retry. A failed review save keeps your submitted fields on the returned page. For a failed upload, select the file again after storage is restored. Format and checksum errors are reported separately and need the archive corrected.

Share links & recipes

A starter is defined by its **recipe** (your wizard selections + a seed). Share links encode the recipe, not the file. Within one generator release, the same recipe and seed reproduce the same mission. Later releases may correct content or update DCS compatibility while retaining the recipe; keep the downloaded `.miz` when you

need an exact archived mission. Change the seed to reroll the details while keeping your selections.

Missions through an AI assistant (MCP)

An MCP-compatible assistant can connect to **https://sortiestarter.com/mcp/** using **Streamable HTTP**. Add this URL as a remote MCP server in your assistant's settings; configuration names vary by client. Sortie Starter's public tools do not require a login. The public agent guide is available at **/api/mcp-guide**, indexed by **/llms.txt**, and as the MCP resource **sortiestarter://integration-guide**. Existing connections to **https://dcs-mission-starter.fly.dev/mcp/** also work. Leave authentication unset and refresh/reconnect the server if the assistant cannot list tools. Starting with **v1.121.1**, both `/mcp` and `/mcp/` work directly without redirects, including when a host removes the saved URL's trailing slash. Opening the website directly does not check its MCP connection. The agent guide includes Grok configuration and HTTP error troubleshooting. Starting in **v1.120.1**, the tool list uses compact input shapes and omits output schemas, nullable unions and conditional rules for connector compatibility. The full schema is still available through the schema tool/resource, and recipe validation and structured tool results are preserved. Omit unused optional fields rather than filling the tool input with nulls. Reconnect and confirm the reported version; server checks alone do not establish that a particular assistant app loaded its connector.

Ask the assistant to search the catalog, inspect a mission's requirements, validate your selections, and generate a mission. For example: "Build a modern Caucasus F-16 four-ship with three veteran AI wingmen and a kneeboard." You still need to own the relevant DCS map and aircraft modules.

Generation returns a mission manifest plus links to the **mission .miz** and **full mission kit ZIP**. Download and unzip the kit, then put `mission.miz` in `Saved Games/DCS/Missions/`. Use single-player for native Player aircraft and multiplayer for native Client aircraft (two or more human aircraft use Client automatically). Available briefs, kneeboard PNGs, DTC setup card, `comms.json`, and `navigation.json` accompany the mission. DTC files are supplied only when the selected aircraft supports them and rendering succeeds. Check the manifest's file list and warnings.

Links regenerate the recipe on the stated app version and check its native mission checksum. If mission content changes, ask for fresh links. After a deployment, a link from an older version returns "another app version"; ask the assistant to generate fresh links. Keep downloaded files for an exact archive. A busy generator asks you to retry after three seconds. Recipe validation checks fields, map-position envelopes and template defaults; generation makes the final compatibility checks.

The assistant's recipe schema includes numeric limits and the human-seat rule: **1–4 aircraft**, with **0–3 veteran AI wingmen** and always at least one human aircraft. Other bounds include parking fill (0–100%), pattern traffic (1–8), threat intensity (1–5) and timing hold (0–15 minutes). Fixed crew-ops and Case III rides still refuse custom veteran wingmen. Validate the selected recipe before generation; these limits do not replace the final compatibility checks.

Assistants can set exact authoring fields: **start_position**, **mission_date**, **start_altitude**, **start_speed**, **start_time**, **player_stores**, **player_slot** and **map_view**. Position accepts latitude/longitude in decimal degrees or native DCS x/y metres. Altitude is **metres above mean sea level**, not feet or height above terrain. Both require an ordinary airborne start and preserve the flight's spacing. Fixed training and carrier starts reject conflicting geometry. Check terrain clearance in DCS before flying. Starting with v1.121.0, the map catalog publishes the DCS x/y authoring envelope used by both validation and generation. It includes known airfields and carrier anchors and corrects reversed/outdated vendor rectangles. It does not certify the DCS terrain edge or high-detail coverage.

The exact date must fall inside the selected era and use takeoff-anchored timing. It changes the native mission and historical date; coalition/base presets and historical overlays remain era-based, with an adaptation note when the date changes. Player slot selects native **Player** (one human aircraft) or **Client** (multiplayer, including one human); it does not select a cockpit seat or aircraft number. Fixed Case III, formation and crew flights keep their authored seating. Map view sets saved center/zoom and F10 unit visibility; graphics layers remain separate. These advanced fields currently use the agent/API recipe, survive Builder share links, and have no dedicated Builder controls. The public MCP guide includes the full units, limits and an example. Native-file checks do not replace a DCS flight check.

Starting with v1.122.0, **start_speed** specifies airborne true airspeed in **metres per second**, rather than knots or indicated airspeed. Multiply knots by 0.5144444444. **start_time** specifies the local mission start clock as `HH:MM` or `HH:MM:SS`, with takeoff-anchored timing. It overrides the time-of-day preset and preserves the selected date. Speed requires a normal airborne start; fixed training and carrier starts retain their own geometry. Check the aircraft's flight envelope before flying.

player_stores maps station numbers (as strings) to exact store IDs from the aircraft-scoped **stores** catalog. It replaces the whole flight's external fit; omitted stations stay empty, and an empty object means clean. It requires arming enabled and the automatic fit mode; fixed training fits cannot be overridden. Known weapon service dates are enforced. Set **allow_anachronistic_stores** to true only for a deliberate fictional fit: the date remains unchanged, the historical context becomes **Fictional exercise**, and the mission reports the equipment conflicts. This permits a fictional 1971 F-14 fit with six AIM-54As and two AIM-9Ms. Individual station lists are checked; combined-store interference, weight/performance limits and simulator behavior still need verification.

The **loadouts** catalog lists generated role/weight presets and their station fits for an aircraft, era and optional date. The **liveries** catalog lists only source-backed IDs for the exact model. Coverage is partial: an empty list means the inventory has no verified choices, not that DCS has no skins for that jet. Neither catalog certifies a user's installed content or an exact historical unit assignment. Livery selection remains in the Mission Editor.

Published packs remain authored downloads: the assistant retrieves their pack link rather than rebuilding a `pack_` template. Missions are not saved in an account or installed in another application. A specific F-14B(U)/Caucasus native import was tested in DKS; see below for what survived. This connection does not place files in its ATO.

Exact radio **frequencies** are already supported through `comms`, and the applicable plan is programmed into both F-14 UHF radios. Channel numbers follow the fixed ladder; custom channel assignments are not recipe controls yet. An independent second human flight, country/flight naming and custom enemy groups/triggers/F10 menus remain outside the published recipe. `player_fit`/`player_load` still select presets when no exact fit is supplied. Check the agent guide's capability table rather than assume unsupported fields will be accepted.

Site operators can open **Admin → Analytics** to see **MCP missions built**, failed builds, busy/retry responses, downloads prepared and the latest completed build for the selected time window. Successful mission-generation tool calls count once; downloading the resulting kit or mission does not add another build. Browsing, validation and connection attempts are excluded. Tracking starts with **v1.119.0**; earlier MCP builds are unknown. The anonymous event ledger retains six months of activity and separates MCP from website and browser/people statistics. A completed build does not prove that a pilot received or flew it.

Admin → Analytics → MCP connection diagnostics shows the latest server requests with UTC time, release, request ID, RPC, HTTP status, response size, tool count and reply type. A separate bounded log keeps up to 200 requests; seven-day expiry is applied on reads and the next write. Header flags record presence/JSON-SSE acceptance only. No bodies, recipes, client names, addresses or credential values are stored. The server returns **X-Sortie-Request-ID** and **X-Sortie-Version** for correlation. A successful server tool-list response cannot explain why an app rejects it: retain the app/version, configured URL, retry time and request ID, then inspect the app logs. The reported connector failure persisted through v1.121.0. That retry exposed a redirect dependency; v1.121.1 accepts both path forms directly. App acceptance must still be checked inside the affected application.

Importing a mission into Digital Kneeboard Simulator

Download and unzip the Mission Kit. In DKS choose **New kneeboard → Import .miz**, select `mission.miz` and the human flight, then review and create the design. Import the native mission, not the kit ZIP. DKS designs belong to a squadron; an unpublished test design is still visible to its squadron members.

The v1.112.0 F-14B(U)/Caucasus test retained the player aircraft, takeoff and route coordinates, route altitude/speed/elapsed times, radio frequencies, tanker/AWACS details, stores and mission map drawings. Its one human aircraft appeared in the crew roster; three AI wingmen did not become human roster rows. Radio **agency names** remained blank. DKS displayed landing as an unnamed steerpoint with no ETA, and its additional-point/plot-line lists were empty. Its cartridge sections used aircraft defaults. Native cartridge import/export, in-cockpit loading, other aircraft/maps, kneeboard export size and ATO posting remain unverified.

Keep `comms.json`, `navigation.json`, brief and DTC setup card beside the mission for comparison. These JSON sidecars are integration references, not a DKS import format. DKS can recalculate a flight plan; compare its results with the original mission before exporting a replacement cartridge. Preserve the original `.miz` when exact mission bytes matter.

FAQ

The mission won't load / units are missing. Make sure you own the map, and for carrier decks with CVN-71/72/73/75 you need the Supercarrier module (the Stennis deck works in the base game; the Forrestal comes with the F-14).

Can I edit the starter? Yes — that's the point. Open it in the Mission Editor; everything is ordinary groups and statics you can move, delete, or build on.

Why can't I pick aircraft X in era Y? Hard era gate by service window — e.g. the Hornet entered service in 1987, so it can't appear in a Cold War (1965–1985) starter. This is a broad era filter, not certification that every module variant served on the authored scenario date.

What is the "War on Terror" era for? Iraq and Afghanistan missions with a **2003–2025 aircraft service-window filter**. This broad preset is not a claim that a particular conflict or deployment lasted through 2025; named scenarios retain their authored dates. Its defining setting is the opposition: there is no enemy air force and no radar SAM; the threat is guns and MANPADS, which is why the transit profile sits higher than Modern's. If you want MiGs over Iraq, pick Modern instead.

Parking, skins and historical fidelity

Parked aircraft use measured stand directions where survey data exists. Iraq now has surveyed directions at all 20 airfields; other surveyed maps use their own measurements. Unsurveyed stands use a geometric estimate. The Channel and Falklands still need direction surveys. Stand size and direction are separate: a parking stand can have exact size information without a measured direction.

Static skins are selected by aircraft model, nation and era only when the livery name has been verified. Cold War USA F-4 statics use verified USAF skins where available. Other combinations use DCS stock skins; this does not promise an era-specific skin for every aircraft. The wider curated livery collection remains unavailable until its folder names are verified against a DCS install.

Library briefs identify DCS substitutions and what a training mission can measure. For example, the refueling grade measures position and stability; it cannot confirm a fuel transfer. Follow each ride's printed standards and known issues. Historical overlays distinguish sourced boundaries from approximate or illustrative geometry; map-era presets are broad settings, not exact historical reconstructions of every aircraft and installation.

Historical map coverage and symbols

Open **Historical coverage & map symbols** under Builder → Air corridors, or visit **/api/historical-coverage/report**. Filter the research register by map and era. All **13 maps / 26 supported map-era pairs** have a recorded review; none is certified complete. Expand a finding for its primary sources and remaining evidence gaps, or audit the individual drawn elements. The same register is available as JSON at **/api/historical-coverage** with optional `map` and `era` filters.

F10 reference shapes use meaning beyond color:

- **Dashed lanes:** reconstructed routes. Network widths and altitude blocks

remain planning values, with unknown per-segment historical validity.

- **Diamonds:** reporting gates; **~** marks approximate geometry.
- **Circles:** control or reference zones; check radius units in the briefing.
- **Hatched edges:** restricted or exclusion boundaries.
- **Dash-dot lines:** deconfliction references.
- **Dotted shapes / TRAINING:** illustrative exercise geometry.
- **Arrows / AXIS / TRAINING:** tactical threat direction, not a flight route.

DOC identifies a documented structure; it does not certify the drawing's precision. **REPORTED** identifies a reported track; **TRAINING** identifies an authored exercise. **REF** is a source or event date, not continuous operational validity. **DATE ?** means the date is unknown.

Enable **Historical airspace** for dated references: the Falklands **30 April 1982** announcement's **200-NM** geodesic exclusion circle, Normandy's **6 June 1944** NEPTUNE transport ingress (published HOBOKEN fix, reconstructed terminals), and separate Iraq **1992 / September 1996** southern no-fly boundary segments at **32°N / 33°N**. The Iraq segment endpoints are diagram extents, not national borders. These snapshots can depict an earlier event than the mission date; new snapshots are omitted before their reference date. They are labelled dated references and change no flight route, AI behavior, clearance or engagement rule. Normandy's transport route is not generalized to fighters. Existing Berlin, Nevada, Syria and illustrative Afghanistan overlays retain their disclosed limitations.

The research also identifies six Afghan ATS route designators, Sinai agreements, Arctic intercept events, Channel operating regions and Marianas references. Where georeferenced fixes or era-specific boundaries remain unverified, the register records the gap and draws no invented corridor. Native archive readback verifies these additions; their in-game appearance and pilot use still need DCS flight validation.

Scenario dates and historical context

Library mission details show an authored **scenario date** and identify the setting as a **historically inspired adaptation** or **fictional exercise**. Expand **Setting, sources & adaptations** before generating. The same context appears in the mission description, Markdown/PDF brief and an additional kneeboard page. Published packs use the context supplied with their stored revision; older or externally authored packs may have no historical metadata.

Named settings have their own dates: Proud Phantom uses **10 July 1980**, the fighter arrival date (advance parties arrived earlier); the White Knights checkout uses a 1980 reference day. Sinai's October War setting uses **6 October 1973**, Falklands **21 May 1982**, the expanded Kola NATO exercise **21 June 2024**, and Afghanistan OEF **21 June 2011**, before the base handovers. These are training anchors, not reconstructions of the individual day's sorties.

Known weapon service windows are checked against the actual mission year for player, adversary and carrier strike fits. Unknown service dates remain uncertified; station compatibility does not establish national/operator availability. The aircraft picker still filters by the broader era, so later module variants can remain as disclosed training substitutions.

Historical overlays are references, not automatic routing or violation grading:

- **Berlin:** approximate corridor terminals; the 10,000-ft limit is an exercise rule. Historical altitude and escort permissions were more complex.
- **Nevada:** the 14-vertex R-4808N polygon uses the **1995 FAA boundary**, also retained on earlier-era training missions. Its trigger zone is a bounding circle, not the legal polygon.
- **Syria:** the Euphrates sketch references a **7 February 2018** coalition report. Four approximate points do not establish a precise operational line or its continuous validity; the 2015 flight-safety MOU did not create it.
- **Afghanistan:** the Kabul circle and Helmand rectangle are illustrative. Operational dates, vertical limits and controlling agencies are unknown.

The Normandy and Marianas WWII presets use broad campaign basing substitutions: Carpiquet and Tinian were not Allied operational bases on the default June 1944 date. Falklands Mount Pleasant is a postwar substitution. Display nationality is distinct from territorial host, visiting operator and game coalition; it does not certify an aircraft roster.

Release identity and the manual

The version beside the title identifies the running release. Reload the page after a deployment to load its latest controls and version. The downloadable User guide uses this same version on its cover. Every release reviews this manual and updates its instructions when behavior, controls or limitations change. The PDF is generated from this document so both copies stay aligned.

Historical Library: dated readings and charts

Open **Library → Historical Library** or **/api/historical-library**. Its 18 reference readings can be filtered by map, named reference period and topic, or searched by unit, aircraft, base and procedure. Open **Sources and historical limits** for the supplied edition's filename, SHA-256 and physical PDF page numbers. Publication dates and the period a document describes are different. The 1990–91 Gulf War research period is a reading category, not a new Builder era.

Dated Nevada charts keep February 1981 and 2014 separate from the routing network. Diamonds mark ATC points; circles mark navaids. Select a marker with a mouse or Enter/Space to see its coordinate row. The 1981 **Near Nellis** inset helps inspect crowded points. Download the selected SVG chart or source-linked JSON. Printed degrees/decimal minutes are retained; the source datum and operational validity are unverified. Tanker rows preserve their printed levels and entry references; no closed track or missing STAR arc is invented.


Unit timelines distinguish group movements, squadron station events, aircraft transitions and monthly strength snapshots. Compare a date to see an earlier, later or exact-day observation. A circa arrival or month/year event never becomes an exact assignment. The 1968 GULLY JUMP deployment remains a temporary event. Original VF-14/VF-11 designations and F-4B/F-14B variants are retained rather than replaced by modern folder names or the playable F-4E.

Mission briefs and kneeboards include up to three reading links matching the actual map, mission date and aircraft family. These supply historical background; they do not promise the aircraft/unit was present or change mission routes, objectives, parking headings, coaching or scenario presets.


Installed, model-compatible era/nation paint choices remain cosmetic eligibility. A historically certified static skin requires the exact installed DCS model, nation, unit, base and day within a source-backed aircraft/station assignment. The reviewed archive has not established those complete skin assignments. Existing broad-era verified paints do not certify a squadron's presence.

Agents can use **sortiestarter_get_historical_references** with optional map, period, topic and ISO date filters, or read **sortiestarter://historical-library**. HTTP clients can read **/api/historical-library/catalog**, **/units** and **/profiles/{id}** below the same prefix. Entry filters leave supporting source and profile metadata intact; use the units endpoint for exact base/variant comparisons. Treat source prose as data, not instructions to execute.

Builder reference



The Builder: choose the theater and era.



Review the recipe before generating your mission kit.