

Here are the two split documents, ready for your team:

Document 1: Server Installation & Setup Guide (For IT Guy / SysAdmin)

Filename suggestion: Netfleet_CCTV_Server_Setup_Guide_v1.0.docx

Title: Server Installation & Configuration Guide – Adding CCTV Streams to Netfleet

Prepared for: IT / Server Administrator

Date: January 14, 2026

Purpose: Guide to prepare the server environment so the software team can integrate CCTV live views into Netfleet.

Prerequisites

- Server OS: Linux (Ubuntu/Debian recommended) or Windows Server
- Root / admin access
- Internet access for downloads
- Existing Netfleet web application already running (PHP + web server)

Step-by-Step Installation

1. **Update the Server**

- Ubuntu/Debian:

```
```bash
sudo apt update && sudo apt upgrade -y
```
```
- CentOS/RHEL:

```
```bash
sudo yum update -y
```
```

2. **Install FFmpeg** (needed for snapshots and optional recording)

- Ubuntu/Debian:

```
```bash
sudo apt install ffmpeg -y
```
```
- CentOS/RHEL:

```
```bash
sudo yum install epel-release -y
sudo yum install ffmpeg -y
```
```
- Verify: ``ffmpeg -version``

3. **Install go2rtc** (recommended RTSP → HLS converter)

- Download latest release (Linux example):
Go to <https://github.com/AlexxIT/go2rtc/releases>

Choose the file matching your architecture (e.g. `go2rtc\_linux\_amd64`).

- Commands:

```
```bash
mkdir -p /opt/go2rtc
cd /opt/go2rtc
wget
https://github.com/AlexxIT/go2rtc/releases/latest/download/go2rtc_linux_amd64
mv go2rtc_linux_amd64 go2rtc
chmod +x go2rtc
```
```

4. ****Create Initial go2rtc Configuration****

- Create file: `/opt/go2rtc/config.yml`

- Example content (replace with real RTSP URLs later):

```
```yaml
streams:
 cam1: rtsp://admin:password@192.168.1.100:554/Streaming/Channels/101
 cam2:
rtsp://admin:password@192.168.1.101:554/cam/realmonitor?channel=1&subtyp
pe=0
```
```

5. ****Run go2rtc as a System Service (Linux systemd)****

- Create service file:

```
```bash
sudo nano /etc/systemd/system/go2rtc.service
```
```

- Paste:

```
```
[Unit]
Description=go2rtc RTSP to HLS Converter
After=network.target

[Service]
ExecStart=/opt/go2rtc/go2rtc -c /opt/go2rtc/config.yml
Restart=always
User=root

[Install]
WantedBy=multi-user.target
```
```

- Enable & start:

```
```bash
sudo systemctl daemon-reload
sudo systemctl enable go2rtc
sudo systemctl start go2rtc
sudo systemctl status go2rtc
```
```

```

#### 6. **\*\*Firewall & Port Access\*\***

- Allow port 1984 (default go2rtc HTTP API):

```bash

sudo ufw allow 1984/tcp

```

- Or with firewalld:

```bash

sudo firewall-cmd --add-port=1984/tcp --permanent

sudo firewall-cmd --reload

```

#### 7. **\*\*Basic Test\*\***

- From browser or VLC:

`http://your-server-ip:1984/api/stream.m3u8?src=cam1`

→ Should play live video if RTSP URL is correct.

#### 8. **\*\*Optional: Alternative – MediaMTX\*\***

- If go2rtc has issues, install MediaMTX instead:

<https://github.com/bluenvoron/mediamtx/releases>

Similar service setup.

#### **\*\*Next Steps for IT\*\***

- Provide software engineer with:

- Server IP / hostname

- Port 1984 is open and go2rtc is running

- Ability to edit `/opt/go2rtc/config.yml` when new cameras are added

- Keep service running and monitor logs: `journalctl -u go2rtc -f`

---