

AirBar Server - Quickstart Windows (machine vierge)

Objectif: installer et demarrer rapidement le serveur avec Docker.

1) Installer les outils

1. Installer Git: <https://git-scm.com/download/win>
2. Installer Docker Desktop: <https://www.docker.com/products/docker-desktop/>
3. Ouvrir Docker Desktop et attendre l'etat Running.

Verification:

```
git --version
docker --version
docker compose version
```

2) Recuperer le projet

```
cd C:\
mkdir airbar_production
cd airbar_production
git clone https://github.com/rorophil/airbar_backend.git
cd .\airbar_backend\airbar_backend_server
```

3) Configurer les secrets

Ouvrir `.env` et mettre des valeurs fortes:

```
POSTGRES_PASSWORD=ChangeMePostgresPassword
REDIS_PASSWORD=ChangeMeRedisPassword
SERVERPOD_PASSWORD_SHARED=ChangeMeSharedKeyAtLeast32Chars
SERVERPOD_PASSWORD_SERVICE_SECRET=ChangeMeServiceSecretAtLeast32Chars
```

```
SERVERPOD_PASSWORD_JWT_REFRESH_PEPPER=ChangeMeJwtRefreshPepperAtLeast32Chars  
SERVERPOD_PASSWORD_JWT_HMAC_SHA512_PRIVATE_KEY=ChangeMeJwtHmacSha512PrivateKeyAtLeast32Chars  
SERVERPOD_PASSWORD_EMAIL_SECRET_HASH_PEPPER=ChangeMeEmailSecretHashPepperAtLeast32Chars
```

4) Build + demarrage

```
docker compose -f .\docker-compose.yaml up -d --build  
docker compose -f .\docker-compose.yaml ps
```

Attendu: postgres et redis en healthy, backend en Up.

5) Appliquer les migrations (premier demarrage)

```
docker compose -f .\docker-compose.yaml run --rm --entrypoint /bin/sh airbar_server  
-c "./server --mode=production --server-id=prod-001 --logging=normal --  
role=monolith --apply-migrations"  
docker compose -f .\docker-compose.yaml up -d airbar_server
```

6) Verifier les logs

```
docker compose -f .\docker-compose.yaml logs --tail 100 airbar_server
```

7) Commandes utiles

Redemarrer:

```
docker compose -f .\docker-compose.yaml restart
```

Arreter:

```
docker compose -f .\docker-compose.yaml down
```

Reset complet (supprime les volumes, destructif):

```
docker compose -f .\docker-compose.yaml down -v
```

8) Si probleme

- docker compose non reconnu: relancer Docker Desktop puis reouvrir PowerShell.
- Missing password for ...: verifier toutes les variables
SERVERPOD_PASSWORD_* dans .env.
- relation ... does not exist: relancer la commande d'application des migrations en mode production.
- backend en boucle de restart: lire les logs:

```
docker compose -f .\docker-compose.yaml logs --tail 200 airbar_server
```