## All about CP

#### **Table of Content**

- 1 Development
- 2 FastIO
  - 2.1 The Magic Line
- 3 Language
  - 3.1 Return by reference
- 4 Maths
  - 4.1 Summation
    - 4.1.1 Identities
- 5 Bit Manipulation
  - 5.1 Non-decimal Literal in C++
  - 5.2 How integers are stored
  - 5.3 I/O with Non-Decimal Numbers
    - 5.3.1 Using cin/cout:
    - 5.3.2 Using scanf/prinjf:
  - 5.4 Signed and Unsigned Integers
  - 5.5 Index of Bit
  - 5.6 Terminologies
  - 5.7 NOT
    - 5.7.1 x in terms of  $\sim x$
  - 5.8 XOR
    - 5.8.1 How to Visualize XOR
  - 5.9 Thinking of Bitwise Operators: Fixing one operand
    - 5.9.1 AND
    - 5.9.2 OR
    - 5.9.3 XOR
  - 5.10 Visualizing n-1
  - 5.11 Common Bit Operations and Checks
    - 5.11.1 Parity Check
    - 5.11.2 Left Shift as  $\times 2$

```
5.11.3 Right Shift as ÷ 2
5.11.4 Set i-th Bit
5.11.5 Clear i-th Bit
5.11.6 Flip i-th Bit
5.11.7 Check i-th Bit
5.11.8 Unset Rightmost Set Bit
5.11.9 Check if Power of Two
5.11.10 Count Set Bits: Brian Kernighan's Algorithm
5.11.11 Set Range of bits
5.11.12 Clear Range of bits
5.11.13 Flip Range of bits
5.12 Builtin Functions
```

## 1 Development

This book is publicly developed on <u>GitHub</u>. If you find anything confusing, or you think that there is a better way to express the idea, please make a pull request.

## 2 FastIO

### 2.1 The Magic Line

```
1 cin.tie(0)->sync_with_stdio(0);
```

## 3 Language

## 3.1 Return by reference

Lets define an array to demonstrate return by reference

```
<u>int</u> vals[] = {10, 12, 83, 122, 5, 34};
```

The following function returns the value of the i-th element

```
int getVal(int i) {
   return vals[i];
}
```

The following function returns a reference to the i-th element

```
int& getRef(int i) {
  return vals[i];
}
```

Demonstration:

Problem: This code causes TLE, but this gets AC

## 4 Maths

#### 4.1 Summation

#### 4.1.1 Identities

```
• \sum c \times f(n) = c \times \sum f(n), c is constant
```

```
• \sum (f(n) \pm g(n)) = \sum f(n) \pm \sum g(n)
```

 $\label{limits} $$\sup_{i=1}^n\sum_{j=1}^n{a_{ib_{j}}}=(\sum_{i=1}^n{a_{i}}) (\sum_{j=1}^n{b_{j}}) $$ 

Proof of this identity is interesting

Problem: AtCoder ARC A - Simple Math

## 5 Bit Manipulation

### 5.1 Non-decimal Literal in C++

Base	Prefix
bin	0b
hex	0x
oct	0

```
1 assert(13 == 0b1101);
2 assert(13 == 0xd);
3 assert(13 == 015);
```

## 5.2 How integers are stored

Integers are stored as blocks of bytes

Data Type	No. of Bytes
char	1
short	2
int	3
long long	4
int128_t (g++ extension)	5

## 5.3 I/O with Non-Decimal Numbers

#### 5.3.1 Using cin/cout:

```
int x;
cin>>hex>>x;
cout<<hex<<x;
cin>>oct>>x;
cout<<oct<<x;</pre>
```

```
6 cin>>dec>>x;
7 cout<<dec<<x;</pre>
```

#### 5.3.2 Using scanf/prinjf:

```
1 int x;
2 scanf("%x",&x);
3 printf("%x",x);
4 scanf("%o",&x);
5 printf("%o",x);
6 scanf("%d",&x);
7 printf("%d",x);
```

## 5.4 Signed and Unsigned Integers

Positive integers (both signed and unsigned) are just represented with their binary digits, and negative signed numbers (which can be positive and negative) are usually represented with the Two's complement  $^{1}$ 

#### 5.5 Index of Bit

Bits in a bit string are indexed from right to left, starting with 0.

```
bit string: 1 0 1 1 0 1 index: ... 3 2 1 0
```

In this text, i-th bit means bit with index i.

## 5.6 Terminologies

Terms	Meaning
Set bit	Make the bit 1

Terms	Meaning
Unset/Clear bit	Make the bit 0
Flip bit	Make the bit opposite
Lower bit/ Higher bit	i-th bit is lower that j-th bit if i <j MSB is highest bit, LSB is the lowest bit</j 

#### **5.7 NOT**

Operation	Meaning
~X	1's complement of x
~x+1	2's complement of x

#### 5.7.1 - x in terms of $\sim x$

```
\underline{1} assert(-x == ^{\sim}x+1);
```

#### **5.8 XOR**

#### **5.8.1 How to Visualize XOR**

#### **Method-1: Non-equivalence Operator**

A^B is true if truth value of A and B are different. The following function uses this algorithm:

```
bool xor(bool a, bool b) {
  if (a!=b)
   return true;
  return false;
}
```

#### **Method-2: Programmable Inverter**

Think of XOR as a machine with an on/off button, that takes one bit as input and one bit as output. If the machine is on, the ouput bit will be inverse of input bit, otherwise, the output bit will be the same as input bit.

In A^B, one bit decides if the other should be flipped.

The following function uses this algorithm:

```
bool xor(bool a, bool b) {
  if (a)
    return !b;
  return b;
}
```

# 5.9 Thinking of Bitwise Operators: Fixing one operand

#### 5.9.1 AND

Operation	Meaning
& 1	same
& 0	0

#### 5.9.2 OR

C	peration	Meaning
-	1	1
	0	same

#### 5.9.3 XOR

Operation	Meaning
^ 1	flip
^ 0	same

## 5.10 Visualizing n-1

When we substract 1 from a number, the rightmost set bit becomes unset and all the bits to its right becomes set

```
n = xxxx10000
n-1 = xxxx01111
```

There for value of a binary number with all 1s of length n is  $2^n - 1$ 

# **5.11 Common Bit Operations and Checks**

#### 5.11.1 Parity Check

If n is an integer(positive or negative) then n&1 represent parity of n. It is similar to n%2 but better, because unlike n%2, n&1 works for both positive and negative numbers.

```
int n;
n=5;
assert((n&1) == 1);
assert((n%2) == 1);
n=-5;
assert((n&1) == 1);
assert((n%2) == -1);
```

In general, x % (1<<k) is equivalent to x & (1<<k)-1

#### 5.11.2 Left Shift as $\times 2$

x<<y is equivalent to  $x \times 2^y$ 

```
1 = assert((5 << 2) == 20);
```

#### 5.11.3 Right Shift as $\div 2$

x>>y is equivalent to  $\frac{x}{2^y} \cdot \frac{x}{2^y} \cdot \frac{x}{y}$ 

```
<u>1</u> assert((10>>2) == 2);
```

#### 5.11.4 Set i-th Bit

```
n|(1<<i)
```

#### 5.11.5 Clear i-th Bit

```
n&~(1<<i)
```

#### 5.11.6 Flip i-th Bit

We already discussed that, XOR works as a programmable inverter.  $n^{(1<< i)}$ 

#### 5.11.7 Check i-th Bit

```
n&(1<< x) (n>> x)&1
```

#### 5.11.8 Unset Rightmost Set Bit

```
n&(n-1)
```

#### 5.11.9 Check if Power of Two

n is power of two, if there is only one set bit. To check if there is only one set bit, unset the last set bit, and check if it becomes zero or greater. If it becomes zero its a power of two

```
bool isPowerOf2(int n) {
   return n!=0 && (n&(n-1))>0;
}
```

Corner case: 0

# 5.11.10 Count Set Bits: Brian Kernighan's Algorithm

The idea is to count how many times we can unset the rightmost set bit, until we reach 0

#### 5.11.11 Set Range of bits

The concept is similar to setting i-th bit, except we will use a different bit mask.

1<<i ii is i 0s after one 1
(1<<i)-1 is i 1s at the end, and rest are 0s
Now we can leftshift these 1s to fit into the range</pre>

```
int setRange(int n, int start, int stop) {
  int length = stop-start;
  int mask = (1<<length);
  mask = mask-1;
  mask = mask<<start;
  return n|mask;
}</pre>
```

#### 5.11.12 Clear Range of bits

```
int clearRange(int n, int start, int stop) {
  int length = stop-start;
  int mask = (1<<length);
  mask = mask-1;
  mask = mask<<start;
  mask = ~mask;
  return n&mask;
}</pre>
```

#### 5.11.13 Flip Range of bits

```
int flipRange(int n, int start, int stop) {
  int length = stop-start;
  int mask = (1<<length);
  mask = mask-1;
  mask = mask<<start;
  return n^mask;
}</pre>
```

### **5.12 Builtin Functions**

The g++ compiler provides the following functions for counting bits:

\_\_builtin\_clz(x):
 the number of zeros at the beginning of the number
\_\_builtin\_ctz(x):
 the number of zeros at the end of the number
\_\_builtin\_popcount(x):
 the number of ones in the number
\_\_builtin\_parity(x):

the parity (even or odd) of the number of ones

The functions can be used as follows:

```
int x = 5328; // 000000000000000000001010011010000
cout << __builtin_clz(x) << "\n"; // 19
cout << __builtin_ctz(x) << "\n"; // 4
cout << __builtin_popcount(x) << "\n"; // 5
cout << __builtin_parity(x) << "\n"; // 1</pre>
```

While the above functions only support int numbers, there are also long long versions of the functions available with the suffix ll. Source: CSES Book

1. cp-algorithms - bit manipulation ←