

BEAWebLogic Server®

WebLogic Tuxedo Connector Programmer's Guide

Version 9.0 BETA Revised: December 15, 2004



Copyright

Copyright © 2004-2005 BEA Systems, Inc. All Rights Reserved.

Restricted Rights Legend

This software and documentation is subject to and made available only pursuant to the terms of the BEA Systems License Agreement and may be used or copied only in accordance with the terms of that agreement. It is against the law to copy the software except as specifically allowed in the agreement. This document may not, in whole or in part, be copied, photocopied, reproduced, translated, or reduced to any electronic medium or machine readable form without prior consent, in writing, from BEA Systems, Inc.

Use, duplication or disclosure by the U.S. Government is subject to restrictions set forth in the BEA Systems License Agreement and in subparagraph (c)(1) of the Commercial Computer Software-Restricted Rights Clause at FAR 52.227-19; subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013, subparagraph (d) of the Commercial Computer Software--Licensing clause at NASA FAR supplement 16-52.227-86; or their equivalent.

Information in this document is subject to change without notice and does not represent a commitment on the part of BEA Systems. THE SOFTWARE AND DOCUMENTATION ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND INCLUDING WITHOUT LIMITATION, ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. FURTHER, BEA Systems DOES NOT WARRANT, GUARANTEE, OR MAKE ANY REPRESENTATIONS REGARDING THE USE, OR THE RESULTS OF THE USE, OF THE SOFTWARE OR WRITTEN MATERIAL IN TERMS OF CORRECTNESS, ACCURACY, RELIABILITY, OR OTHERWISE.

Trademarks or Service Marks

BEA, BEA WebLogic Server, Jolt, Tuxedo, and WebLogic are registered trademarks of BEA Systems, Inc. BEA Builder, BEA Campaign Manager for WebLogic, BEA eLink, BEA Liquid Data for WebLogic, BEA Manager, BEA WebLogic Commerce Server, BEA WebLogic Enterprise, BEA WebLogic Enterprise Platform, BEA WebLogic Enterprise Security, BEA WebLogic Express, BEA WebLogic Integration, BEA WebLogic JRockit, BEA WebLogic Personalization Server, BEA WebLogic Platform, BEA WebLogic Portal, BEA WebLogic Server Process Edition, BEA WebLogic Workshop and How Business Becomes E-Business are trademarks of BEA Systems, Inc.

All other trademarks are the property of their respective companies.



Contents

About This Document

7 110 0 01 0		
	Audience	.xii
	e-docs Web Site	.xii
	How to Print the Document	xii
	Related Information	
	Contact Us!	. xiii
	Documentation Conventions	. xiii
ln ⁻	troduction to WebLogic Tuxedo Connector Programming	
	Developing WebLogic Tuxedo Connector Applications	. 1-1
	Developing WebLogic Tuxedo Connector Clients	. 1-2
	Developing WebLogic Tuxedo Connector Servers.	. 1-2
	WebLogic Tuxedo Connector Interoperability with Tuxedo CORBA objects	. 1-2
	WebLogic Tuxedo Connector JATMI Primitives	. 1-3
	WebLogic Tuxedo Connector TypedBuffers	. 1-4
De	eveloping WebLogic Tuxedo Connector Client EJBs	
	Joining and Leaving Applications	. 2-1
	Joining an Application	. 2-1
	Leaving an Application	. 2-2

Send and Receive Messages2-4	1
Request/Response Communication	4
Conversational Communication	7
Enqueuing and Dequeuing Messages	8
Close a Connection to a Tuxedo Object	8
Example Client EJB	8
Developing WebLogic Tuxedo Connector Service EJBs	
Basic Service EJB Operation	1
Access Service Information	2
Buffer Messages	2
Perform the Requested Service	3
Return Client Messages for Request/Response Communication	
Use tpsend and tprecv for Conversational Communication	3
Example Service EJB	4
Using WebLogic Tuxedo Connector for RMI/IIOP and CORBA	
Interoperability	
How to Develop WebLogic Tuxedo Connector Client Beans using the CORBA Java API4-	-1
Using CosNaming Service4-2	2
Example ToupperCorbaBean.java Code4-3	3
Using FactoryFinder 4-4	4
WLEC to WebLogic Tuxedo Connector Migration	5
Example Code	5
How to Develop RMI/IIOP Applications for the WebLogic Tuxedo Connector 4-7	7
How to Modify Inbound RMI/IIOP Applications to use the WebLogic Tuxedo	
Connector	8

How to Develop Outbound RMI/IIOP Applications to use the WebLogic Tuxedo
Connector
How to Modify the ejb-jar.xml File to Pass a FederationURL to EJBs 4-9
How to Modify EJBs to Use FederationURL to Access an Object 4-11
How to Use FederationURL Formats
Using corbaloc URL Format
Examples of corbaloc:tgiop
Examples using -ORBInitRef
Examples Using -ORBDefaultInitRef
Using the corbaname URL Format
Examples Using -ORBInitRef
How to Manage Transactions for Tuxedo CORBA Applications
WebLogic Tuxedo Connector JATMI Transactions
Global Transactions
JTA Transaction API
Types of JTA Interfaces
Transaction
TransactionManager
UserTransaction
JTA Transaction Primitives
Defining a Transaction
Starting a Transaction
Using TPNOTRAN5-4
Terminating a Transaction
WebLogic Tuxedo Connector Transaction Rules
Example Transaction Code

WebLogic Tuxedo Connector JATMI Conversations

	Overview of WebLogic Tuxedo Connector Conversational Communication 6-2
	WebLogic Tuxedo Connector Conversation Characteristics
	WebLogic Tuxedo Connector JATMI Conversation Primitives 6-3
	Creating WebLogic Tuxedo Connector Conversational Clients and Servers 6-3
	Creating Conversational Clients
	Establishing a Connection to a Tuxedo Conversational Service 6-3
	Example TuxedoConversationBean.java Code
	Creating WebLogic Tuxedo Connector Conversational Servers
	Sending and Receiving Messages
	Sending Messages
	Receiving Messages
	Ending a Conversation
	Tuxedo Application Originates Conversation
	WebLogic Tuxedo Connector Application Originates Conversation 6-7
	Ending Hierarchical Conversations
	Executing a Disorderly Disconnect
	Understanding Conversational Communication Events
	WebLogic Tuxedo Connector Conversation Guidelines
U	sing FML with WebLogic Tuxedo Connector
	Overview of FML
	The WebLogic Tuxedo Connector FML API
	FML Field Table Administration
	Using the DynRdHdr Property for mkfldclass32 Class
	tBridge XML/FML32 Translation
	FLAT 7-5
	NO 7-6

7-6
8-1
8-2
8-3
8-4
8-6
8-7
9-1
9-2
9-15
10-1
10-1
10-2
10-2
10-2
10-3
10-3
10-3



About This Document

This document introduces the BEA WebLogic Server WebLogic Tuxedo Connector application development environment. It describes how to develop EJBs that allow WebLogic Server to interoperate with Tuxedo objects.

The document is organized as follows:

- Chapter 1, "Introduction to WebLogic Tuxedo Connector Programming," provides information about the development environment you will be using to write code for applications that interoperate between WebLogic Server and Tuxedo.
- Chapter 2, "Developing WebLogic Tuxedo Connector Client EJBs," provides information on how to create client EJBs.
- Chapter 3, "Developing WebLogic Tuxedo Connector Service EJBs," provides information on how to create service EJBs.
- Chapter 4, "Using WebLogic Tuxedo Connector for RMI/IIOP and CORBA Interoperability," provides information on how to develop CORBA applications for the WebLogic Tuxedo Connector.
- Chapter 5, "WebLogic Tuxedo Connector JATMI Transactions," provides information on global transactions and how to define and manage them in your applications.
- Chapter 6, "WebLogic Tuxedo Connector JATMI Conversations," provides information on conversations and how to define and manage them in your applications.

- Chapter 7, "Using FML with WebLogic Tuxedo Connector," discusses the Field Manipulation Language (FML) and describes how the WebLogic Tuxedo Connector uses FML.
- Chapter 8, "WebLogic Tuxedo Connector JATMI VIEWs," provides information on View buffers and how to define and manage them in your applications.
- Chapter 9, "How to Create a Custom AppKey Plug-in," provides information on how to develop a Custom AppKey Plug-in.
- Chapter 10, "Application Error Management," provide mechanisms to manage and interpret error conditions.

Audience

This document is written for system administrators and application developers who are interested in building distributed Java applications that interoperate between WebLogic Server and Tuxedo environments. It is assumed that readers are familiar with the WebLogic Server, Tuxedo, CORBA, and Java programming.

e-docs Web Site

BEA product documentation is available on the BEA corporate Web site. From the BEA Home page, click on Product Documentation.

How to Print the Document

You can print a copy of this document from a Web browser, one main topic at a time, by using the File—Print option on your Web browser.

A PDF version of this document is available on the WebLogic Server documentation Home page on the e-docs Web site (and also on the documentation CD). You can open the PDF in Adobe Acrobat Reader and print the entire document (or a portion of it) in book format. To access the PDFs, open the WebLogic Server documentation Home page, click Download Documentation, and select the document you want to print.

Adobe Acrobat Reader is available at no charge from the Adobe Web site at http://www.adobe.com.

Related Information

The BEA corporate Web site provides all documentation for WebLogic Server and Tuxedo.

For more information about Java and Java CORBA applications, refer to the following sources:

- The OMG Web Site at http://www.omg.org/
- The Sun Microsystems, Inc. Java site at http://java.sun.com/

Contact Us!

Your feedback on BEA documentation is important to us. Send us e-mail at docsupport@bea.com if you have questions or comments. Your comments will be reviewed directly by the BEA professionals who create and update the documentation.

In your e-mail message, please indicate the software name and version you are using, as well as the title and document date of your documentation. If you have any questions about this version of BEA WebLogic Server, or if you have problems installing and running BEA WebLogic Server, contact BEA Customer Support through BEA WebSupport at http://www.bea.com. You can also contact Customer Support by using the contact information provided on the Customer Support Card, which is included in the product package.

When contacting Customer Support, be prepared to provide the following information:

- Your name, e-mail address, phone number, and fax number
- Your company name and company address
- Your machine type and authorization codes
- The name and version of the product you are using
- A description of the problem and the content of pertinent error messages

Documentation Conventions

The following documentation conventions are used throughout this document.

Convention	Usage
Ctrl+Tab	Keys you press simultaneously.
italics	Emphasis and book titles.

Convention	Usage
monospace text	Code samples, commands and their options, Java classes, data types, directories, and file names and their extensions. Monospace text also indicates text that you enter from the keyboard.
	Examples:
	<pre>import java.util.Enumeration;</pre>
	chmod u+w *
	config/examples/applications
	.java
	config.xml
	float
monospace	Variables in code.
italic	Example:
text	String CustomerName;
UPPERCASE	Device names, environment variables, and logical operators.
TEXT	Examples:
	LPT1
	BEA HOME
	OR
{ }	A set of choices in a syntax line.
[]	Optional items in a syntax line. Example:
	<pre>java utils.MulticastTest -n name -a address [-p portnumber] [-t timeout] [-s send]</pre>
	Separates mutually exclusive choices in a syntax line. <i>Example</i> :
	<pre>java weblogic.deploy [list deploy undeploy update] password {application} {source}</pre>

Convention	Usage
	 Indicates one of the following in a command line: An argument can be repeated several times in the command line. The statement omits additional optional arguments. You can enter additional parameters, values, or other information
	Indicates the omission of items from a code example or from a syntax line.





Introduction to WebLogic Tuxedo Connector Programming

Note: For information on how to develop WebLogic Server Enterprise JavaBeans (EJBs), see Programming WebLogic Enterprise JavaBeans at http://e-docs.bea.com/wls/docs90/ejb/index.html.

The following sections provide information about the development environment you will be using to write code for applications that interoperate between WebLogic Server and Tuxedo:

- Developing WebLogic Tuxedo Connector Applications
- WebLogic Tuxedo Connector JATMI Primitives
- WebLogic Tuxedo Connector TypedBuffers

Developing WebLogic Tuxedo Connector Applications

Note: For more information on the WebLogic Tuxedo Connector JATMI, view the Javadocs for WebLogic Classes at http://e-docs.bea.com/wls/docs90/javadocs/index.html. The WebLogic Tuxedo Connector classes are located in the weblogic.wtc.jatmi and weblogic.wtc.gwt packages.

In addition to the Java code that expresses the logic of your application, you will be using the Java Application -to-Transaction Monitor Interface (JATMI) to provide the interface between WebLogic Server and Tuxedo.

Developing WebLogic Tuxedo Connector Clients

Note: For more information, see "Developing WebLogic Tuxedo Connector Client EJBs" on page 2-1.

A client process takes user input and sends a service request to a server process that offers the requested service. WebLogic Tuxedo Connector JATMI client classes are used to create clients that access services found in Tuxedo. These client classes are available to any service that is made available through a the WebLogic Tuxedo Connector WTCServer MBean.

Developing WebLogic Tuxedo Connector Servers

Note: For more information, see "Developing WebLogic Tuxedo Connector Service EJBs" on page 3-1.

Servers are processes that provide one or more services. They continually check their message queue for service requests and dispatch them to the appropriate service subroutines. WebLogic Tuxedo Connector uses EJBs to implement services which Tuxedo clients invoke.

WebLogic Tuxedo Connector Interoperability with Tuxedo CORBA objects

Note: For more information, see "Using WebLogic Tuxedo Connector for RMI/IIOP and CORBA Interoperability" on page 4-1.

The WebLogic Tuxedo Connector provides bi-directional interoperability between WebLogic Server and Tuxedo CORBA objects. The WebLogic Tuxedo Connector:

- Enables Tuxedo CORBA objects to invoke upon EJBs deployed in WebLogic Server using the RMI/IIOP API (Inbound).
- Enables objects (such as EJBs or RMI objects) to invoke upon CORBA objects deployed in Tuxedo using the RMI/IIOP API (Outbound).
- Enables objects (such as EJBs or RMI objects) to invoke upon CORBA objects deployed in Tuxedo using a CORBA Java API (Outbound).

WebLogic Tuxedo Connector JATMI Primitives

The JATMI is a set of primitives used to begin and end transactions, allocate and free buffers, and provide the communication between clients and servers.

Table 1-1 JATMI Primitives

Name	Operation
tpacall	Use for asynchronous invocations of a Tuxedo service during request/response communication.tpacall has two forms:
	 deferred synchronous
	 asynchronous
tpcall	Use for synchronous invocation of a Tuxedo service during request/response communication.
tpconnect	Use to establish a connection to a Tuxedo conversational service.
tpdiscon	Use to abort a conversational connection and generate a TPEV_DISCONIMM event when executed by the process controlling the conversation.
tpdequeue	Use for receiving messages from a Tuxedo /Q during request/response communication.
tpenqueue	Use for placing a message on a Tuxedo /Q during request/response communication.
tpgetrply	Use for retrieving replies from a Tuxedo service during request/response communication.
tprecv	Use to receive data across an open connection from a Tuxedo application during conversational communication.
tpsend	Use to send data across a open connection to a Tuxedo application during conversational communication.
tpterm	Use to close a connection to a Tuxedo object.

WebLogic Tuxedo Connector TypedBuffers

Note: WebLogic Tuxedo Connector does not support double-byte character sets or international character sets. These features are dependent on future releases of Tuxedo.

WebLogic Tuxedo Connector provides an interface called TypedBuffers that corresponds to Tuxedo typed buffers. Messages are passed to servers in typed buffers. The WebLogic Tuxedo Connector provides the following buffer types:.

Table 1-2 TypedBuffers

Buffer Type	Description
TypedString	Buffer type used when the data is an array of characters that terminates with the null character. Tuxedo equivalent: STRING.
TypedCArray	Buffer type used when the data is an undefined array of characters (byte array), any of which can be null. Tuxedo equivalent: CARRAY.
TypedFML	Buffer type used when the data is self-defined. Each data field carries its own identifier, an occurrence number, and possibly a length indicator. Tuxedo equivalent: FML.
TypedFML32	Buffer type similar to TypeFML but allows for larger character fields, more fields, and larger overall buffers. Tuxedo equivalent: FML32.
TypedXML	Buffer type used when data is an XML based message. Tuxedo equivalent: XML for Tuxedo Release 7.1 and higher.
TypedView	Buffer type used when the application uses a Java structure to define the buffer structure using a view description file. Tuxedo equivalent: VIEW
TypedView32	Buffer type similar to View but allows for larger character fields, more fields, and larger overall buffers. Tuxedo equivalent: VIEW32.
TypedXOctet	Buffer type used when the data is an undefined array of characters (byte array) any of which can be null. X_OCTET is identical in semantics to CARRAY. Tuxedo equivalent: X_OCTET.

Table 1-2 TypedBuffers

Buffer Type	Description
TypedXCommon	Buffer type identical in semantics to View. Tuxedo equivalent: VIEW.
TypedXCType	Buffer type identical in semantics to View. Tuxedo equivalent: VIEW.





Developing WebLogic Tuxedo Connector Client EJBs

Note: For more information on the WebLogic Tuxedo Connector JATMI, view the Javadocs for WebLogic Classes at http://e-docs.bea.com/wls/docs90/javadocs/index.html. The WebLogic Tuxedo Connector classes are located in the weblogic.wtc.jatmi and weblogic.wtc.gwt packages.

The following sections describe how to create client EJBs that take user input and send service requests to a server process or outbound object that offers a requested service.

- Joining and Leaving Applications
- Basic Client Operation
- Example Client EJB

WebLogic Tuxedo Connector JATMI client classes are used to create clients that access services found in Tuxedo.

Joining and Leaving Applications

Tuxedo and WebLogic Tuxedo Connector have different approaches to connect to services.

Joining an Application

The following section compares how Tuxedo and WebLogic Tuxedo Connector join an application:

• Tuxedo uses tpinit() to join an application.

- WebLogic Tuxedo Connector uses a WTCServer MBean to provide information required to create a path to the Tuxedo service. Security and client authentication is provided by configuring the Remote TDM and Imported Services MBean components of a WTCServer MBean. This pathway is created when the WebLogic Server is started and a WTCServer MBean is present in the config.xml file and assigned (targeted) to a server.
- WebLogic Tuxedo Connector uses <u>TuxedoConnection</u> to get a Tuxedo object and then
 uses <u>getTuxedoConnection()</u> to make a connection to the Tuxedo object. The following
 example shows how a WebLogic Server application joins a Tuxedo application using
 WebLogic Tuxedo Connector.

Listing 2-1 Example Client Code to Join a Tuxedo Application

Leaving an Application

The following section compares how Tuxedo and WebLogic Tuxedo Connector leave an application:

- Tuxedo uses tpterm() to leave an application.
- WebLogic Tuxedo Connector uses the JATMI primitive tpterm() to close a connection to a Tuxedo object.
- WebLogic Tuxedo Connector closes the pathway to a Tuxedo service when a WTCserver MBean is assigned a new target server or the server is shutdown.

Basic Client Operation

A client process uses Java and JATMI primitives to provide the following basic application tasks:

- Get a Tuxedo Object
- Perform Message Buffering
- Send and Receive Messages
- Close a Connection to a Tuxedo Object

A client may send and receive any number of service requests before leaving the application.

Get a Tuxedo Object

Establish a connection to a remote domain by using the TuxedoConnectionFactory to lookup "tuxedo.services.TuxedoConnection" in the JNDI tree and get a TuxedoConnection object using getTuxedoConnection().

Perform Message Buffering

Use the following TypedBuffers when sending and receiving messages between your application and Tuxedo:

Table 2-1 TypedBuffers

Buffer Type	Description
TypedString	Buffer type used when the data is an array of characters that terminates with the null character. Tuxedo equivalent: STRING.
TypedCArray	Buffer type used when the data is an undefined array of characters (byte array), any of which can be null. Tuxedo equivalent: CARRAY.

Table 2-1 TypedBuffers

Buffer Type	Description
TypedFML	Buffer type used when the data is self-defined. Each data field carries its own identifier, an occurrence number, and possibly a length indicator. Tuxedo equivalent: FML.
TypedFML32	Buffer type similar to TypeFML but allows for larger character fields, more fields, and larger overall buffers. Tuxedo equivalent: FML32.
TypedXML	Buffer type used when data is an XML based message. Tuxedo equivalent: XML for Tuxedo Release 7.1 and higher.
TypedView	Buffer type used when the application uses a Java structure to define the buffer structure using a view description file. Tuxedo equivalent: View
TypedView32	Buffer type similar to View but allows for larger character fields, more fields, and larger overall buffers. Tuxedo equivalent: View32.

Send and Receive Messages

WebLogic Tuxedo Connector clients support three types of communications with Tuxedo service applications:

- Request/Response Communication
- Conversational Communication
- Enqueuing and Dequeuing Messages

Request/Response Communication

Note: WebLogic Tuxedo Connector does not provide a JATMI primitive to support setting the priority of a message request. All messages originating from a WebLogic Tuxedo Connector client have a message priority of 50.

Use the following JATMI primitives to request and receive response messages between your WebLogic Tuxedo Connector client application and Tuxedo:

Table 2-2 JATMI Primitives

Name	Operation
tpacall	Use for asynchronous invocations of a Tuxedo service. This JATMI primitive has two forms: • deferred synchronous • asynchronous
tpcall	Use for synchronous invocation of a Tuxedo service.
tpgetrply	Use for retrieving replies from deferred synchronous calls to a Tuxedo service.
tpcancel	Use to cancel an outstanding message reply for a call descriptor returned by tpacall.
	Note: You can not use tpcancel to cancel a call descriptor associated with a transaction.

Using Synchronous Service Calls

Use tpcall to send a request to a service and synchronously await for the reply. The service specified must be advertised by your Tuxedo application. Logically, tpcall() has the same functionality as calling tpacall() and immediately calling tpgetreply().

Using Deferred Synchronous Service Calls

A deferred synchronous tpacall allows you to send a request to a Tuxedo service and not immediately wait for the reply. This allows you to send a request, perform other work, and then retrieve the reply.

A deferred tpacall() service call sends a request to a Tuxedo service and immediately returns from the call. The service specified must be advertised by your Tuxedo application. Upon successful completion of the call, tpacall() returns an object that serves as a descriptor. The calling thread is now available to perform other tasks. You can use the call descriptor to:

- Get the correct reply for the sent request using tpgetreply()
- Cancel an outstanding message reply using tpcancel().

When you are ready to retrieve the reply, use tpgetreply() to dequeue the reply using the call descriptor returned by tpacall(). If the reply is not immediately available, the calling thread polls for the reply.

If tpacall() is in a transaction, you must receive the reply using tpgetreply() before the transaction can commit. You can not use tpcancel to cancel a call descriptor associated with a transaction. For example: If you make three tpacall() requests in a transaction, you must make three tpgetreply() calls and successfully dequeue a reply for each of the three requests for the transaction to commit.

Using Asynchronous Calls

The asynchronous tpacall allows you to send a request to a Tuxedo service and release the thread resource that performed the call to the thread pool. This allows a very large number of outstanding requests to be serviced with a much smaller number of threads.

An asynchronous tpacall() service call sends a request to a Tuxedo service. The service specified must be advertised by your Tuxedo application. Upon successful completion of the call, asynchronous tpacall() returns an object that serves as a descriptor. The calling thread is now available to perform other tasks. You can use the call descriptor to identify the correct message reply from TpacallAsynchReply for a sent message request or cancel an outstanding message reply using tpcancel().

Note: You can not use the call descriptor to invoke tpgetreply().

When the service reply is ready, the callback object is invoked on a different thread. If the original request succeeded, the TpacallAsynchReply.sucess method returns the reply from the service. If the original request failed, the TpacallAsynchReply.failure method returns a failure code.

You should implement the callback object using the following guidelines:

- The reply thread is obtained from the threadpool. The thread making the asynchronous tpacall() does not wait for the reply message.
- The user context of the reply thread will be restored to that of the original caller of asynchronous tpacall().
- It is up to the callback object to restore any additional context and resume whatever processing was interrupted when the original asynchronous tpacall() was made.
- It is up to you to synchronize work within the multi threaded environment. For example: If an asynchronous tpacall() request is made and the reply is returned immediately, it is

possible for the call back object to be modified by the reply thread before the calling thread has finished.

- The reply thread will not retain the transaction context of the calling thread.
- If asynchronous tpacall() is in a transaction, you must receive the reply using TpacallAsynchReply before the transaction can commit. You can not use tpcancel to cancel a call descriptor associated with a transaction.

Conversational Communication

Note: For more information on Conversational Communication, see "WebLogic Tuxedo Connector JATMI Conversations" on page 6-1.

Use the following conversational primitives when creating conversational clients that communicate with Tuxedo services:

Table 2-3 WebLogic Tuxedo Connector Conversational Client Primitives

Name	Operation
tpconnect	Use to establish a connection to a Tuxedo conversational service.
tpdiscon	Use to abort a connection and generate a TPEV_DISCONIMM event when executed by the process controlling the conversation.
tprecv	Use to receive data across an open connection from a Tuxedo application.
tpsend	Use to send data across a open connection to a Tuxedo application.

Enqueuing and Dequeuing Messages

Use the following JATMI primitives to enqueue and dequeue messages between your WebLogic Tuxedo Connector client application and Tuxedo /Q:

Table 2-4 JATMI Primitives

Name	Operation
tpdequeue	Use for receiving messages from a Tuxedo /Q.
tpenqueue	Use for placing a message on a Tuxedo /Q.

Close a Connection to a Tuxedo Object

Use tpterm() to close a connection to an object and prevent future operations on this object.

Example Client EJB

The following Java code provides an example of the ToupperBean. java client EJB which sends a string argument to a server and receives a reply string from the server.

Listing 2-2 Example Client Application

```
}
     catch (NamingException ne) {
          // Could not get the tuxedo object, throw TPENOENT
           throw new TPException(TPException.TPENOENT, "Could not get
TuxedoConnectionFactory : " + ne);
     }
    myTux = tcf.getTuxedoConnection();
    myData = new TypedString(toConvert);
     log("About to call tpcall");
     try {
         myRtn = myTux.tpcall("TOUPPER", myData, 0);
}
     catch (TPReplyException tre) {
          log("tpcall threw TPReplyExcption " + tre);
          throw tre;
     }
     catch (TPException te) {
          log("tpcall threw TPException " + te);
          throw te;
     }
     catch (Exception ee) {
          log("tpcall threw exception: " + ee);
          throw new TPException(TPException.TPESYSTEM, "Exception: " + ee);
     log("tpcall successfull!");
    myData = (TypedString) myRtn.getReplyBuffer();
    myTux.tpterm();// Closing the association with Tuxedo
    return (myData.toString());
}
```

2-9



Developing WebLogic Tuxedo Connector Service EJBs

The following sections provide information on how to create WebLogic Tuxedo Connector service EJBs:

- Basic Service EJB Operation
- Example Service EJB

Basic Service EJB Operation

A service application uses Java and JATMI primitives to provide the following tasks:

- Access Service Information
- Buffer Messages
- Perform the Requested Service

Access Service Information

Use the TPServiceInformation class to access service information sent by the Tuxedo client to run the service.

Table 3-1 JATMI TPServiceInformation Primitives

Buffer Type	Description	
getServiceData()	Use to return the service data sent from the Tuxedo Client.	
<pre>getServiceFlags()</pre>	Use to return the service flags sent from the Tuxedo Client.	
getServiceName()	Use to return the service name that was called.	

Buffer Messages

Use the following TypedBuffers when sending and receiving messages between your application and Tuxedo:

Table 3-2 TypedBuffers

Buffer Type	Description
TypedString	Buffer type used when the data is an array of characters that terminates with the null character. Tuxedo equivalent: STRING.
TypedCArray	Buffer type used when the data is an undefined array of characters (byte array), any of which can be null. Tuxedo equivalent: CARRAY.
TypedFML	Buffer type used when the data is self-defined. Each data field carries its own identifier, an occurrence number, and possibly a length indicator. Tuxedo equivalent: FML.
TypedFML32	Buffer type similar to TypeFML but allows for larger character fields, more fields, and larger overall buffers. Tuxedo equivalent: FML32.
TypedXML	Buffer type used when data is an XML based message. Tuxedo equivalent: XML for Tuxedo Release 7.1 and higher.
TypedView	Buffer type used when the application uses a Java structure to define the buffer structure using a view description file. Tuxedo equivalent: VIEW

Table 3-2 TypedBuffers

Buffer Type	Description
TypedView32	Buffer type similar to View but allows for larger character fields, more fields, and larger overall buffers. Tuxedo equivalent: VIEW32.
TypedXOctet	Buffer type used when the data is an undefined array of characters (byte array) any of which can be null. X_OCTET is identical in semantics to CARRAY. Tuxedo equivalent: X_OCTET.
TypedXCommon	Buffer type identical in semantics to View. Tuxedo equivalent: VIEW.
TypedXCType	Buffer type identical in semantics to View. Tuxedo equivalent: VIEW.

Perform the Requested Service

Use Java code to express the logic required to provide your service.

Return Client Messages for Request/Response Communication

Use the TuxedoReply class setReplyBuffer() method to respond to client requests.

Use tpsend and tprecy for Conversational Communication

Note: For more information on Conversational Communication, see "WebLogic Tuxedo Connector JATMI Conversations" on page 6-1.

Use the following JATMI primitives when creating conversational servers that communicate with Tuxedo clients:

Table 3-3 WebLogic Tuxedo Connector Conversational Client Primitives

Name	Operation
tpconnect	Use to establish a connection to a Tuxedo conversational service.
tpdiscon	Use to abort a connection and generate a TPEV_DISCONIMM event when executed by the process controlling the conversation.

Table 3-3 WebLogic Tuxedo Connector Conversational Client Primitives

Name	Operation
tprecv	Use to receive data across an open connection from a Tuxedo application.
tpsend	Use to send data across a open connection to a Tuxedo application.

Example Service EJB

The following provides an example of the TolowerBean.java service EJB which receives a string argument, converts the string to all lower case, and returns the converted string to the client.

Listing 3-1 Example Service EJB

```
public Reply service(TPServiceInformation mydata) throws TPException {
    TypedString data;
    String lowered;
    TypedString return_data;

    log("service tolower called");

    data = (TypedString) mydata.getServiceData();
    lowered = data.toString().toLowerCase();
    return_data = new TypedString(lowered);

    mydata.setReplyBuffer(return_data);
    return (mydata);
}
...
...
```

Using WebLogic Tuxedo Connector for RMI/IIOP and CORBA Interoperability

Note: You will need to perform some administration tasks to configure the WebLogic Tuxedo Connector for CORBA interoperability. For information on how to administer the WebLogic Tuxedo Connector for CORBA interoperability, see Administration of CORBA Applications at

http://e-docs.bea.com/wls/docs90/wtc admin/WTC Admin CORBA.html.

For information on how to develop Tuxedo CORBA applications, see CORBA Programming at http://e-docs.bea.com/tuxedo/tux81/interm/corbaprog.htm.

The following sections provide information on how to modify your applications to use WebLogic Tuxedo Connector to support interoperability between WebLogic Server and Tuxedo CORBA objects:

- How to Develop WebLogic Tuxedo Connector Client Beans using the CORBA Java API
- How to Develop RMI/IIOP Applications for the WebLogic Tuxedo Connector
- How to Use FederationURL Formats
- How to Manage Transactions for Tuxedo CORBA Applications

How to Develop WebLogic Tuxedo Connector Client Beans using the CORBA Java API

Note: For more information on the WebLogic CORBA API implementation, see Using the CORBA API in *Using RMI over IIOP Programming Models to Develop Applications*.

The WebLogic Tuxedo Connector enables objects (such as EJBs or RMI objects) to invoke upon CORBA objects deployed in Tuxedo using the CORBA Java API (Outbound). This release of WebLogic Tuxedo Connector implements a new WTC ORB which uses WebLogic Server RMI-IIOP runtime and CORBA support. This enhancement provides the following features:

- Support of out and inout parameters
- Support for a call a CORBA service from WebLogic Server using transactions and security.
- Support for an ORB hosted in JNDI rather than an instance of the JDK ORB used in previous releases.
- A wrapper is provided to allow users with legacy applications to use the new ORB without
 modifying their existing applications. BEA recommends that users migrate to the new
 method of looking up the ORB in JNDI instead of doing:

```
ORB orb = ORB.init(args, Prop);
```

To use CORBA Java API, you must use the WTC ORB. Use one of the following methods to obtain an ORB in your Bean:

```
Properties Prop;
Prop = new Properties();
Prop.put("org.omg.CORBA.ORBClass", "weblogic.wtc.corba.ORB");
ORB orb = ORB.init(new String[0], Prop);

or
ORB orb = (ORB) (new InitialContext().lookup("java:comp/ORB"));
or
ORB orb = ORB.init();
```

You can use either of the following methods to reference objects deployed in Tuxedo:

- Using CosNaming Service
- Using FactoryFinder

Using CosNaming Service

Note: For more information on object references, see "How to Use FederationURL Formats" on page 4-12.

1. The WebLogic Tuxedo Connector us[---es the CosNaming service to get a reference to an object in the remote Tuxedo CORBA domain. This is accomplished by using a corbaloc:tgiop or corbaname:tgiop object reference. The following statements use the CosNaming service to get a reference to a Tuxedo CORBA Object:

```
// Get the simple factory.
org.omg.CORBA.Object simple_fact_oref =
    orb.string_to_object("corbaname:tgiop:simpapp#simple_factory");
```

Where:

- simpapp is the domain id of the Tuxedo domain specified in the Tuxedo UBB.
- simple_factory is the name that the object reference was bound to in the Tuxedo CORBA CosNaming server.

Example ToupperCorbaBean.java Code

Note: For an example on how to develop client beans for outbound Tuxedo CORBA objects, see the SAMPLES_HOME\server\examples\src\examples\wtc\corba\simpappcns package in your WebLogic Server examples distribution.

The following ToupperCorbaBean. java code provides an example of how to call the WTC ORB and get an object reference using the COSNaming Service.

Listing 4-1 Example Service Application

```
// Get the simple factory.
   org.omg.CORBA.Object simple_fact_oref =
   orb.string_to_object("corbaname:tgiop:simpapp#simple_factory");
   //Narrow the simple factory.
   SimpleFactory simple_factory_ref =
   SimpleFactoryHelper.narrow(simple_fact_oref);
   // Find the simple object.
   Simple simple = simple_factory_ref.find_simple();
   // Convert the string to upper case.
   org.omg.CORBA.StringHolder buf =
     new org.omg.CORBA.StringHolder(toConvert);
   simple.to_upper(buf);
   return buf.value;
catch (Exception e) {
   throw new RemoteException("Can't call TUXEDO CORBA server: " +e);
}
```

Using FactoryFinder

Note: For more information on object references, see "How to Use FederationURL Formats" on page 4-12.

WebLogic Tuxedo Connector provides support for FactoryFinder objects using the find_one_factory_by_id method. This is accomplished by using a corbaloc:tgiop or corbaname:tgiop object reference. Use the following method to obtain the FactoryFinder object using the ORB:

}

```
org.omg.CORBA.Object simple_fact_oref =
    fact_finder_ref.find_one_factory_by_id(SimpleFactoryHelper.id());
```

Where:

- simpapp is the domain id of the Tuxedo domain specified in the Tuxedo UBB.
- FactoryFinder is the name that the object reference was bound to in the Tuxedo CORBA server.

WLEC to WebLogic Tuxedo Connector Migration

WLEC is deprecated in this release of WebLogic Server. WLEC uses should migrate their applications to WebLogic Tuxedo Connector. For more information, see WLEC to WebLogic Tuxedo Connector Migration Guide at http://e-docs.bea.com/wls/docs90/wlec-migration/index.html.

Example Code

The following code provides an example of how to call the WTC ORB and get an object reference using FactoryFinder.

Listing 4-2 Example FactoryFinder Code

```
.
.
.
public ConverterResult convert (String changeCase, String mixed)
throws ProcessingErrorException
{
    String result;
    try {
        // Initialize the ORB.
        String args[] = null;
        Properties Prop;
        Prop = new Properties();
        Prop.put("org.omg.CORBA.ORBClass", "weblogic.wtc.corba.ORB");
        ORB orb = (ORB)new InitialContext().lookup("java:comp/ORB");
        org.omg.CORBA.Object fact_finder_oref =
```

```
orb.string_to_object("corbaloc:tgiop:simpapp/FactoryFinder");
     // Narrow the factory finder.
     FactoryFinder fact_finder_ref =
        FactoryFinderHelper.narrow(fact_finder_oref);
     // find_one_factory_by_id
     org.omg.CORBA.Object simple_fact_oref =
        fact_finder_ref.find_one_factory_by_id(FactoryFinderHelper.id());
     // Narrow the simple factory.
     SimpleFactory simple_factory_ref =
        SimpleFactoryHelper.narrow(simple_fact_oref);
     // Find the simple object.
     Simple simple = simple_factory_ref.find_simple();
     if (changeCase.equals("UPPER")) {
     // Invoke the to_upper opeation on M3 Simple object
     org.omg.CORBA.StringHolder buf =
        new org.omg.CORBA.StringHolder(mixed);
     simple.to upper(buf);
     result = buf.value;
     else
     result = simple.to_lower(mixed);
     catch (org.omg.CORBA.SystemException e) {e.printStackTrace();
     throw new ProcessingErrorException("Converter error: Corba system exc
eption: " + e);
     }
     catch (Exception e) {
     e.printStackTrace();
     throw new ProcessingErrorException("Converter error: " + e);
```

```
}
return new ConverterResult(result);
}
.
.
```

How to Develop RMI/IIOP Applications for the WebLogic Tuxedo Connector

Note: For more information on how to develop RMI/IIOP applications, see Programming WebLogic RMI over IIOP at http://e-docs.bea.com/wls/docs90/rmi_iiop/index.html.

For an example on how to develop RMI/IIOP applications for the WebLogic Tuxedo Connector, see the

WL_HOME\samples\server\examples\src\examples\iiop\ejb\stateless\server\tux package in your WebLogic Server distribution.

RMI over IIOP (Internet Inter-ORB Protocol) extends RMI so that Java programs can interact with Common Object Request Broker Architecture (CORBA) clients and execute CORBA objects. The WebLogic Tuxedo Connector:

- Enables Tuxedo CORBA objects to invoke upon EJBs deployed in WebLogic Server (Inbound).
- Enables objects (such as EJBs or RMI objects) to invoke upon CORBA objects deployed in Tuxedo (Outbound).

The following sections provide information on how to modify RMI/IIOP applications to use the WebLogic Tuxedo Connector to interoperate with Tuxedo CORBA applications:

- How to Modify Inbound RMI/IIOP Applications to use the WebLogic Tuxedo Connector
- How to Develop Outbound RMI/IIOP Applications to use the WebLogic Tuxedo Connector

How to Modify Inbound RMI/IIOP Applications to use the WebLogic Tuxedo Connector

A client must pass the correct name to which the WebLogic Server's name service has been bound to the COSNaming Service.

The following code provides an example for obtaining a naming context. "WLS" is the bind name specified in the cnsbind command detailed in the Administration of CORBA Applications at http://e-docs.bea.com/wls/docs90/wtc_admin/WTC_Admin_CORBA.html.

Listing 4-3 Example Code to Obtain a Naming Context

How to Develop Outbound RMI/IIOP Applications to use the WebLogic Tuxedo Connector

An EJB must use a FederationURL to obtain the initial context used to access a remote Tuxedo CORBA object. Use the following sections to modify outbound RMI/IIOP applications to use the WebLogic Tuxedo Connector:

• How to Modify the ejb-jar.xml File to Pass a FederationURL to EJBs

• How to Modify EJBs to Use FederationURL to Access an Object

How to Modify the ejb-jar.xml File to Pass a FederationURL to EJBs

The following code provides an example of how to configure an ejb-jar.xml file to pass a FederationURL format to the EJB at run-time.

Listing 4-4 Example ejb-jar.xml File Passing a FederationURL to an EJB

```
<?xml version="1.0"?>
<!DOCTYPE ejb-jar PUBLIC '-//Sun Microsystems, Inc.//DTD Enterprise JavaBeans
1.1//EN' 'http://java.sun.com/j2ee/dtds/ejb-jar_1_1.dtd'>
<ejb-jar>
     <small-icon>images/green-cube.gif</small-icon>
     <enterprise-beans>
     <session>
          <small-icon>images/orange-cube.gif</small-icon>
          <ejb-name>IIOPStatelessSession</ejb-name>
          <home>examples.iiop.ejb.stateless.TraderHome
          <remote>examples.iiop.ejb.stateless.Trader</remote>
          <ejb-class>examples.iiop.ejb.stateless.TraderBean</ejb-class>
          <session-type>Stateless</session-type>
          <transaction-type>Container</transaction-type>
          <env-entry>
               <env-entry-name>foreignOrb</env-entry-name>
               <env-entry-type>java.lang.String </env-entry-type>
               <env-entry-value>corbaloc:tgiop:simpapp</env-entry-value>
          </env-entry>
          <env-entry>
               <env-entry-name>WEBL</env-entry-name>
               <env-entry-type>java.lang.Double </env-entry-type>
               <env-entry-value>10.0/env-entry-value>
          </env-entry>
          <env-entry>
               <env-entry-name>INTL</env-entry-name>
               <env-entry-type>java.lang.Double </env-entry-type>
               <env-entry-value>15.0</env-entry-value>
          </env-entry>
          <env-entry>
               <env-entry-name>tradeLimit</env-entry-name>
               <env-entry-type>java.lang.Integer </env-entry-type>
               <env-entry-value>500</env-entry-value>
          </env-entry>
     </session>
```

To pass the FederationURL to the EJB at run-time, add an env-entry for the EJB in the ejb-jar.xml file for your application. You must assign the following env-entry sub-elements:

- Assign env-entry-name
- Assign env-entry-type
- Assign env-entry-value

Assign env-entry-name

The env-entry-name element is used to specify the name of the variable used to pass the value in the env-entry-value element to the EJB. The example code shown in Figure 4-4 specifies the env-entry-name as foreignOrb.

Assign env-entry-type

The env-entry-type element is used to specify the data type (example String, Integer, Double) of the env-entry-value element that is passed to the EJB. The example code shown in Figure 4-4 specifies that the foreignOrb variable passes String data to the EJB.

Assign env-entry-value

The env-entry-value element is used to specify the data that is passed to the EJB. The example code shown in Figure 4-4 specifies that the foreignOrb variable passes the following FederationURL format to the EJB:

```
corbaloc:tgiop:simpapp
```

Where simpapp is the DOMAINID of the Tuxedo remote service specified in the Tuxedo UBB.

How to Modify EJBs to Use FederationURL to Access an Object

This section provides information on how to use the FederationURL to obtain the InitialContext used to access a remote Tuxedo CORBA object.

The following code provides an example of how to use FederationURL to get an InitialContext.

Listing 4-5 Example TraderBean.java Code to get InitialContext

```
public void createRemote() throws CreateException {
     log("createRemote() called");
     try {
          InitialContext ic = new InitialContext();
     // Lookup a EJB-like CORBA server in a remote CORBA domain
          Hashtable env = new Hashtable();
          env.put(Context.PROVIDER_URL, (String)
             ic.lookup("java:/comp/env/foreignOrb")
             + "/NameService");
          InitialContext cos = new InitialContext(env);
          TraderHome thome =
             (TraderHome) PortableRemoteObject.narrow(
             cos.lookup("TraderHome_iiop"), TraderHome.class);
             remoteTrader = thome.create();
}
     catch (NamingException ne) {
     throw new CreateException("Failed to find value "+ne);
}
     catch (RemoteException re) {
     throw new CreateException("Error creating remote ejb "+re);
```

•

Use the following steps to use FederationURL to obtain an InitialContext for a remote Tuxedo CORBA object:

1. Retrieve the FederationURL format defined in the ejb-jar.xml file.

Example:

```
"ic.lookup("java:/comp/env/foreignOrb")
```

The example code shown in Listing 4-4 specifies that the foreignOrb variable passes the following FederationURL format to the EJB:

```
corbaloc:tgiop:simpapp
```

2. Concatenate the FederationURL format with "/NameService" to form the FederationURL.

Example:

```
"ic.lookup("java:/comp/env/foreignOrb") + "/NameService"
The resulting FederationURL is:
corbaloc:tgiop:simpapp/NameService
```

3. Get the InitialContext.

Example:

```
env.put(Context.PROVIDER_URL, (String)
    ic.lookup("java:/comp/env/foreignOrb") + "/NameService");
InitialContext cos = new InitialContext(env);
```

The result is the InitialContext of the Tuxedo CORBA object.

How to Use FederationURL Formats

This section provides information on the syntax for the following FederationURL formats:

- The CORBA URL syntax is described in the CORBA specification. For more information, see the OMG Web Site at http://www.omg.org/.
- The corbaloc: tgiop form is specific to the BEA tgiop protocol.

Using corbaloc URL Format

This section provides the syntax for corbaloc URL format:

```
<corbaloc> = "corbaloc:tgiop":[<version>] <domain>["/"<key_string>]
<version> = <major> "." <minor> "@" | empty_string
<domain> = TUXEDO CORBA domain name
<major> = number
<minor> = number
<key_string> = <string> | empty_string
```

Examples of corbaloc:tgiop

This section provides examples on how to use corbaloc:tgiop

```
orb.string_to_object("corbaloc:tgiop:simpapp/NameService");
orb.string_to_object("corbaloc:tgiop:simpapp/FactoryFinder");
orb.string_to_object("corbaloc:tgiop:simpapp/InterfaceRepository");
orb.string_to_object("corbaloc:tgiop:simpapp/Tobj_SimpleEventsService");
orb.string_to_object("corbaloc:tgiop:simpapp/NotificationService");
orb.string_to_object("corbaloc:tgiop:1.1@simpapp/NotificationService);
```

Examples using -ORBInitRef

Given the following -ORBInitRef definitions:

You can also use the -ORBInitRef option to orb.init and resolve_initial_reference.

```
-ORBInitRef FactoryFinder=corbaloc:tgiop:simp/FactoryFinder
-ORBInitRef InterfaceRepository=corbaloc:tgiop:simp/InterfaceRepository
-ORBInitRef
Tobj_SimpleEventService=corbaloc:tgiop:simp/Tobj_SimpleEventService
-ORBInitRef NotificationService=corbaloc:tgiop:simp/NotificationService
then:
orb.resolve_initial_references("NameService");
```

```
orb.resolve_initial_references("FactoryFinder");
orb.resolve_initial_references("InterfaceRepository");
orb.resolve_initial_references("Tobj_SimpleEventService");
orb.resolve_initial_references("NotificationService");
```

Examples Using -ORBDefaultInitRef

You can use the -ORBDefaultInitRef and resolve_initial_reference.

Given the following -ORBDefaultInitRef definition:

Using the corbaname URL Format

You can also use the corbaname format instead of the corbaloc format.

-ORBInitRef NameService=corbaloc:tgiop:simpapp/NameService

Examples Using -ORBInitRef

Given the following -ORBInitRef definition:

```
then:
orb.string_to_object("corbaname:rir:#simple_factory");
orb.string_to_object("corbaname:tgiop:simpapp#simple_factory");
orb.string_to_object("corbaname:tgiop:1.1@simpapp#simple_factory");
orb.string_to_object("corbaname:tgiop:simpapp#simple/simple_factory");
```

How to Manage Transactions for Tuxedo CORBA Applications

Note: For more information on managing transactions in Tuxedo CORBA applications, see Overview of Transactions in BEA Tuxedo CORBA Applications at http://e-docs.bea.com/tuxedo/tux80/transact/gstrx.htm.

The WebLogic Tuxedo Connector uses the Java Transaction API (JTA) to manage transactions with Tuxedo Corba Applications. For more detailed information, see:

- Programming WebLogic JTA at http://e-docs.bea.com/wls/docs90/jta/index.html
- Transaction Design and Management Options at http://e-docs.bea.com/wls/docs90/ejb/design_best_practices.html#TransactionDesignandManagementOptions





WebLogic Tuxedo Connector JATMI Transactions

The following sections provide information on global transactions and how to define and manage them in your applications:

- Global Transactions
- JTA Transaction API
- Defining a Transaction
- WebLogic Tuxedo Connector Transaction Rules
- Example Transaction Code

Global Transactions

A global transaction is a transaction that allows work involving more than one resource manager and spanning more than one physical site to be treated as one logical unit. A global transaction is always treated as a specific sequence of operations that is characterized by the following four properties:

- Atomicity: All portions either succeed or have no effect.
- Consistency: Operations are performed that correctly transform the resources from one consistent state to another.
- Isolation: Intermediate results are not accessible to other transactions, although other processes in the same transaction may access the data.

• Durability: All effects of a completed sequence cannot be altered by any kind of failure.

JTA Transaction API

Note: For more detailed information, see the JTA API at http://java.sun.com/products/jta/index.htm.

The WebLogic Tuxedo Connector uses the Java Transaction API (JTA) to manage transactions.

Types of JTA Interfaces

JTA offers three types of transaction interfaces:

- Transaction
- TransactionManager
- UserTransaction

Transaction

The Transaction interface allows operations to be performed against a transaction in the target Transaction object. A transaction object is created to correspond to each global transaction created. Use the Transaction interface to enlist resources, synchronize registration, and perform transaction completion and status query operations.

TransactionManager

The TransactionManager interface allows the application server to communicate to the Transaction Manager for transaction boundaries demarcation on behalf of the application. Use the TransactionManager interface to communicate to the transaction manager on behalf of container-managed EJB components.

UserTransaction

The UserTransaction interface is a subset of the TransactionManager interface. Use the UserTransaction interface when it is necessary to restrict access to Transaction object.

JTA Transaction Primitives

The following table maps the functionality of Tuxedo transaction primitives to equivalent JTA transaction primitives.

Table 5-1 Mapping Tuxedo Transaction Primitives to JTA Equivalents

Tuxedo	Tuxedo Functionality	JTA Equivalent
tpabort	Use to end a transaction.	setRollbackOnly or rollback
tpcommit	Use to complete a transaction.	commit
tpgetlev	Use to determine if a service routine is in transaction mode.	getStatus
tpbegin	Use to begin a transaction.	setTransactionTimeout begin

Defining a Transaction

Transactions can be defined in either client or server processes. A transaction has three parts: a starting point, the program statements that are in transaction mode, and a termination point.

To explicitly define a transaction, call the <code>begin()</code> method. The same process that makes the call, the initiator, must also be the one that terminates it by invoking a <code>commit()</code>, <code>setRollbackOnly()</code>, or <code>rollback()</code>. Any service subroutines that are called between the transaction delimiter become part of the current transaction.

Starting a Transaction

Note: Setting setTransactionTimeout() to unrealistically large values delays system detection and reporting of errors. Use time-out values to ensure response to service requests occur within a reasonable time and to terminate transactions that have encountered problem, such as a network failure. For productions environments, adjust the time-out value to accommodate expected delays due to system load and database contention.

A transaction is started by a call to begin(). To specify a time-out value, precede the begin() statement with a setTransactionTimeout(int seconds) statement.

To propagate the transaction to Tuxedo, you must do the following:

- Look up a TuxedoConnectionFactory object in the JNDI.
- Get a TuxedoConnection object using getTuxedoConnection().

Using TPNOTRAN

Service routines that are called within the transaction delimiter are part of the current transaction. However, if tpcall() or tpacall() have the flags parameter set to TPNOTRAN, the operations performed by the called service do not become part of that transaction. As a result, services performed by the called process are not affected by the outcome of the current transaction.

Terminating a Transaction

A transaction is terminated by a call to <code>commit()</code>, <code>rollback()</code>, or <code>setRollbackOnly()</code>. When <code>commit()</code> returns successfully, all changes to the resource as a result of the current transaction become permanent. In order for a <code>commit()</code> to succeed, the following two conditions must be met:

- The calling process must be the same one that initiated the transaction with a begin ()
- The calling process must have no transaction replies outstanding

If either condition is not true, the call fails and an exception is thrown.

setRollbackOnly() and rollback() are used to indicate an abnormal condition and to roll back any call descriptors to their original state.

- Use setRollbackOnly() if further processing or cleanup is needed before rolling back the transaction.
- Use rollback() if no further processing or cleanup is required before rolling back the transaction.

WebLogic Tuxedo Connector Transaction Rules

You must follow certain rules while in transaction mode to insure successful completion of a transaction. The basic rules of etiquette that must be observed while in a transaction mode follow:

- You must propagate the transaction to Tuxedo using a TuxedoConnection object after you initiate a transaction with a begin ().
- tpterm() closes a connection to an object and prevents future operations on this object.

- Processes that are participants in the same transaction must require replies for their requests.
- Requests requiring no reply can be made only if the flags parameter of tpacall() is set to TPNOREPLY.
- A service must retrieve all asynchronous transaction replies before calling commit().
- The initiator must retrieve all asynchronous transaction replies before calling begin().
- The asynchronous replies that must be retrieved include those that are expected from non-participants of the transaction, that is, replies expected for requests made with a tpacall() suppressing the transaction but not the reply.
- If a transaction has not timed out but is marked abort-only, further communication should be performed with the TPNOTRAN flag set so that the work done as a result of the communication has lasting effect after the transaction is rolled back.
- If a transaction has timed out:
 - the descriptor for the timed out call becomes stale and any further reference to it will return TPEBADDESC.
 - further calls to tpgetrply() or tprecv() for any outstanding descriptors will return
 the global state of transaction time-out by setting tperrono to TPETIME.
 - asynchronous calls can be make with the *flags* parameter of tpacall() set to TPNOREPLY | TPNOBLOCK | TPNOTRAN.
- Once a transaction has been marked abort-only for reasons other than time-out, a call to tpgetrply() will return whatever represents the local state of the call, that is, it can either return success or an error code that represents the local condition.
- Once a descriptor is used with tpgetrply() to retrieve a reply, it becomes invalid and any
 further reference to it will return TPEBADDESC.
- Once a descriptor is used with tpsend() or tprecv() to report an error condition, it becomes invalid and any further reference to it will return TPEV_DISCONIMM.
- Once a transaction is aborted, all outstanding transaction call descriptions (made without the TPNOTRAN flag) become stale, and any further reference to them will return TPEBADDESC.

Example Transaction Code

The following provides a code example for a transaction:

Listing 5-1 Example Transaction Code

```
public class TransactionSampleBean implements SessionBean {
. . . . .
public int transaction_sample () {
     int ret = 0;
     try {
          javax.naming.Context myContext = new InitialContext();
          TransactionManager tm = (javax.transaction.TransactionManager)
          myContext.lookup("javax.transaction.TransactionManager");
// Begin Transaction
          tm.begin ();
          TuxedoConnectionFactory tuxConFactory = (TuxedoConnectionFactory)
          ctxt.lookup("tuxedo.services.TuxedoConnection");
// You could do a local JDBC/XA-database operation here
// which will be part of this transaction.
. . . . .
// NOTE 1: Get the Tuxedo Connection only after
// you begin the transaction if you want the
// Tuxedo call to be part of the transaction!
// NOTE 2: If you get the Tuxedo Connection before
// the transaction was started, all calls made from
// that Tuxedo Connection are out of scope of the
// transaction.
          TuxedoConnection myTux = tuxConFactory.getTuxedoConnection();
// Do a tpcall. This tpcall is part of the transaction.
          TypedString depositData = new TypedString("somecharacters, 5000.00");
          Reply depositReply = myTux.tpcall("DEPOSIT", depositData, 0);
// You could also do tpcalls which are not part of
// transaction (For example, Logging all attempted
// operations etc.) by setting the TPNOTRAN Flag!
          TypedString logData =
          new TypedString("DEPOSIT:somecharacters,5000.00");
          Reply logReply = myTux.tpcall("LOGTRAN", logData,
          ApplicationToMonitorInterface.TPNOTRAN);
```

```
// Done with the Tuxedo Connection. Do tpterm.
         myTux.tpterm ();
// Commit Transaction...
          tm.commit ();
// NOTE: The TuxedoConnection object which has been
// used in this transaction, can be used after the
// transaction only if TPNOTRAN flag is set.
}
          catch (NamingException ne) {
          System.out.println ("ERROR: Naming Exception looking up JNDI: " + ne);
          ret = -1;
}
          catch (RollbackException re) {
          System.out.println("ERROR: TRANSACTION ROLLED BACK: " + re);
          ret = 0;
}
          catch (TPException te) {
          System.out.println("ERROR: tpcall failed: TpException: " + te);
          ret = -1;
}
          catch (Exception e) {
          log ("ERROR: Exception: " + e);
          ret = -1;
}
          return ret;
}
```



WebLogic Tuxedo Connector JATMI Conversations

Note: For more information on conversational communications for BEA Tuxedo, see Writing Conversational Clients and Servers at http://e-docs.bea.com/tuxedo/tux80/atmi/pgconv.htm.

The following sections provide information on conversations and how to define and manage them in your applications:

- Overview of WebLogic Tuxedo Connector Conversational Communication
- WebLogic Tuxedo Connector Conversation Characteristics
- WebLogic Tuxedo Connector JATMI Conversation Primitives
- Creating WebLogic Tuxedo Connector Conversational Clients and Servers
- Sending and Receiving Messages
- Ending a Conversation
- Executing a Disorderly Disconnect
- Understanding Conversational Communication Events
- WebLogic Tuxedo Connector Conversation Guidelines

Overview of WebLogic Tuxedo Connector Conversational Communication

WebLogic Tuxedo Connector supports BEA Tuxedo conversations as a method to exchange messages between WebLogic Server and Tuxedo applications. In this form of communication, a virtual connection is maintained between the client and the server and each side maintains information about the state of the conversation. The process that opens a connection and starts a conversation is the originator of the conversation. The process with control of the connection is the initiator; the process without control is called the subordinate. The connection remains active until an event occurs to terminate it.

During conversational communication, a half-duplex connection is established between the initiator and the subordinate. Control of the connection is passed between the initiator and the subordinate. The process that has control can send messages (the initiator); the process that does not have control can only receive messages (the subordinate).

WebLogic Tuxedo Connector Conversation Characteristics

WebLogic Tuxedo Connector JATMI conversations have the following characteristics:

- Data is passed using TypedBuffers. The type and sub-type of the data must match one of the types and sub-types recognized by the service.
- The logical connection between the conversational client and the conversational server remains active until it is terminated.
- Any number of messages can be transmitted across a connection between a conversational client and the conversational server.
- A WebLogic Tuxedo Connector conversational client initiates a request for service using tpconnect rather than a tpcall or tpacall.
- WebLogic Tuxedo Connector conversational clients and servers use the JATMI primitives tpsend to send data and tprecv to receive data.
- A conversational client only sends service requests to a conversational server.
- Conversational servers are prohibited from making calls to tpforward.

WebLogic Tuxedo Connector JATMI Conversation Primitives

Use the following WebLogic Tuxedo Connector primitives when creating conversational clients and servers that communicate between WebLogic Server and Tuxedo:

Table 6-1 WebLogic Tuxedo Connector Conversational Client Primitives

Name	Operation
tpconnect	Use to establish a connection to a Tuxedo conversational service.
tpdiscon	Use to abort a connection and generate a TPEV_DISCONIMM event.
tprecv	Use to receive data across an open connection from a Tuxedo application.
tpsend	Use to send data across a open connection to a Tuxedo application.

Creating WebLogic Tuxedo Connector Conversational Clients and Servers

The following sections provide information on how to create conversational clients and servers.

Creating Conversational Clients

Follow the steps outlined in "Developing WebLogic Tuxedo Connector Client EJBs" on page 2-1 to create WebLogic Tuxedo Connector conversational clients. The following section provide information on how to use tpconnect to open a connection and start a conversation.

Establishing a Connection to a Tuxedo Conversational Service

A WebLogic Tuxedo Connector conversational client must establish a connection to the Tuxedo conversational service. Use the JATMI primitive tpconnect to open a connection and start a conversation. A successful call returns an object that can be used to send and receive data for a conversation.

The following table describes tpconnect parameters:

Table 6-2 WebLogic Tuxedo Connector JATMI tpconnect Parameters

Parameter	Description	
SVC	Character pointer to a conversational service name. If you do not specify a <i>svc</i> , the call will fail and TPException is set to TPEV_DISCONIMM.	
data	Pointer to the data buffer. When establishing a connection, you can send data simultaneously by setting the <i>data</i> parameter to point to a buffer. The type and subtype of the buffer must be recognized by the service being called. You can set the value of <i>data</i> to NULL to specify that no data is to be sent.	
flags	Use flags or combinations of flags as required by your application needs. Valid flag values are:	
	TPSENDONLY: specifies that the control is being retained by the originator. The called service is subordinate and can only receive data. Do not use in combination with TPRECVONLY.	
	TPRECVONLY: specifies that control is being passed to the called service. The originator becomes subordinate and can only receive data. Do not use in combination with TPSENDONLY.	
	TPNOTRAN: specifies that when <i>svc</i> is invoked and the originator is transaction mode, <i>svc</i> is not part of the originator's transaction. A call remains subject to transaction timeouts. If <i>svc</i> fails, the originator's transaction is unaffected.	
	TPNOBLOCK: specifies that a request is not sent if a blocking condition exists. If TPNOBLOCK is not specified, the originator blocks until the condition subsides, a transaction timeout occurs, or a blocking timeout occurs.	
	TPNOTIME: specifies that the originator will block indefinitely and is immune to blocking timeouts. If the originator is in transaction mode, the call is subject to transaction timeouts.	

Example TuxedoConversationBean.java Code

The following provides a code example to use tpconnect to start a conversation:

Listing 6-1 Example Conversation Code

```
Context ctx;
Conversation myConv;
TuxedoConnection myTux;
TuxedoConnectionFactory tcf;
.
.
.
ctx = new InitialContext();
tcf = (TuxedoConnectionFactory) ctx.lookup
("tuxedo.services.TuxedoConnection");
myTux = tcf.getTuxedoConnection();
flags =ApplicationToMonitorInterface.TPSENDONLY;
myConv = myTux.tpconnect("CONNECT_SVC",null,flags);
.
.
```

Creating WebLogic Tuxedo Connector Conversational Servers

Follow the steps outlined in "Developing WebLogic Tuxedo Connector Service EJBs" on page 3-1 to create WebLogic Tuxedo Connector conversational servers.

Sending and Receiving Messages

Once a conversational connection is established between a WebLogic Server application and a Tuxedo application, the communication between the initiator (sends message) and subordinate (receives message) is accomplished using send and receive calls. The following sections describe how WebLogic Tuxedo Connector applications use the JATMI primitives tpsend and tprecv:

- Sending Messages
- Receiving Messages

Sending Messages

Use the JATMI primitive tpsend to send a message to a Tuxedo application.

The following table describes tpsend parameters:

Table 6-3 WebLogic Tuxedo Connector JATMI tpconnect Parameters

Parameter	Description	
data	Pointer to the buffer containing the data sent with this conversation.	
flags	The flag can be one of the following:	
	TPRECVONLY: specifies that after the initiator's data is sent, the initiator gives up control of the connection. The initiator becomes subordinate and can only receive data.	
	TPNOBLOCK: specifies that the request is not sent if a blocking condition exists. If TPNOBLOCK is not specified, the originator blocks until the condition subsides, a transaction timeout occurs, or a blocking timeout occurs.	
	TPNOTIME : specifies that an initiator is willing to block indefinitely and is immune from blocking timeouts. The call is subject to transaction timeouts.	

Receiving Messages

Use the JATMI primitive tprecy to receive messages from a Tuxedo application.

The following table describes tprecy parameters:

Table 6-4 WebLogic Tuxedo Connector JATMI tpconnect Parameters

Parameter	Description	
flags	The flag can be one of the following:	
	TPNOBLOCK: specifies that tprecv does not wait for a reply to arrive. If a reply is available, tprecv gets the reply and returns. If this flag is not specified and a reply is not available, tprecv waits for one of the following to occur: a reply, a transaction timeout, or a blocking timeout.	
	TPNOTIME: specifies that tprecy waits indefinitely for a reply. tprecy is immune from blocking timeouts but is subject to transaction timeouts.	
	A flag value of 0 specifies that the initiator blocks until the condition subsides or a timeout occurs.	

Ending a Conversation

A conversation between WebLogic Server and Tuxedo ends when the server process successfully completes its tasks. The following sections describe how a conversation ends:

- Tuxedo Application Originates Conversation
- WebLogic Tuxedo Connector Application Originates Conversation
- Ending Hierarchical Conversations

Tuxedo Application Originates Conversation

A WebLogic Server conversational server ends a conversation by a successful call to return. A TPEV_SVCSUCC event is sent to the Tuxedo client that originated connection to indicate that the service finished successfully. The connection is then disconnected in an orderly manner.

WebLogic Tuxedo Connector Application Originates Conversation

A Tuxedo conversational server ends a conversation by a successful call to tpreturn. A TPEV_SVCSUCC event is sent to the WebLogic Tuxedo Connector client that originated connection to indicate that the service finished successfully. The connection is then disconnected in an orderly manner.

Ending Hierarchical Conversations

The order in which an conversation ends is important to gracefully end hierarchal conversations.

Assume there are two active connections: A-B and B-C. If B is a WebLogic Tuxedo Connector application in control of both connections, a call to return has the following effect: the call fails and a TPEV_SVCERR event is posted on all open connections, and the connections are closed in a disorderly manner.

In order to terminate both connections in an orderly manner, the application must execute the following sequence:

- 1. B calls tpsend with TPRECVONLY to transfer control of the B-C connection to the Tuxedo application C.
- 2. C calls departure with rval set to TPSUCCESS, TPFAIL, or TPEXIT.

3. B calls return and posts an event (TPEV_SVCSUCC or TPEV_SVCFAIL) for A.

Conversational services can make request/response calls. Therefore, in the preceding example, the calls from B to C may be executed using tpacall() or tpcall() instead of tpconnect. Conversational services are not permitted to make calls to tpforward.

Executing a Disorderly Disconnect

WebLogic Server conversational clients or servers execute a disorderly disconnect is through a call to tpdiscon. This is the equivalent of "pulling the plug" on a connection.

A call to tpdiscon:

- Immediately tears down the connection and generates a TPEV_DISCONIMM at the other end
 of the connection. Any data that has not yet reached its destination may be lost. If the
 conversation is part of a transaction, the transaction must be rolled back.
- Can only be called by the initiator of the conversation.

Understanding Conversational Communication Events

WebLogic Tuxedo Connector JATMI uses five events to manage conversational communication. The following table lists the events, the functions for which they are returned, and a detailed description of each.

Table 6-5 WebLogic Tuxedo Connector Conversational Communication Events

Event	Received by	Description
TPEV_SENDONLY	Tuxedo tprecv	Control of the connection has passed; this Tuxedo process can now call tpsend
	JATMI tprecv	Control of the connection has passed; this JATMI process can now call tpsend

Table 6-5 WebLogic Tuxedo Connector Conversational Communication Events

Event	Received by	Description
TPEV_DISCONIMM	Tuxedo tprecv, tpsend, tpreturn	The connection has been torn down and no further communication is possible. The JATMI tpdiscon posts this event in the originator of the connection. The originator sends it to all open connections when tpreturn is called. Connections are closed in a disorderly manner and if a transaction exists, it is aborted.
	JATMItprecv, tpsend, return	The connection has been torn down and no further communication is possible. The Tuxedo tpdiscon posts this event in the originator of the connection. The originator sends it to all open connections when return is called. Connections are closed in a disorderly manner and if a transaction exists, it is aborted.
TPEV_SVCERR	Tuxedo tpsend or JATMI tpsend	Received by the originator of the connection indicating that the subordinate program issued a tpreturn (Tuxedo) or return (JATMI) and ended without control of the connection.
	Tuxedo tprecy or JATMI tprecy	Received by the originator of the connection indicating that the subordinate program issued a successful tpreturn (Tuxedo) or a successful return (JATMI) without control of the connection, but an error occurred before the call completed.
TPEV_SVCSUCC	Tuxedo tprecv	Received by the originator of the connection, indicating that the subordinate service finished successfully; that is, return was successfully called.
	JATMI tprecv	Received by the originator of the connection, indicating that the subordinate service finished successfully; that is, tpreturn was called with TPSUCCESS.

6-9

Table 6-5 WebLogic Tuxedo Connector Conversational Communication Events

Event	Received by	Description
TPEV_SVCFAIL	Tuxedo tpsend or JATMI tpsend	Received by the originator of the connection indicating that the subordinate program issued a tpreturn (Tuxedo) or return (JATMI) and ended without control of the connection. The service completed with status of TPFAIL or TPEXIT and the data is set to null.
	Tuxedo tprecv or JATMI tprecv	Received by the originator of the connection indicating that the subordinate program finished unsuccessfully. The service completed with status of TPFAIL or TPEXIT.

WebLogic Tuxedo Connector Conversation Guidelines

Use the following guidelines while in conversation mode to insure successful completion of a conversation:

- Use the JATMI conversational primitives as defined in the WebLogic Tuxedo Connector Conversation interface and ApplicationToMonitorInterface interface.
 - Always use a flag.
 - Only use flags defined in the WebLogic Tuxedo Connector JATMI.
- WebLogic Tuxedo Connector does not have a parameter that can be used to limit the number of simultaneous conversations to prevent overloading the WebLogic Server network.
- If Tuxedo exceeds the maximum number of possible conversations (defined by the MAXCONV parameter), TPEV_DISCONIMM is the expected WebLogic Tuxedo Connector exception value.
- A tprecv to an unauthorized Tuxedo service results in a TPEV_DISCONIMM exception value.
- If a WebLogic Tuxedo Connector client is connected to a Tuxedo conversational service which does tpforward to another conversational service, TPEV_DISCONIMM is the expected WebLogic Tuxedo Connector exception value.

- Conversations may be initiated within a transaction. Start the conversation as part of the program statements in transaction mode. For more information on transactions, see "WebLogic Tuxedo Connector JATMI Transactions" on page 5-1.
- If a WebLogic Tuxedo Connector remote domain experiences a TPENOENT, the remote domain will send back a disconnect event message and be caught on the WebLogic Tuxedo Connector application tprecv as a TPEV_DISCONIMM exception.





Using FML with WebLogic Tuxedo Connector

The following sections discuss the Field Manipulation Language (FML) and describe how the WebLogic Tuxedo Connector uses FML.

- Overview of FML
- The WebLogic Tuxedo Connector FML API
- FML Field Table Administration
- tBridge XML/FML32 Translation

Overview of FML

Note: For more information about using FML, see Programming a BEA Tuxedo Application Using FML at http://e-docs.bea.com/tuxedo/tux80/atmi/fml01.htm.

FML is a set of java language functions for defining and manipulating storage structures called fielded buffers. Each fielded buffer contains attribute-value pairs in fields. For each field:

- The attribute is the field's identifier.
- The associated value represents the field's data content.
- An occurrence number.

There are two types of FML:

• FML16 based on 16-bit values for field lengths and identifiers. It is limited to 8191 unique fields, individual field lengths of 64K bytes, and a total fielded buffer size of 64K bytes.

• FML32 based on 32-bit values for the field lengths and identifiers. It allows for about 30 million fields, and field and buffer lengths of about 2 billion bytes.

The WebLogic Tuxedo Connector FML API

Note: The WebLogic Tuxedo Connector implements a subset of FML functionality. For more information regarding FML32, refer to "FML32 Considerations."

The FML application program interface (API) is documented in the weblogic.wtc.jatmi package included in the Javadocs for WebLogic Server Classes.

FML Field Table Administration

Field tables are generated in a manner similar to Tuxedo field tables. The field tables are text files that provide the field name definitions, field types, and identification numbers that are common between the two systems. To interoperate with a Tuxedo system using FML, the following steps are required:

1. Copy the field tables from the Tuxedo system to WebLogic Tuxedo Connector environment.

For example: Your Tuxedo distribution contains a bank application example called bankapp. It contains a file called bankflds that has the following structure:

```
#Copyright (c) 1990 Unix System Laboratories, Inc.
#All rights reserved
#ident "@(#) apps/bankapp/bankflds
                                        $Revision: 1.3 $"
# Fields for database bankdb
                               number
# name
                                       type
                                               flags
                                                       comments
ACCOUNT_ID
                              110
                                       long
                               112
ACCT_TYPE
                                       char
ADDRESS
                               109
                                       string -
```

2. Converted the field table definition into Java source files. Use the mkfldclass utility supplied in the weblogic.wtc.jatmi package. This class is a utility function that reads a FML32 Field Table and produces a Java file which implements the FldTbl interface. There are two instances of this utility:

```
- mkfldclass
```

⁻ mkfldclass32

Use the correct instance of the command to convert the bankflds field table into FML32 java source. The following example uses mkfldclass.

```
java weblogic.wtc.jatmi.mkfldclass bankflds
```

The resulting file is called bankflds.java and has the following structure:

```
import java.io.*;
import java.lang.*;
import java.util.*;
import weblogic.wtc.jatmi.*;

public final class bankflds
        implements weblogic.wtc.jatmi.FldTbl
{
        /** number: 110 type: long */
        public final static int ACCOUNT_ID = 33554542;
        /** number: 112 type: char */
        public final static int ACCT_TYPE = 67108976;
        /** number: 109 type: string */
        public final static int ADDRESS = 167772269;
        /** number: 117 type: float */
.
```

3. Compile the resulting bankflds. java file using the following command:

```
javac bankflds.java
```

The result is a bankflds.class file. When loaded, the WebLogic Tuxedo Connector uses the class file to add, retrieve and delete field entries from an FML32 field.

- 4. Add the field table class file to your application CLASSPATH.
- 5. Update your WTCServer MBean.
 - Update the WTCResources MBean to reflect the fully qualified location of the field table class file.
 - Use the keywords required to describe the FML buffer type: fml16 or fml32.

- You can enter multiple field table classes in a comma separated list.

For example:

```
<WTCResources
FldTbl16Classes="my.bankflds,your.bankflds,more.bankflds"
Name="BankappResources"/>
```

6. Restart your WebLogic Server to load the field table class definitions.

Using the DynRdHdr Property for mkfldclass32 Class

WebLogic Tuxedo Connector provides a property that provides an alternate method to compile FML tables. You may need to use the DynRdHdr utility if:

- You are using very large FML tables and the . java method created by the mkfldclass32 class exceeds the internal Java Virtual Machine limit on the total complexity of a single class or interface.
- You are using very large FML tables and are unable to load the class created when compiling the . java method.

Use the following steps to use the DynRdHdr property when compiling your FML tables:

1. Convert the field table definition into Java source files.

```
java -DDynRdHdr=Path_to_Your_FML_Table weblogic.wtc.jatmi.mkfldclass32
userTable
```

The arguments for this command are defined as follows:

Attribute	Description
-DDynRdHdr	WebLogic Tuxedo Connector property used to compile an FML table.
Path_to_Your_FM L_Table	Path name of your FML table. This may be either a fully qualified path or a relative path that can be found as a resource file using the server's CLASSPATH.
weblogic.wtc.ja tmi.mkfldclass3	This class is a utility function that reads an FML32 Field Table and produces a Java file which implements the FldTbl interface.

Attribute	Description
userTable	Name of the . java method created by the mkfldclass32 class .

2. Compile the *userTable* file using the following command:

javac userTable.java

- 3. Add the userTable.class file to your application CLASSPATH.
- 4. Update the WTCResources MBean to reflect the fully qualified location of the userTable.class file.
- Target your WTCServer. The userTable.class is loaded when the WTCServer service starts.

Once you have created the <code>userTable.class</code> file, you can modify the FML table and deploy the changes without having to manually create an updated <code>userTable.class</code>. When the WTC Service is started, Weblogic Tuxedo Connector will load the updated FML table using the location specified in the Resources tab of your WTC service configuration. If the <code>Path_to_Your_FML_Table</code> attribute changes, you will need to use the preceding procedure to update your <code>userTable.java</code> and <code>userTable.class</code> files.

tBridge XML/FML32 Translation

Note: The data type specified must be FLAT or NO. If any other data type is specified, the redirection fails.

The TranslateFML element of the WTCtBridgeRedirect MBean is used to indicate if FML32 translation is performed on the message payload. There are two types of FML32 translation: FLAT and NO.

FI AT

The message payload is translated using the WebLogic Tuxedo Connector internal FML32/XML translator. Fields are converted field-by-field values without knowledge of the message structure (hierarchy) and repeated grouping.

In order to convert an FML32 buffer to XML, the tBridge pulls each instance of each field in the FML32 buffer, converts it to a string, and places it within a tag consisting of the field name. All of these fields are placed within a tag consisting of the service name. For example, an FML32 buffer consisting of the following fields:

NAME JOE

ADDRESS CENTRAL CITY

PRODUCTNAME BOLT
PRICE 1.95
PRODUCTNAME SCREW
PRICE 2.50

The resulting XML buffer would be:

```
<FML32>
  <NAME>JOE</NAME>
  <ADDRESS>CENTRAL CITY</ADDRESS>
  <PRODUCTNAME>BOLT</PRODUCTNAME>
  <PRODUCTNAME>SCREW</PRODUCTNAME>
  <PRICE>1.95</PRICE>
  <PRICE>2.50</PRICE>
</FML32>
```

NO

No translation is used. The tBridge maps a JMS TextMessage into a Tuxedo TypedBuffer (TypedString) and vice versa depending on the direction of the redirection. JMS BytesMessage are mapped into Tuxedo TypedBuffer (TypedCarray) and vice versa.

FML32 Considerations

Remember to consider the following information when working with FML32:

- For XML input, the root element is required but ignored.
- For XML output, the root element is always <FML32>.
- The field table names must be loaded as described in "FML Field Table Administration" on page 7-2.
- The tBridge translator is capable of only "flat" or linear grouping. This means that information describing FML32 ordering is not maintained, therefore buffers that contain a series of repeating data could be presented in an unexpected fashion. For example, consider a FML32 buffer that contains a list of parts and their associated price. The expectation would be PART A, PRICE A, PART B, PRICE B, etc. however since there is no structural group information contained within the tBridge, the resulting XML could be PART A, PART B, etc., PRICE A, PRICE B, etc.

- When translating XML into FML32, the translator ignores blank values. For example, <STRING></STRING> is skipped in the resulting FML32 buffer.
- Embedded FML is not supported in this release.
- Embedded VIEW fields within FML32 buffers are not supported.
- TypedCArray is not supported for FML to XML conversion. Select from the following list of supported field types:
 - SHORT
 - LONG
 - CHAR
 - FLOAT
 - DOUBLE
 - STRING
 - INT (FML32)
 - DECIMAL (FML32)
- If you have TypedCArray in your FML, encode to TypedString and decode the XML to TypedCArray.
- If you need to pass binary data, encode to a field type of your choice and decode the XML on the receiving side.



WebLogic Tuxedo Connector JATMI VIEWs

The following sections provide information about how to use WebLogic Tuxedo Connector VIEW buffers:

- Overview of WebLogic Tuxedo Connector VIEW Buffers
- How to Create a VIEW Description File
- How to Use the viewi Compiler
- How to Pass Information to and from a VIEW Buffer
- How to Use VIEW Buffers in JATMI Applications

Overview of WebLogic Tuxedo Connector VIEW Buffers

Note: For more information on Tuxedo VIEW buffers, see Using a VIEW Typed Buffer at http://e-docs.bea.com/tuxedo/tux81/pgc/pgbuf.htm#1262459.

WebLogic Tuxedo Connector allows you to create a Java VIEW buffer type analogous to a Tuxedo VIEW buffer type derived from an independent C structure. This allows WebLogic Server applications and Tuxedo applications to pass information using a common structure. WebLogic Tuxedo Connector VIEW buffers do not support FML VIEWs or FML VIEWs/Java conversions.

How to Create a VIEW Description File

Note: fbname and null fields are not relevant for independent Java and C structures and are ignored by the Java and C VIEW compiler. You must include a value (for example, a dash) as a placeholder in these fields.

Your WebLogic Server application and your Tuxedo application must share the same information structure as defined by the VIEW description. The following format is used for each structure in the VIEW description file:

```
$ /* VIEW structure */
VIEW viewname
type cname fbname count flag size null
```

where

- The file name is the same as the VIEW name.
- You can have only one VIEW description per file.
- The VIEW description file is the same file used for both the WebLogic Tuxedo Connector viewj compiler and the Tuxedo viewc compiler.
- viewname is the name of the information structure.
- You can include a comment line by prefixing it with the # or \$ character.
- The following table describes the fields that must be specified in the VIEW description file for each structure.

Table 8-1 VIEW Description File Fields

Field	Description
type	Data type of the field. Can be set to short, long, float, double, char, string, carray, or dec_t (packed decimal).
cname	Name of the field as it appears in the information structure.
fbname	Ignored.
count	Number of times field occurs.

Table 8-1 VIEW Description File Fields

Field	Description
flag	 Specifies any of the following optional flag settings: N—zero-way mapping C—generate additional field for associated count member (ACM) L—hold number of bytes transferred for STRING and CARRAY
size	For STRING and CARRAY buffer types, specifies the maximum length of the value. This field is ignored for all other buffer types.
null	User-specified NULL value, or minus sign (-) to indicate the default value for a field. NULL values are used in VIEW typed buffers to indicate empty C structure members. The default NULL value for all numeric types is 0 (0.0 for dec_t). For character types, the default NULL value is `\0'. For STRING and CARRAY types, the default NULL value is " ".
	Constants used, by convention, as escape characters can also be used to specify a NULL value. The VIEW compiler recognizes the following escape constants: \ddd (where d is an octal digit), $\0$, \n , \t , \v , \r , \t , \n ,
	You may enclose STRING, CARRAY, and char NULL values in double or single quotes. The VIEW compiler does not accept unescaped quotes within a user-specified NULL value.
	You can also specify the keyword NONE in the NULL field of a VIEW member description, which means that there is no NULL value for the member. The maximum size of default values for string and character array members is 2660 characters.

Example VIEW Description File

The following provides an example VIEW description which uses VIEW buffers to send information to and receive information from a Tuxedo application. The file name for this VIEW is infoenc.

Listing 8-1 Example VIEW Description

```
VIEW infoenc
#type cname fbname count flag size null
float amount AMOUNT 2
                                  0.0
short
     status STATUS 2
                                  0
init
             TERM 2
      term
      mychar MYCHAR 2
char
string name
             NAME 1
                             16
                             10
carray carray1 CARRAY1 1
      decimal DECIMAL 1 -
                             9
                                  - #size ignored by
dec_t
viewj/viewj32
END
```

How to Use the viewj Compiler

To compile a VIEW typed buffer, run the <code>viewj</code> command, specifying the package name and the name of the VIEW description file as arguments. The output file is written to the current directory.

To use the viewj compiler, enter the following command:

```
java weblogic.wtc.jatmi.viewj [options] [package] viewfile
```

To use the viewj32 compiler, enter the following command:

```
java weblogic.wtc.jatmi.viewj32 [options] [package] viewfile
```

The arguments for this command are defined as follows:

Argument

Description

options

• -associated_fields:

Use to set AssociatedFieldHandling to true. This allows set and get accessor methods to use the values of the associated length and count fields if they are specified in the VIEW description file. If not specified, the default value for AssociatedFieldHandling is false.

-bean_names:

Use to create set and get accessor names that follow JavaBeans naming conventions. The first character of the field name is changed to upper case before the set or get prefix is added. The signature of indexed set accessors for array fields changes from the default signature of void setAfield(T value, int index) to void setAfield(int index, T value).

• -compat names:

Use to create set and get accessor names that are formed by taking the field name from the VIEW description file and adding a set or get prefix. Provides compatibility with releases prior to WebLogic Server 8.1 SP2. Default value is -compat_names if -bean_names or -compat_names is not specified.

-modify_strings:

Use to generate different Java code for encoding strings sent to Tuxedo and decoding strings received from Tuxedo. Encoding code adds a null character to the end of each string. Decoding code truncates each string at the first null character recieved.

• -xcommon:

Use to generate output class as extending TypedXCommon instead of TypedView.

-xtype:

Use to generate output class as extending TypedXCType instead of TypedView.

Note: -compat_names and -bean_names are mutually exclusive options.

Argument	Description
package	The package name to be included in the .java source file. Example: examples.wtc.atmi.simpview
viewfile	Name of the VIEW description file. Example: Infoenc

For example:

• A VIEW buffer is compiled as follows:

java weblogic.wtc.jatmi.viewj -compat_names examples.wtc.atmi.simpview inf
oenc

• A VIEW32 buffer is compiled as follows:

java weblogic.wtc.jatmi.viewj32 -compat_names -modify_strings examples.wtc
.atmi.simpview infoenc

How to Pass Information to and from a VIEW Buffer

The output of the viewj and viewj32 command is a . java source file that contains set and get accessor methods for each field in the VIEW description file. Use these set and get accessor methods in your Java applications to pass information to and from a VIEW buffer.

The AssociatedFieldHandling flag is used to specify if the set and get methods use the values of the associated length and count fields if they are specified in the VIEW description file.

- set methods set the count for an array field and set the length for a string or carray field.
- Array get methods return an array that is at most the size of the associated count field.
- String and carray get methods return data that is at most the length of the associated length field.

Use one of the following to set or get the state of the AssociatedFieldHandling flag:

- Use the -associated_fields option for the viewj and viewj32 compiler to set the AssociatedFieldHandling flag to true..
- Invoke the void setAssociatedFieldHandling (boolean state) method in your Java application to set the state of the AssociatedFieldHandling flag.

- If false, the set and get methods ignore the length and count fields.
- If true, the set and get methods use the values of the associated length and count fields if they are specified in the VIEW description file.
- The default state is false.
- Invoke the boolean getAssociatedFieldHandling() method in your Java application to return the current state of AssociatedFieldHandling.

How to Use VIEW Buffers in JATMI Applications

Use the following steps when incorporating VIEW buffers in your JATMI applications:

- Create a VIEW description file for your application as described in How to Create a VIEW Description File.
- 2. Compile the VIEW description file as described in How to Use the view Compiler.
- 3. Use the set and get accessor methods to pass information to and recieve information from a VIEW buffer as described in How to Pass Information to and from a VIEW Buffer.
 - See the examples/wtc/atmi/simpview/ViewClient.java file in your WebLogic Server distribution for an example of how a client uses accessors to pass information to and from a VIEW buffer.
- 4. Import the output of the VIEW compiler into your source code.
- If necessary, compile the VIEW description file for your Tuxedo application and include the
 output in your C source file as described in Using a VIEW Typed Buffer at
 http://e-docs.bea.com/tuxedo/tux80/atmi/pgbuf8.htm.
- Configure a WTCServer MBean with a Resources Mbean that specifies the VIEW buffer type (VIEW or VIEW32) and the fully qualified class name of the compiled Java VIEW description file.
- 7. Build and launch your Tuxedo application.
- 8. Build and launch your WebLogic Server Application.



How to Create a Custom AppKey Plug-in

The following sections provide information about how to create custom AppKey generator plug-ins:

- How to Create a Custom Plug-In
- Example Custom Plug-in

How to Create a Custom Plug-In

Note: You cannot customize Tuxedo AAA tokens.

- Create your custom Java plug-in using the AppKey and UserRec interfaces. You can provide
 any required initialization parameters or a property file using the param parameter of the init
 method.
- 2. Compile your plug-in. Example:

```
javac exampleAppKey.java
```

3. Update your CLASSPATH to include the path to your compiled plug-in. Example:

```
export CLASSPATH=$CLASSPATH:/home/mywork
```

- 4. Start your server.
- 5. Configure your WTC Service to use the Custom Plug-in. For more information, see the Custom Plug-in at http://e-docs.bea.com/wls/docs90/wtc admin/BDCONFIG.html#custom.

Example Custom Plug-in

The exampleAppKey. java file is an example of a custom plug-in. It utilizes a tpusrfile file as the database to store the AppKey.

Listing 9-1 exampleAppKey.Java Custom Plug-In

```
import java.io.*;
import java.lang.*;
import java.util.*;
import java.security.Principal;
import weblogic.wtc.jatmi.AppKey;
import weblogic.wtc.jatmi.UserRec;
import weblogic.wtc.jatmi.DefaultUserRec;
import weblogic.wtc.jatmi.TPException;
import weblogic.security.acl.internal.AuthenticatedSubject;
import weblogic.security.WLSPrincipals;
/ * *
 * @author Copyright (c) 2002 by BEA Systems, Inc. All Rights Reserved.
/**
 * @exclude
 * Sample AppKey plug-in using TPUSRFILE as the database for APPKEY.
 * It is installed through "Custom" option.
 * The syntax for option custom plug parameter input contains the full
 * pathname to the <tpusrfile>
```

```
* @author BEA Systems, Inc.
 * /
public class exampleAppKey implements AppKey {
 private String anon_user = null;
 private String tpusrfile = null;
 private File myfile;
 private HashMap userMap;
 private long
                 1 time;
 private int dfltAppkey;
 private boolean allowAnon;
 private final static int USRIDX = 0;
 private final static int PWDIDX = 1;
 private final static int UIDIDX = 2;
 private final static int GIDIDX = 3;
 private final static int CLTIDX = 4;
 private final static byte[] tpsysadm_string = {
    (byte)'t', (byte)'p', (byte)'s', (byte)'y', (byte)'s',
    (byte) 'a', (byte) 'd', (byte) 'm' };
 private final static byte[] tpsysop_string = {
    (byte)'t', (byte)'p', (byte)'s', (byte)'y', (byte)'s', (byte)'o',
    (byte) 'p' };
 public void init(String param, boolean anonAllowed, int dfltAppKey)
    throws TPException {
```

9-3

```
if (param == null) {
  System.out.println("Error: tpusrAppKey.init@param == null");
  throw new TPException (TPException. TPESYSTEM,
                        "Invalid input parameter");
}
// get the tpusrfile name
parseParam(param);
myfile = new File(tpusrfile);
if (myfile.exists() != true) {
  System.out.println("Error: exampleAppKey.init@file \"" + param
                     + "\" does not exist");
  throw new TPException (TPException. TPESYSTEM,
                         "Failed to find TPUSR file");
}
if (myfile.isFile() != true) {
 System.out.println("Error: exampleAppKey.init@the specified name \"" +
                     param + "\" is not a file");
  throw new TPException (TPException. TPESYSTEM,
                         "Invalid TPUSR file");
}
if (myfile.canRead() != true) {
  System.out.println("Error: exampleAppKey.init@file \"" + param +
                     "\" is not readable");
  throw new TPException (TPException. TPESYSTEM,
                         "Bad TPUSR file permission");
```

```
}
   userMap = new HashMap();
   // create the cache
   if (createCache(tpusrfile) == -1) {
      System.out.println("Error: exampleAppkey.init@fail to create user
cache");
      throw new TPException (TPException. TPESYSTEM,
                            "fail to create user cache");
    }
    1_time = myfile.lastModified();
   anon_user = weblogic.security.WLSPrincipals.getAnonymousUsername();
   allowAnon = anonAllowed;
   dfltAppkey = dfltAppKey;
    System.out.println("exampleAppKey installed!");
   return;
  }
 public void uninit() throws TPException {
   if (userMap != null) {
     userMap.clear();
    }
   return;
  }
```

```
public UserRec getTuxedoUserRecord(AuthenticatedSubject subj) {
   Object[] obj = subj.getPrincipals().toArray();
   if (obj == null || obj.length == 0) {
      // a subject without principals is an anonymous user
      if (allowAnon) {
       return new DefaultUserRec(anon_user, dfltAppkey);
      }
                System.out.println("Error:
exampleAppKey.getTuxedoUserRecord@return " +
                         "anonymous user not allowed");
     return null;
    }
   // looping through all Principal names if necessary to get first user
    // name defined in tpuser file
   Principal user;
   String
              username;
    int
              key;
   UserRec
              rec;
    for (int i = 0; i < obj.length; i++) {
             = (Principal)obj[i];
     user
     username = user.getName();
      if (username.equals(anon_user)) {
       return new DefaultUserRec(anon_user, dfltAppkey);
      }
      if ((rec = (UserRec)userMap.get(username)) != null) {
```

```
return rec;
     }
    }
    System.out.println("WARN: exampleAppKey.getTuxedoUserRecord@return " +
                       "null UserRec");
   return null;
  }
 private int createCache(String fname) {
   FileInputStream fin;
   byte[]
                   line;
    try {
      fin = new FileInputStream(fname);
     while ((line = readOneLine(fin)) != null) {
        DefaultUserRec newUser = parseOneLine(line);
        if (newUser != null) {
          userMap.put(newUser.getRemoteUserName(), newUser);
        }
      }
     fin.close();
    }
   catch (FileNotFoundException fnfe) {
      System.out.println("Error: exampleAppKey.createCache@reason: " +
fnfe);
     return -1;
    }
```

```
catch (SecurityException se) {
   System.out.println("Error: exampleAppKey.createCache@reason: " + se);
   return -1;
  }
 catch (IOException ioe) {
  System.out.println("Error: exampleAppKey.createCache@reason: " + ioe);
   return -1;
  }
 catch (Exception e) {
   System.out.println("Error: exampleAppKey.createCache@reason: " + e);
   return -1;
  }
 return 0;
}
private byte[] readOneLine(FileInputStream fh) {
  int
        len = 80;
 byte[] line = new byte[len];
  int
         inp = -1;
  int
       idx = 0;
  try {
   while ((inp = fh.read()) != -1) {
      if (idx == 0 && (inp == '\n' || inp == '\0')) {
        continue;
      }
      if (inp == '\n') {
```

```
break;
      }
     if (idx == (len - 1)) {
       byte[] tmp = new byte[len + 80];
        System.arraycopy(line, 0, tmp, 0, len);
        line = tmp;
        len += 80;
     }
     line[idx] = (byte)inp;
     idx++;
    }
  }
 catch (Exception e) {
   System.out.println("Error: exampleAppKey.readOneLine@reason: " + e);
   return null;
  }
  if (inp == -1 && idx == 0)
   return null;
  }
 byte[] tmp = new byte[idx];
 System.arraycopy(line, 0, tmp, 0, idx);
 return tmp;
}
```

```
private DefaultUserRec parseOneLine(byte[] line) {
 String
             name;
  int
             key = 0;
 DefaultUserRec usr;
  int
             firstCharacter;
  int
            i;
  int
            sidx;
  int
           fldlen;
  int
            fn;
 byte[]
             buid = null;
 byte[]
             bgid = null;
 byte[]
             clt = null;
 byte[]
             uname = null;
  firstCharacter = (int)line[0];
  if (firstCharacter == '#' || firstCharacter == '\n' ||
      firstCharacter == '!' || firstCharacter == '\0' ||
     firstCharacter == '\r') {
   return null;
  }
  fldlen = 0;
  sidx = 0;
  for (i = 0, fn = 0; i < line.length && fn <= CLTIDX; i++) {
   if (line[i] == (byte)':') {
     switch (fn) {
     case USRIDX:
       uname = new byte[fldlen];
```

```
System.arraycopy(line, sidx, uname, 0, fldlen);
  break;
case UIDIDX:
  buid = new byte[fldlen];
  System.arraycopy(line, sidx, buid, 0, fldlen);
  break;
case GIDIDX:
  bgid = new byte[fldlen];
  System.arraycopy(line, sidx, bgid, 0, fldlen);
  break;
case CLTIDX:
                 if (line[sidx ] == (byte)'T' &&
                          line[sidx+1] == (byte)'P' &&
                          line[sidx+2] == (byte)'C' &&
                          line[sidx+3] == (byte)'L' &&
                          line[sidx+4] == (byte)'T' &&
                          line[sidx+5] == (byte)'N' &&
                          line[sidx+6] == (byte)'M' &&
                          line[sidx+7] == (byte)',') {
                        sidx
                              += 8;
                        fldlen -= 8;
                 }
  if (fldlen > 0) {
                         clt = new byte[fldlen];
                      System.arraycopy(line, sidx, clt, 0, fldlen);
  }
  break;
```

```
default:
     break;
    } // end of switch
    fn++;
    fldlen = 0;
    sidx = i + 1;
  } // end of if
  else {
    fldlen++;
  }
}
// try to tolerate incomplete line
if (fn <= CLTIDX && fldlen > 0) {
             switch (fn) {
              case USRIDX:
                     uname = new byte[fldlen];
                     System.arraycopy(line, sidx, uname, 0, fldlen);
                     break;
              case UIDIDX:
                     buid = new byte[fldlen];
                     System.arraycopy(line, sidx, buid, 0, fldlen);
                     break;
              case GIDIDX:
                     bgid = new byte[fldlen];
                     System.arraycopy(line, sidx, bgid, 0, fldlen);
                     break;
```

```
case CLTIDX:
                     if (line[sidx ] == (byte)'T' &&
                              line[sidx+1] == (byte)'P' &&
                              line[sidx+2] == (byte)'C' &&
                              line[sidx+3] == (byte)'L' &&
                              line[sidx+4] == (byte)'T' &&
                              line[sidx+5] == (byte)'N' &&
                              line[sidx+6] == (byte)'M' &&
                              line[sidx+7] == (byte)',') {
                                   += 8;
                            sidx
                            fldlen -= 8;
                     }
                     clt = new byte[fldlen];
                     System.arraycopy(line, sidx, clt, 0, fldlen);
                     break;
             }
}
if (uname == null || buid == null || bgid == null) {
  return null;
}
name = new String(uname);
if (clt != null) {
  if (Arrays.equals(tpsysadm_string, clt) == true) {
    key = TPSYSADM_KEY;
  }
```

```
key = TPSYSOP_KEY;
      }
    }
    if (key == 0) {
      Integer u_val;
      Integer g_val;
      int uid = 0;
      int gid = 0;
      try {
        u_val = new Integer(new String(buid));
        g_val = new Integer(new String(bgid));
        uid = u_val.intValue();
        gid = g_val.intValue();
        uid &= UIDMASK;
        gid &= GIDMASK;
        key = uid | (gid << GIDSHIFT);</pre>
      }
      catch (NumberFormatException nfe) {
        System.out.println("Error: exampleAppKey.readOneLine@reason: " +
nfe);
        return null;
      }
    }
    return new DefaultUserRec(name, key);
```

else if (Arrays.equals(tpsysop_string, clt) == true) {

```
private void parseParam(String param) {
   String str;

   // trim the input
   tpusrfile = param.trim();

   return;
}
```



Application Error Management

The following sections provide mechanisms to manage and interpret error conditions in your applications:

- Testing for Application Errors
- WebLogic Tuxedo Connector Time-Out Conditions
- Guidelines for Tracking Application Events

Testing for Application Errors

Note: To view an example that demonstrates how to test for error conditions, see "Example Transaction Code" on page 5-5.

Your application logic should test for error conditions after the calls that have return values and take suitable steps based on those conditions. In the event that a function returned a value, you may invoke a functions that tests for specific values and performs the appropriate application logic for each condition.

Exception Classes

The WebLogic Tuxedo Connector throws the following exception classes:

- Ferror: Exception thrown for errors occurring while manipulating FML.
- TPException: Exception thrown that represents a TPException failure.

• TPReplyException: Exception thrown that represents a TPException failure when user data is associated with the exception thrown.

Fatal Transaction Errors

In managing transactions, it is important to understand which errors prove fatal to transactions. When these errors are encountered, transactions should be explicitly aborted on the application level by having the initiator of the transaction call commit(). Transactions fail for the following reasons:

- The initiator or participant of the transaction caused it to be marked for rollback.
- The transaction timed out.
- A commit() was called by a participant rather than by the originator of a transaction.

WebLogic Tuxedo Connector Time-Out Conditions

There are two types of time-out which can occur when using the WebLogic Tuxedo Connector:

- Blocking time-out.
- Transaction time-out.

Blocking vs. Transaction Time-out

Blocking time-out is exceeding the amount of time a call can wait for a blocking condition to clear up. Transaction time-out occurs when a transaction takes longer than the amount of timed defined for it in setTransactionTimeout(). By default, if a process is not in transaction mode, blocking time-outs are performed. When the *flags* parameter of a a communication call is set to TPNOTIME, it applies to blocking time-outs only. If a process is in transaction mode, blocking time-out and the TPNOTIME flag are not relevant. The process is sensitive to transaction time-out only as it has been defined for it when the transaction was started. The implications of the two different types of time-out follow:

- If a process is not in transaction mode and a blocking time-out occurs on an asynchronous call, the communication call that blocked will fail, but the call descriptor is still valid and may be used on a re-issue call. Further communication in general is unaffected.
- In the case of transaction time-out, the call descriptor to an asynchronous transaction reply (done without the TPNOTRAN flag) becomes stale and may no longer be referenced. The

only further communication allowed is the one case described earlier of no reply, no blocking, and no transaction.

Effect on commit()

The state of a transaction if time-out occurs after the call to <code>commit()</code> is undetermined. If the transaction timed out and the system knows that it was aborted, <code>setRollbackOnly()</code> or <code>rollback()</code> returns with an error.

If the state of the transaction is in doubt, you must query the resource to determine if any of the changes that were part of that transaction have been applied to it in order to discover whether the transaction committed or aborted.

Effect of TPNOTRAN

Note: A transaction can time-out while waiting for a reply that is due from a service that is not part of that transaction.

When a process is in transaction and makes a communications call with *flags* set to TPNOTRAN, it prohibits the called service from becoming a participant of that transaction. The success or failure of the service does not influence the outcome of that transaction.

Guidelines for Tracking Application Events

You can track the execution of your applications by using System.out.println() to write messages to the WebLogic Server trace log. Create a log() method that takes a variable of type String and use the variable name as the argument to the call, or include the message as a literal within quotation marks as the argument to the call. In the following example, a series of messages are used to track the progress of a tpcall().

Listing 10-1 Example Event Logging

```
.
.
.
log("About to call tpcall");
    try {
        myRtn = myTux.tpcall("TOUPPER", myData, 0);
```

```
}
       catch (TPReplyException tre) {
              log("tpcall threw TPReplyExcption " + tre);
              throw tre;
       }
       catch (TPException te) {
              log("tpcall threw TPException " + te);
              throw te;
       }
       catch (Exception ee) {
              log("tpcall threw exception: " + ee);
              throw new TPException(TPException.TPESYSTEM, "Exception: " +
ee);
       }
       log("tpcall successfull!");
private static void
log(String s)
{
       System.out.println(s);}
```