
NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

CCNA ITN Lab 3

Names: Shanjida,

Team-No.: 04 Rubaiya, Febin

# IPv4 Subnetting and Routing Secure SSH Connection and Device Security TCP, UDP, DNS



# **Lab Preparations**

ITN Assessments: Modules 14 - 15: Network Application Communications Exam

Modules 16 - 17: Building and Securing a Small Network Exam

(By the ITN Module Group Exams 1-17 you exercise for the ITN

Final Exam.)

NP Course: NP Chapter 4-7

Re-Call Cisco IOS Commands (prepare for the ITN Skill Test)

**IPv4** Subnetting and Summary Routes

## **Lab Instructions**

Task 1 - IPv4 Network and Static Routes Task 2 - Accessing Network Devices with SSH Task 3 - Securing Network Devices Task4 - Observe the TCP 3-Way Handshake, UDP, and DNS

## **Deliverables and List of Due Dates**

Write your answers in red color. You may use the comment capabilities of the free Adobe reader.

# **Preparation**

## Part 1: Recall for the ITN Skill Test: Basic Configuration Commands

- a. Read the Lab Instructions of this Lab
- b. Check the IOS Command List, provided for the Labs.
- c. Which IOS commands are necessary to configure the following tasks?
- Enter the privileged mode from startup mode. Router>enable
- Enter the configuration (EXEC) mode from terminal. Router# config t or configure terminal
- Set the hostname to R1. Router(config)# hostname R1
- Disable DNS lookup.
   R1(config)# no ip domain-lookup
- Assign class the EXEC encrypted password R1(config)# enable secret class
- Configure global password encryption. R1(config)# service password-encryption
- Return from configuration (EXEC) mode: R1(config)# end
- Assign cisco the console password and enforce login and set logging synchronous to prevent console messages from interrupting command entry.

R1(config)# line con 0

R1(config-line) # password cisco

R1(config-line) # login

R1(config-line) # logging synchronous

R1(config-line) # exit

Use vty (Telnet) lines 0-4, assign cisco as the vty (Telnet) password and enforce login.
 R1(config)# line vty 0 4

R1(configline) # password cisco

R1(config-line) # login

R1(configline) # exit

- Create a banner that will warn anyone accessing the device that unauthorized access is prohibited.

R1(config)# banner motd # unauthorized access is prohibited #

- Save the running configuration to the startup configuration file.

R1(config)# copy running-config startup-config

- Display the running configuration. R1(config)# show running-config or sh run
- Display the status of all interfaces in brief. R1(config)#show ip interface brief
   or sh ip int br

#### Part 2: Calculate IPv4 Subnets

#### Step 1: Network Topology A

The 10.10.10.0/24 network address is used to provide the addresses in the network. Determine the number of subnets in Network Topology A.

a. How many subnets are there? 9 b. The Inter-Router links have no other hosts connected. Which subnet mask should be used? 50/1/0 255.255.255.252 The LANs connected to c. 50/0/1 the switches have the different host numbers. Which subnet mask are valid for these LANs? 50/0/0 S1: 10 hosts mask: 255.255.255.240/28 50/0/0 G0/1 S2: 27 hosts mask: 255.255.255.224/27 G0/1 S3: 48 hosts mask: **255.255.255.192/26** 


- d. Record the subnet information.
- Derive the subnets from the largest subnet to the smallest subnet.
- Name the LAN subnets according to their switch number Sx Name the Inter-Router subnets Rx-Ry

Subnet	Subnet Address	First Usable Host Address	Last Usable Host Address	Broadcast Address
LAN3/26	10.10.10.0/26	10.10.10.1	10.10.10.62	10.10.10.63
LAN2/27	10.10.10.64/27	10.10.10.65	10.10.10.96	10.10.10.97
LAN1/28	10.10.10.98/28	10.10.10.99	10.10.10.112	10.10.10.113
R3-R2	10.10.10.114/30	10.10.10.115	10.10.10.116	10.10.10.117
R3-R1	10.10.10.118/30	10.10.10.119	10.10.10.120	10.10.10.121
R1-R2	10.10.10.122/30	10.10.10.123	10.10.10.124	10.10.10.125
R3-R4	10.10.10.126/30	10.10.10.127	10.10.10.128	10.10.10.129
R2-R4	10.10.10.130/30	10.10.10.131	10.10.10.132	10.10.10.133
R1-R4	10.10.10.134/30	10.10.10.135	10.10.10.136	10.10.10.137

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

#### Step 2: Network Subnetting

Given is the following simple network without any Internet access.



Available is the IP address range 192.168.100.0 / 24. Subnet the network to provide 60 host addresses per subnet while wasting the fewest address in table 1.

Subnet	Subnet Address	First Usable Host Address	Last Usable Host Address	Broadcast Address
1	192.168.100.0	192.168.100.1	192.168.100.62	192.168.100.63
2	192.168.100.64	192.168.100.65	192.168.100.126	192.168.100.127
3	192.168.100.128	192.168.100.129	192.168.100.190	192.168.100.191
4	192.168.100.192	192.168.100.193	192.168.100.254	192.168.100.255

We assign the <u>third</u> subnet to the First Floor LAN. Assign the last network host address (the highest) in this subnet to the G0/0 interface of router R1 in table2.

Assign the first network host address in this subnet to the NIC interface of PC-B in table2.

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/0	192.168.100.190	255.255.255.192	no
	G0/1	192.168.100.254	255.255.255.224	no
S1	VLAN1	192.168.100.253	255.255.255.224	192.168.100.254
PC-A	NIC	192.168.100.225	255.255.255.224	192.168.100.254
PC-B	NIC	192.168.100.129	255.255.255.192	192.168.100.190

Starting with the <u>forth</u> subnet of table 1, subnet this network again so that the new subnets will provide 28 host addresses per subnet while wasting the fewest addresses in table3.

Subnet	Subnet Address	First Usable Host Address	Last Usable Host Address	Broadcast Address
4 <sup>th</sup> -1	192.168.100.192	192.168.100.193	192.168.100.222	192.168.100.223
4 <sup>th</sup> -2	192.168.100.224	192.168.100.225	192.168.100.254	192.168.100.255


Assign the second of these new 28-host subnets to the Second Floor LAN. Assign the last network host address (the highest) in the Second Floor LAN subnet to the G0/1 interface of router R1 in table2.

Assign the second to the last address (the second highest) in this subnet to the VLAN 1 interface of the Second Floor Switch in table2.

Assign the first address in this subnet to the NIC interface of PC-A in table2.

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

## Part 3: Calculating IPv4 Summary Routes



## **Addressing Table**

Subnet	Subnet IPv4 Address		Subnet	IPv4 Address
HQ LAN1	192.168.64.0/23		WEST LAN1	192.168.70.0/25
HQ LAN2 192.168.66.0/23			WEST LAN2	192.168.70.128/25
			Link from HQ to EAST	192.168.71.4/30
EAST LAN1	192.168.68.0/24		Link from HQ to WEST	192.168.71.0/30
EAST LAN2	192.168.69.0/24		Link from HQ to ISP	209.165.201.0/30

Step 1: Determine the summary route for HQ LAN1 and HQ LAN2

You may work step by step to the following scheme: List the HQ LAN1 and HQ LAN2 IP subnet mask in decimal form. Then List the HQ LAN1 and HQ LAN2 IP address in binary form. Finally Count the number of far left matching bits to determine the subnet mask for the summary route:

- a. How many far left matching bits are present in the two networks? 22 bits are matched
- b. List the matching binary bits for HQ subnets. 11000000.101010000 /(192.168.010000) are matching
- d. List the summarized network address in decimal form. 192.168.64.0/22

Subnet	IPv4 Address	Subnet Mask	Subnet IP Address in Binary Form
HQ LAN1	192.168.64.0/23	255.255.254.0	11000000.10101000.01000000.00000000
HQ LAN2	192.168.66.0/23	255.255.254.0	11000000.10101000.01000010.000000000
HQ LANs Summary Address	192.168.64.0/22	255.255.252.0	11000000.10101000.01000000.00000000

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

#### Step 2: Determine the summary route for EAST LAN1 and EAST LAN2

- a. How many far left matching bits are present in the two networks? 23 bits are matched
- b. Build the summarized network address 192.168.01000100.00000000=192.168.68.0/23 Matching binary bits are underlined as red.

Subnet	IPv4 Address	Subnet Mask	Subnet Address in Binary Form
EAST LAN1	192.168.68.0/24	255.255.255.0	11000000.10101000.01000100.00000000
EAST LAN2	192.168.69.0/24	255.255.255.0	11000000.10101000.0100010 <mark>1.00000000</mark>
EAST LANs Summary Address	192.168.68.0/23	255.255.254.0	11000000.10101000.01000100.00000000

#### Step 3: Determine the summary route for WEST LAN1 and WEST LAN2

- a. How many far left matching bits are present in the two networks? 24
- b. Build the summarized network address

192.168.<u>01000110</u>.00000000= 192.168.70.0/24

Subnet	IPv4 Address	Subnet Mask	Subnet IP Address in Binary Form
WEST LAN1	192.168.70.0/25	255.255.255.128	11000000.10101000.01000110.00000000
WEST LAN2	192.168.70.128/25	255.255.255.128	11000000.10101000.01000110.10000000
WEST LANs Summary Address	192.168.70.0/24	255.255.255.0	11000000.10101000.01000110.00000000


## Step 4: Determine the summary routes for HQ, EAST and WEST

- a. List the matching binary bits for HQ, EAST, and WEST subnets. 11000000.10101000.01000
- b. Add zeros to comprise the remainder of the network address in binary form. 000.00000000
- List the summarized network address in decimal form.
   Summarized network address = 192.168.010001\_00.00000000=192.168.64.0/22

Subnet	IPv4 Address	Subnet Mask	Subnet IP Address in Binary Form
HQ	192.168.64.0/22	255.255.255.252	11000000.10101000.01000000.00000000
EAST	192.168.68.0/23	255.255.254.0	11000000.10101000.01000100.00000000
WEST	192.168.70.0/24	255.255.255.0	11000000.10101000.01000110.00000000
Network Address Summary Route	192.168.64.0/22	255.255.255.252	11000000.10101000.01000000.00000000

# Task 1 – IPv4 Network and Static Routes

## **Packet Tracer Topology**



## **Addresing Table**

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/0/0	10.0.2.1	255.255.255.0	N/A
	G0/0/1	10.0.1.1	255.255.255.0	N/A
	G0/0/2	172.16.0.1	255.255.255.252	N/A
S1	VLAN 1	10.0.1.2	255.255.255.0	10.0.1.1
R2	G0/0/0	172.16.0.2	255.255.255.252	N/A
	G0/0/1	192.168.20.1	255.255.255.0	N/A
	G0/0/2	192.168.10.1	255.255.255.0	N/A
PC-A	NIC	10.0.1.10	255.255.255.0	10.0.1.1
PC-B	NIC	10.0.2.20	255.255.255.0	10.0.2.1
PC-C	NIC	192.168.10.30	255.255.255.0	192.168.10.1
PC-D	NIC	192.168.20.40	255.255.255.0	192.168.20.1

# Part 1: Set Up Network Topology and Initialize Devices

## Step 1: Build topology in Packet Tracer.

**COVID-19 Version:** Build topology in **Packet Tracer**. Use and re-label the following devices:

- a. Build the network with ISR4331 routers, 2960 switches, and PCs in Packet Tracer. Rename the devices.
- b. Implement a 3<sup>rd</sup> Gigabit Ethernet interface GLC-T SFP in slot G0/0/2 in each ISR 4331 router.





NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

## Part 2: Router R1 Settings

#### Step 1: Perform basic Router configurations

Access router R1 through the Serial Console Port and Desktop Terminal of PC-B

- Assign a device name R1 to the router Router(config)# hostname R1
- Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands as though they were host names **R1(config)# no ip domain-lookup**

#### Step 2: Secure access lines and basic device security

- Assign class as the privileged EXEC secret R1(config)# enable secret class
- Create a banner that warns anyone accessing the device that unauthorized access is prohibited
   R1(config)# banner motd # unauthorized access is prohibited #
- Assign cisco as the console password and enable login

R1(config)# line con 0
R1(config-line) # password cisco
R1(config-line) # login

- Assign cisco the Telnet (VTY) password for 5 lines and enable login

R1(config)# line vty 0 4
R1(config-line) # password cisco
R1(config-line) # login

Encrypt the clear text passwords in the configuration file
 R1(config)# service password-encryption

#### Step 3: Configure and activate router interfaces

d. Configure and activate interface g0/0/0 with IP address, mask and description

R1(config)# interface g0/0/0
R1(config-if)# description Connected to PC-B
R1(config-if)# ip address 10.0.2.1 255.255.255.0
R1(config-if)# no shutdown

e. Configure and activate interface g0/0/1 with IP address, mask and description

R1(config)# interface g0/0/1
R1(config-if)# description Connected to S1
R1(config-if)# ip address 10.0.1.1 255.255.255.0
R1(config-if)# no shutdown

f. Configure and activate interface g0/0/2 with IP address, mask and description

R1(config)# interface g0/0/2
R1(config-if)# description Connected to R2
R1(config-if)# ip address 172.16.0.1 255.255.252
R1(config-if)# no shutdown

#### Step 4: Test LAN A and LAN B Connectivity

Assign static IP address, network mask and default gateway to PC-A and PC-B. Done

- From PC-A ping switch S1. Successful (y/n) yes
- Test PC-A to PC-B connectivity by ping. Successful (y/n) yes

**Note:** Remove errors and reconfigure network in case of no connectivity.

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

## Part 3: Router R2 Settings

#### **Step 1:** Perform basic Router configurations

Access router R2 through the Serial Console Port and Desktop Terminal of PC-C

- Assign a device name R2 to the router Router(config)# hostname R2
- Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands as though they were host names R2(config)# no ip domain-lookup

#### Step 2: Secure access lines and basic device security

- Assign class as the privileged EXEC secret R2(config)# enable secret class
- Create a banner that warns anyone accessing the device that unauthorized access is prohibited
   R2(config)# banner motd # unauthorized access is prohibited #
- Assign cisco as the console password and enable login

```
R2(config)# line con 0
R2(config-line) # password cisco
R2(config-line) # login
```

- Assign cisco the Telnet (VTY) password for 5 lines and enable login

```
R2(config)# line vty 0 4
R2(config-line) # password cisco
R2(config-line) # login
```

Encrypt the clear text passwords in the configuration file
 R2(config)# service password-encryption

#### Step 3: Configure and activate router interfaces

Configure and activate interface g0/0/0 with IP address, mask and description

```
R2(config)# interface g0/0/0
R2(config-if)# description Connected to R1
R2(config-if)# ip address 10.0.0.2 255.255.255
R2(config-if)# no shutdown
```

- Configure and activate interface g0/0/1 with IP address, mask and description

```
R2(config)# interface g0/0/1
R2(config-if)# description Connected to S2
R2(config-if)# ip address 10.0.20.1 255.255.255.0
R2(config-if)# no shutdown
```

Configure and activate interface g0/0/2 with IP address, mask and description

```
R2(config)# interface g0/0/2
R2(config-if)# description Connected to PC-C
R2(config-if)# ip address 10.0.10.1 255.255.255.0
R2(config-if)# no shutdown
```

#### Step 4: Test LAN C and LAN D Connectivity

- Assign static IP address, network mask and default gateway to PC-C and PC-D.
- From PC-D ping router R2 interface g0/0/2. Successful (y/n) yes
- From router R2 ping router R1 interface g0/0/2. Successful (y/n) yes
   Note: Remove errors and reconfigure network in case of no connectivity.

#### Step 5: Check Routes in Router R1

- Display routing table of router R1. Record the networks which are reachable by router R1.

```
Rl#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B -
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       NI - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
inter area
       * - candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route
Gateway of last resort is not set
     10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
        10.0.1.0/24 is directly connected, GigabitEthernet0/0/1
        10.0.1.1/32 is directly connected, GigabitEthernet0/0/1
       10.0.2.0/24 is directly connected, GigabitEthernet0/0/0
C
L
       10.0.2.1/32 is directly connected, GigabitEthernet0/0/0
     172.16.0.0/16 is variably subnetted, 2 subnets, 2 masks
C
        172.16.0.0/30 is directly connected, GigabitEthernet0/0/2
L
        172.16.0.1/32 is directly connected, GigabitEthernet0/0/2
```

- Explain, why PC-D is not reachable from PC-A: This means that PC-D is not operating on the same network.

## **Part 4: Configure Static Routes**

#### Step 1: Configure a recursive static route on R2.

With a **recursive static route**, the next-hop IP address is specified. Because only the next-hop IP is specified, the router must perform multiple lookups in the routing table before forwarding packets. The IP address is the next hop router address:

- a. Which network(s) must be configured as static routes on R2? 10.0.1.0/24 and 10.0.2.0/24
- c. Which next hop address must be used on R2?

```
R1 g0/0/2 IP address: 172.16.0.1 must be used <u>as next</u> hop address.
```

c. Configure the required LAN as **recursive static route** on R2. Record the required command.

```
PC-A LAN network address: 10.0.1.0

R2 (config) #ip route 10.0.1.0 255.255.255.0 172.16.0.1
```

## Step 2: Directly connected static route on R2.

With a directly connected static route, the *exit-interface* parameter is specified, which allows the router to resolve a forwarding decision in one lookup. A directly connected static route is typically used with a point-to-point serial interface.

a. Which network(s) must be configured as static routes on R2? same

b. Configure the PC-B LAN as **directly connected static route** on R2. Record the required command.

PC-B LAN network address: 10.0.2.0
R2(config) #ip route 10.0.2.0 255.255.255.0 172.16.0.1

#### Step 3: Static default route on R1

C.

A default route identifies the gateway to which the router sends all IP packets for which it does not have a learned or static route. A default static route is a static route with 0.0.0.0 as the destination IP address and subnet mask. This is commonly referred to as a "quad zero" route. In a default route, either the next-hop IP address (recursive static route) or exit interface (directly connected static route) can be specified.

a. Configure a static default route at R1 using the exit interface of g0/0/2. Record the required command. I have configured the R1 router with a default route using the exit interface of g0/0/2. ip route 0.0.0.0 0.0.0.0 GigabitEthernet0/0/2

#### Step 4: Verify connectivity of the LANs.

a. Display IP routing table of router R2. Is there a path to PC-A LAN (y/n)? yes

```
10.0.0.0/24 is subnetted, 2 subnets
S
        10.0.1.0/24 [1/0] via 172.16.0.1
        10.0.2.0/24 [1/0] via 172.16.0.1

▼ R2

                                                                     Physical
           Config
                   CLI
                         Attributes
                             IOS Command Line Interface
  BGP
          D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
         N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
         E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
          i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
  inter area
          * - candidate default, U - per-user static route, o - ODR
          P - periodic downloaded static route
  Gateway of last resort is not set
       10.0.0.0/24 is subnetted, 2 subnets
  S
          10.0.1.0/24 [1/0] via 172.16.0.1
  S
           10.0.2.0/24 [1/0] via 172.16.0.1
       172.16.0.0/16 is variably subnetted, 2 subnets, 2 masks
  C
           172.16.0.0/30 is directly connected, GigabitEthernet0/0/0
           172.16.0.2/32 is directly connected, GigabitEthernet0/0/0
  L
       192.168.10.0/24 is variably subnetted, 2 subnets, 2 masks
  C
           192.168.10.0/24 is directly connected, GigabitEthernet0/0/2
  L
           192.168.10.1/32 is directly connected, GigabitEthernet0/0/2
        192.168.20.0/24 is variably subnetted, 2 subnets, 2 masks
           192.168.20.0/24 is directly connected, GigabitEthernet0/0/1
           192.168.20.1/32 is directly connected, GigabitEthernet0/0/1
```

- b. From PC-A, is it possible to ping R2 interface g0/0/0 (y/n)? y
- c. From PC-A, is it possible to ping PC-C (y/n)? y
- d. From PC-D, is it possible to ping PC-A (y/n)? y

**Note:** Remove errors and reconfigure network in case of no connectivity.

NP

e. Display the routing table of router R1.


```
Rl#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B -
BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is 172.16.0.2 to network 0.0.0.0
     10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
        10.0.1.0/24 is directly connected, GigabitEthernet0/0/1
        10.0.1.1/32 is directly connected, GigabitEthernet0/0/1
        10.0.2.0/24 is directly connected, GigabitEthernet0/0/0
       10.0.2.1/32 is directly connected, GigabitEthernet0/0/0
L
     172.16.0.0/16 is variably subnetted, 2 subnets, 2 masks
C
       172.16.0.0/30 is directly connected, GigabitEthernet0/0/2
        172.16.0.1/32 is directly connected, GigabitEthernet0/0/2
L
     0.0.0.0/0 [1/0] via 172.16.0.2
```

- Which networks are routed in router R1?
   10.0.1.0/24, 10.0.2.0/24, 172.16.0.0/16 and 0.0.0.0/0
- II. How is this new static default route marked in the routing table?
  with \* mark in the router table as S\*

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

# Task 2 – Accessing Network Devices with SSH

#### **Packet Tracer Topology**



Continue with topology and addressing of Task 1.

## **Objectives**

Protocols such as Telnet do not authenticate or encrypt the information. This allows a network sniffer to intercept passwords and configuration information. Secure Shell (SSH) is a network protocol that establishes a secure terminal emulation connection. SSH encrypts all information and provides authentication of the remote computer.

## Part 1: Configure Router R2 for SSH Access

#### Step 1: Configure device authentication with crypto key.

The device name and domain are used as part in the crypto key when it is generated. Therefore, these names must be entered prior to issuing the **crypto key** command. We use **RSA** encryption with a key length of **1024 Bytes**.

a. Configure the domain for the device.

R2(config) # ip domain-name ccna-lab.com

b. Configure crypto key

R2(config)# crypto key generate rsa

The name for the keys will be: R2.ccna-lab.com

Choose the size of the key of 1024 bits.

How many bits in the modulus [512]: 1024

#### Step 2: Configure a local username stored in the local database.

The local database is used to store usernames and passwords with additional privilege levels. **Note**: A **privilege level of 15** gives the user **administrator** rights.

R2(config) # username admin privilege 15 secret adminpass

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

#### Step 3: Enable SSH on the VTY lines.

a. Enable only SSH on the **inbound** VTY lines using the **transport input** command.

```
R2(config)# line vty 0 4 R2(config-
line)# transport input ssh
```

b. Change the login method to use the **local database** for user verification and save the running configuration to the startup configuration file.

```
R2(config-line)# login
local
R2(config-line)# end
R2# copy running-config startup-config
```


Important Note: From now, access via VTY without having a local user is prohibited!!

#### Part 2: Use SSH Client to start an SSH session to the Router

#### Step 1: SSH Client

SSH is most often used to log in to a remote device and execute commands; however, it can also transfer files using the associated Secure FTP (SFTP) or Secure Copy (SCP) protocols.

- a. What is the default TCP port used for SSH sessions? 22
- b. From PC-B, start the Telnet/SSH Client from Desktop and establish an SSH connection to router R2.



#### Step 2: Administration Tasks

a. Login as administrator on R2.At login the data from local database will be used.

Record the administrator password from running-configuration.

```
username admin privilege 15 secret 5 $1$mERr$89oFbVUY9tU/mdjv3ClG3.

Which command created this representation of the admin password?


R2 (config) # username admin privilege 15 secret adminpass
```

b. Enter exit to exit the SSH session and close the SSH Client. Done

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

# **Task 3 - Securing Network Devices**

#### **Packet Tracer Topology**



Continue with topology and addressing of Task 1.

### Part 1: Basic Switch Security Measures

#### Step 1: Configure Switch S1 via Console Cable

- Access switch S1 through the Serial Console Port and Desktop Terminal of PC-A
- Provide hostname S1. Switch(config)# hostname S1
- Prevent DNS domain lookup. **S1(config)# no ip domain-lookup**

## Step 2: Secure access lines and basic device security

- Assign class as the privileged EXEC secret
- Create a banner for motto-of-the-day
   S1(config)#banner motd #Unauthorized access is denied #
- Implement terminal login (Console) and password is cisco

S1(config)# line con 0

S1(config-line) # password cisco

S1(config-line) # login

- Implement 5 Telnet lines (vty) and password is **cisco**.

S1(config)# line vty 0 4

S1(config-line) # password cisco

S1(config-line) # login

- **Encrypt** all passwords

S1(config)# service password-encryption

#### Step 3: Switch Virtual Interface

Configure and switch-on VLAN 1 interface

S1(config)# interface Vlan1

S1(config-if)# ip address 10.0.1.2 255.255.255.0

S1(config-if)# ip default-gateway 10.0.1.1

Configure the switch default gateway.

S1(config)# ip default-gateway 10.0.1.1

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

#### Step 4: Shut off unused switch ports.

Switch ports must be secured as well. Switch ports are enabled by default. Shut down all ports that are not in use on the switch. Use the **interface range** command to shut down multiple interfaces at a time. Use it for those ports, which are not in use!

```
S1(config) # interface range f0/1-4,f0/7-24,g0/1-
```

2 S1(config-if-range) # shutdown

You can verify the switch port status using the **show ip interface brief** command.

S1# show ip interface brief

Record the status of interface g0/1:



NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

#### Part 2: SSH at Switches

#### Step 1: SSH connectivity on Switch S1

On switches the same security mechanisms as on routers may be applied.

a. Configure the domain for the device.

```
S1(config) # ip domain-name ccna-lab.com
```

b. Configure crypto key

```
S1(config)# crypto key generate rsa ...
How many bits in the modulus [512]: 1024
```

c. Enable SSH on the **inbound** VTY lines and login method to use the **local database** for user verification.

```
S1(config) # username admin privilege 15 secret
adminpass S1(config) # line vty 0 4
S1(config-line) # transport input
ssh S1(config-line) # login local
S1(config-line) # end
```

#### Step 2: Test SSH connectivity to Switch S1.

- a. Open a Telnet connection from PC-A to switch S1. Does S1 accept the Telnet connection? NO
- b. Open an SSH connection from PC-A to switch S1. Does S1 accept the SSH connection? YES
- Issue the show run command.
   What indicates the configuration of SSH in the running-configuration?
   transport input ssh in line vty 0 4 (from show run)

# Part 3: Strengthen Login and Password Security

#### **Step 1:** Strengthen passwords on Router R2.

An administrator should ensure that passwords meet the standard guidelines for strong passwords. These guidelines could include mixing letters, numbers, and special characters in the password and setting a minimum length.

a. Change the privileged EXEC encrypted password to meet guidelines.

```
R2(config)# enable secret Enablep@55
```

b. Require that a minimum of 10 characters be used for all passwords.

```
R2(config) # security passwords min-length 10
```

#### Step 2: Secure the console and VTY lines by timeout and lock

You can set the router to log out of a connection that has been idle for a specified time. If a network administrator was logged into a networking device and was suddenly called away, this command automatically logs the user out after the specified time.

Prof. Dr. A. Grebe

a. The following commands cause the line to log out after five minutes of inactivity.


```
R2(config) # line console 0
R2(config-line) # exec-timeout 5 0
R2(config-line) # line vty 0 4
R2(config-line) # exec-timeout 5 0
```

b. The following command impedes brute force login attempts. The router blocks login attempts for 60 seconds if someone fails two attempts within 120 seconds. This timer is set especially low for the purpose of this lab.

```
R2(config) # login block-for 60 attempts 2 within 120
```

c. From PC-D create an SSH connection to router R2 and intentionally mistype the user and password information to see if login access is blocked after two attempts.

From your PC-C console session on the router, issue the **show login** command.



d. After the 60 seconds has expired, SSH to R2 again and login using the **admin** username and **adminpass** for the password.

From your PC-C console session, after you successfully logged in, what was displayed in the log?

```
R2#show login

A default login delay of 1 seconds is applied.
No Quiet-Mode access list has been configured.


Router enabled to watch for login Attacks.
If more than 2 login failures occur in 120 seconds or less, logins will be disabled for 60 seconds.

Router presently in Normal-Mode.
Current Watch Window

Time remaining: 69 seconds.
Login failures for current window: 0.
Total login failures: 4.
```

# Task 4 - Observe the TCP 3-Way Handshake, UDP, and DNS

#### **Topology**



Use your private PC with Internet Connectivity.

## Part 1: TCP 3-Way Handshake Analysis

#### Step 1: Retrieve the PC interface addresses.

Connect your PC to the switch on your workbench. For this lab, you need to retrieve your PC's IP address and its network interface card (NIC) physical address, also called the MAC address.

IP address	192.168.0.4
MAC address	30-5A-3A-8B-D8-AD
Default gateway IP address	192.168.0.1
DNS server IP address	192.168.0.1

#### Step 2: Start Wireshark and select the appropriate interface.

#### Step 3: Perform a website data capture.


- a. Start a data capture. Open a browser and go to www.dn.th-koeln.de.
  - Close (!) the browser window to end the HTTP session, and return to Wireshark.
  - Stop the data capture.
- b. By nslookup record the IP address of <a href="www.dn.th-koeln.de">www.dn.th-koeln.de</a>: 139.6.19.7
- c. Check the Wireshark capture window.
   Check the Source, Destination, and Protocol columns.
   Find the appropriate packet for the start of the first TCP session to the Webserver in this capture.
- d. Filter your capture to this 1st TCP Session to the www.dn.th-koeln.de Webserver.

Which Socket (IP address and Port) has been used by the webserver in the first TCP session you captured? 139.6.19.7:80

Which Socket has been used by your Web client in the first TCP session? 192.168.0.4: 61143

#### **Step 4:** Analyze TCP Segments

The image shows a TCP datagram diagram.



NP

Prof. Dr. A. Grebe

a. Which three TCP messages start the setup of a TCP session? SYN (synchronize flag), SYN-ACK (synchronizeacknowledgement flag), ACK (acknowledge flag)

Note: These messages are without any application data.

The web client initiates the TCP session. Select the 1<sup>st</sup> TCP message of a TCP session. Which flag is set in this first TCP segment? SYN flag

Record is the initial sequence number of the web client: Sequence Number: Seq No=0

b. Which TCP flags are set in the first response from the server? SYN-ACK flag

Record the sequence number and the acknowledgement number in this TCP message.

Seq No: 0 Ack No: 1

c. Which TCP flag is set in the TCP segment, to finish the TCP 3-way-handshake? ACK Flag

Record the sequence number and the acknowledgement number in this TCP message.

Seq No: 1 Ack No: 0

Important Note: in all TCP segments excluding the first segment, the ACK flag is set.

d. From the TCP 3-way-handshake packets record the initial TCP parameters maximum windows size (WIN) and maximum segment size (MSS) of the web client and the web server.

Note: By the window scale (WS) factor, the window size (WIN) is multiplied, check details of the Wirshark presentation of WS. (Answer yourself the Q: Is the DN-Webserver multiplier 7 or 128?)

TCP Option - Window scale: 7 (multiply by 128)

Parameter	Web client	Web server
MSS	1440	1380
WIN	64800	64800
WS	256	128
WIN*WS	64800*256	64800*128

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

#### Step 5: Display IP flows by Wireshark.

a. In complex scenarios it is helpful to use additional analysis by Wireshark. For our HTTP session to
 <u>www.heise.de</u> show the TCP flow graph by selecting **Statistics – Flow Graph – TCP flow,** and display
 only TCP segments of the selected flow.

By which TCP messages is TCP closed? FIN,ACK & ACK Flags

Note: In TCP closing process, the ack. number is incremented without any data transmission.

b. The web client acknowledges the received TCP segment data (number of application bytes) by TCP packets with the ACK flag and the actual acknowledgement number.

Initial HTTP client ack. number after TCP session setup (SYN, SYN/ACK, ACK): ackinitial = 1

Final HTTP client ack. number, following the last closing FIN message(s): ackfinal = 640

Calculate the number of Bytes M (TCP data = encapsulated HTTP data here), which has been received by the web **client** on application level.

 $M = ack_{final} - 1 - ack_{initial}$ 

M =640-1-0=639 BYTES

## Part 4: Examine Captured DNS and UDP Packets

#### Step 1: Continue and Examine UDP segment using DNS query.

From the same Wireshark capture, examine UDP by using a DNS query, as DNS is encapsulated in UDP. A UDP header only has four fields: source port, destination port, length, and checksum. Each field in UDP header is only 16 bits as depicted below.

	UDP SE	3MENT .	
0	16		31
80	UDP SOURCE PORT	UDP DESTINATION PORT	100
	UDP MESSAGE LENGTH	UDP CHECKSUM	
DATA			

**Note**: If you do not see any results after the DNS filter was applied, close the web browser and in the command prompt window, type **ipconfig /flushdns**.

Restart the Wireshark capture and repeat the instructions in Part 2b –2e. If this does not resolve the issue, in the command prompt window, you can type **nslookup www.google.com** as an alternative to the web browser.

a. Which client socket is used for the DNS query (IP address, transport protocol, port number)?
 socket: 192.168.0.4:56912
 transport protocol: UDP

b. Which server socket is used for the DNS query (IP address, transport protocol, port number)?
 socket: 81.173.194.77:53
 transport protocol: <u>UDP</u>

- c. Is your DNS server connected in the same subnet as your PC client? y
- d. To the MAC address of which device is the DNS query sent? c0:c5:22:eb:0f:6f
- e. In case you want to prevent your network of packet fragmentation, and the MTU size is 1500 Bytes, calculate the maximum UDP segment can be transferred.

IP Header=20 bytes

f. MTU size=1500 bytes

therefore, Maximum UDP size= 1500-20=1480 bytes

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA ITN	Introduction to Networks (ITN)	

## **Step 2:** Examine DNS responses.

a. In your own DNS capture, evaluate the DNS query response and fill out the following table for the DNS query response message.

DNS Flags / Answers	Value	Suggested Meaning
Authoritative Server Flag	0	It is a Non-authoritative name server. It does not have original source files.
Recursion desired Flag	1	Recursive request is desired
Recursion available Flag	1	Server can do recursive queries
Answer <b>Name</b>	www.google.com	
Answer <b>Type</b>	CNAME, A	
Answer Class	IN(0x0001)	
Answer <b>Time to live</b>	167 (2 minutes, 47 seconds)	
Answer <b>Address</b>	www.google.com (142.250.185.196)	

## **Deliverables**

#### **Lab Teams**

This lab may be solved in teams of max. 3 students. All teams have to upload their deliverables in time.

## **Module Group Exams**

Each team member must solve the requested Module Group Exams before delivery date.

#### **Deliverables**

Each teams uploads the following files:

- Create a PDF file ITN-Lab3-Result.pdf with the completed and answered Lab Preparations and Lab Instructions. All tasks must be worked on and all questions must be answered.
   Write your answers in red color. You may use the comment capabilities of the free Adobe reader.
- Save your final Packet Tracer file ITN-Lab3-PT.pkt
- Record the running configuration of router R1 and router R2 (show run) in one text file **ITN-Lab3-Configs.txt**

#### **Due Dates**

Group 1	Teams 1-9	Due Date
	Module Group Exams 14-15, 16-17	22.11. – EOB
	Upload Deliverables	22.11. – EOB
	CCNA ZOOM Presentation	24.11 16:45 ff.
	Final Exam / Skill Test	26.11. – 15:00 ff.

Group 2	Teams 1-9	Due Date
	Module Group Exams 14-15, 16-17	29.11 EOB
	Upload Deliverables	29.11 EOB
	CCNA ZOOM Presentation	02.12 16:45 ff.
	Final Exam / Skill Test	06.12. – 16:45 ff.

- Per team you load one solution in Ilias in time.
- Per team you book one timeslot for acceptance.